



Documentation & Quick Start



Thank you!

Thank you for choosing this pack! We hope you create something really special with it.

*Please consider rating the package through your download list or leave a review at the store page once you're familiar with it.
Feel free to give us feedback via E-Mail info@tidalflask.com or our social media!*

Your feedback helps us focus on the right updates for the future which will be free for existing users!

*Enjoy, your **Tidal Flask** team!*





Content

1. Quick Start

1. Importing to Built-in RP project
2. Importing to URP project
3. a. How to set up your project for URP (option 1)
b. How to set up your project for URP (option 2)
4. Demoscenes

2. Assets

1. Meshes
2. Textures & Materials
3. Shaders

4. Support

1. FAQ
2. Contact & Support
3. Social Media



Quick Start

Importing to Built-in RP project

After importing the Standard version into your project 2021.3.20 & above, which doesn't use any of the Scriptable render pipeline packages (URP/HDRP), it should just worktm.

If you see any warnings in the Console window, try the Clear button and/or relaunch Unity. If the warnings don't disappear consult the FAQ or drop us an e-mail.

If you see any pink assets inside the Project window or in the scenes, simply select said asset -> right click -> Reimport and it should fix it. If you still encounter pink shaders, please make sure you have the correct pack version installed and that you are using a Unity version that is compatible with the pack.

Make sure you have Post Processing installed from Unity's Package Manager. If you install it after you imported the pack, reload the demoscene to get rid of possible errors.

Importing to URP project


Here you will find detailed steps on how to import the package. Please note that this package only works out of the box with Unity 2021.3.20 and above.

IMPORTANT: In case you are using the new URP shaders with a Unity version older than 2021.3.20 please be aware that this might result in shadow cascade errors in the scene. To solve the problem you can set the Cascades option in your render pipeline asset to "No Cascades".




How to set up your project for URP (option 1)

We recommend to create a clean project and install the URP via the Package Manager or via Templates and import our package to this project. To do so follow the steps below:



Step 1: Click “NEW” to create a new project (for URP pick Unity 2021.3.20 or above).



Step 2: In the “Templates” select “Universal 3D”, this way everything you need for this package will be preinstalled.




Step 3: Download the pack from the Asset Store and install the URP version. At this point you already can go to the scenes folder and select any of the scenes.

If you see any errors in the “Console”, try the “Clear” button. If the errors don’t disappear consult the FAQ or drop us an e-mail.


Note: If the error message *“a tree couldn’t be loaded because a prefab is missing”* pops up in the console tab, simply press “Clear” in the “Console” tab and it won’t appear again. This is a known Unity bug (importing a package that has terrain and trees in it) and has nothing to do with the package.

If you see any pink assets inside the Project window or inside the “Terrain”-object in any of the scenes, simply select the said Prefabs (inside the prefabs folder) or the Meshes (inside the 3d folder) > right click > Reimport and it should fix it.

If you still encounter pink shaders, please make sure you have the correct pack version installed, depending on the render pipeline you are using.



Step 4: After the project is loaded, go to Edit > Project Settings...




Step 5: For the Scriptable Render Pipeline Settings select “URP-HighFidelity”. These are the presets Unity preinstalled with the Template.




How to set up your project for URP (option 2)


If you imported the the pack before you installed the URP please follow the steps below:




Step 1: go the Window > Package Manager.



Step 2: Select “Universal RP” asset and click “Install”.



Step 3: After the project is loaded, go to Edit > Project Settings...



Step 4: For the Scriptable Render Pipeline Settings select “URP-HighFidelity”. These are the presets Unity preinstalled with the Template.






Demo scenes

Demoscene_tree_pack_level: the scene from the trailer and screenshots

Demoscene_tree_pack_assets: in this scene you will find all the assets within the package

Quality settings for URP


To quickly adjust any quality settings for URP please find the UniversalRP-HighQuality asset inside the \Assets\Settings folder.



Example settings for shadows

Post Processing

Inside the \Story Tree Pack\Settings folder you will find a PPP_ file for the demo scene. There you can adjust the post processing to your liking.



The post processing settings.





Demoscene_tree_pack_level





Demoscene_tree_pack_assets

In this scene you will find all the assets within this package.





Assets

Meshes

Lightmap UVs

All the assets have a custom Lightmap UV in the second channel.

Textures & Materials

You can find all the textures in the \Assets\2d\textures folder. The materials are in the \Assets\materials folder.

Wood Textures


- T_wood_trunk_north_BC
- T_wood_pine_north_BC
- T_wood_pine_BC
- T_wood_maple_north_BC
- T_wood_birch_BC
- T_wood_detail_BC





Leaves Textures

- T_ENV_tree_leaves_01_BC
- T_ENV_tree_leaves_02_BC
- T_ENV_pine_north_leaves_BC
- T_ENV_maple_north_leaves_BC



Terrain

- T_CLR_green
- T_ENV_snow_01_BC





Shaders

The custom shaders were created using Amplify with Unity version 2021.3.20 and hence can **not** be opened or adjusted using Unity's Shader Graph.

Of course if you have Amplify installed, you can adjust the shaders there. The rest of the shaders are all standard URP or Built-in, depending on which render pipeline you are using.

For the foliage wind movement and the tree trunks we have included 4 shaders in this pack:

- S_foliage_wind_standard/URP_advanced_lit: Doublesided foliage shader, which has a variety of customization options.
- S_foliage_wind_standard/URP_simple_lit: A simple version of the advanced_lit shader with reduced customization options. Primarily used to improve performance.
- S_foliage_wind_standard_textureblend_lit: Doublesided foliage shader, which has a variety of customization options including an option to blend in a snow texture.
- S_two_texture_alpha_blend: An opaque shader with the option to blend in a snow texture on the wood trunks.

Tree Trunk Shader

The customizable tree trunk shader gives you the option to blend in a snow texture and brighten/darken the wood texture.



The customization options inside the tree trunk material.

Foliage shaders


The advanced wind shader is defined by the following main parts:

- Base Color/Texture: Defines texture and tint of the surface.
- Wind Movement: Defines strength, scale and direction of the wind movement.
- Ground Fade: Defines a color fade starting at the bottom of the mesh.
- Wind Tint: Creates moving highlights on the foliage
- Distance Fade: Defines a distant color fade relative to the camera position.



To customize the wind shader you have the following options:

- Base Texture: Slot for the foliage texture
- Base Tex Color Tint: Defines texture tint color
- Alpha Clip Threshold: Defines threshold of the pixels being opaque or transparent
- Shadow Received Strength: Defines the intensity of the received shadow on the mesh (URP only)
- Ground Fade Color: Defines the color used for the fade from the bottom of the asset
- Ground Fade Height: Defines the range of the ground fade
- Ground Fade Contrast: Defines ground fade contrast
- Wind Strength: Strength of the foliage deformation
- Wind Scale: Defines the density of the noise applied to the mesh
- Wind Speed: Movement direction of the noise (only edit the x and y values, z and w are not used)
- Wind Tint Opacity: Defines transparency of the wind tint color
- Wind Tint Contrast: Defines contrast of the tint color
- Wind Tint Scale: Size of the noise for the tint
- Wind Tint Speed: Direction & speed of the noise
- Distance Fade Color: Color of the distance fade
- Distance Fade Start: Defines start of the fade relative to the camera view
- Distance Fade End: Defines the end of the fade
- Distance Fade Opacity: Defines transparency of the distance fade



The customization options inside the wind material.

For the pine trees there are no wind tint and no ground fade options but additional settings for the snow blending:

- Blend Texture: Slot for the texture used for the snow blending
- Blend Texture Tiling: Defines the tiling of the snow texture
- Blend Texture Height: Defines how much of the leaf is covered by the Blend Texture
- Blend Texture Contrast: Defines visibility of the Blend Texture



Additional customization options inside the wind material for the pine trees.



Support

FAQ

Will there be updates to the package?

Yes. We plan to update all our packages as soon as there is a relevant update or if the community asks for adjustments.

Can you give support to users if something doesn't work?

Yes, but first please read through this document and if you still need help with something related to this package, feel free to contact us.

A list of errors shows up in a shader.

Try reimporting the shader (in project tab > right-click on the shader > Reimport). We are aware of some shader warnings showing up, which don't seem to actually break the shader. So simply clearing the warning in the console tab should fix the problem.

I opened the project for the first time and everything is pink. When I select a material, the shader says "Hidden/InternalErrorShader"

This is the case when your project doesn't use the same render pipeline as the pack version you installed.

I'm using Unity version older than 2021.3.20 and the scene assets have shadow errors and/or pink materials and/or the terrain isn't showing.

The URP shaders are created in Unity 2021.3.20 and are not backwards compatible. The errors is created by the shadow cascades settings in the render pipeline asset. You can set the Cascades option in your render pipeline asset to "No Cascades".



I opened the project for the first time and in the Console I get the error "A tree couldn't be loaded because the prefab is missing"

This is a known Unity bug (importing a package that has terrain and trees in it) and has nothing to do with the package. Simply press "Clear" in the "Console" tab and it won't appear again.

I imported the package but some assets still appear pink in the scene...

Make sure you installed the correct render pipeline version of our pack. After opening a scene it's still possible, that some assets are pink. If that is the case, do the following:

- In the Hierarchy window select "Terrain"
- In the "Paint Details" tab double click on any asset
- Click on the circle next to the asset which was added in the "Detail" panel
- Re-add the same asset and the scene should look normal again

I imported the package but some assets still appear pink in the Project window...

If you see any pink assets inside the Project window or inside the "Terrain"-object in any of the scenes simply select the said Prefabs (inside the prefabs folder) or the Meshes (inside the 3d folder) > right click > Reimport and it should fix it.



Contact & Support

Visit our page for updates and more packages in the future:

<https://tidalflask.com/>

Contact us if you didn't find an answer to your questions:

info@tidalflask.com

Social Media



<https://www.facebook.com/tidalflask>



<https://twitter.com/TidalFlask>



<https://www.instagram.com/tidalflask/>

