

Matsuyama PP Trip Data

2007 / Matsuyama

Overview

This dataset contains PP (Probe Person) data collected in Matsuyama City in 2007, comprising 7,810 trips gathered between February 19 and March 23, 2007.

License

Use is permitted only for the 2026 Summer Course on Behavior Modeling in Transportation Networks.

Data Column Specification

Column Name	Data Type	Description
tripID	Int64	Trip identifier.
monitorID	String	Monitor identifier.
purposeID	Int64	Purpose code: 0=--, 100=Work/School, 200=Home, 300=After work/school, 310=Working, 400=Shopping, 410=Eating, 420=Entertainment, 499=Other.
purpose	String	Recorded trip-purpose label.
DepartureTime	Datetime	Date and time in Japan Standard Time (JST, UTC +09:00).
ArrivalTime	Datetime	Date and time in Japan Standard Time (JST, UTC +09:00).
time(second)	Int64	Trip duration in seconds.
DepartureCode	Int64	Identifier code of the departure location.
DepartureName	String	Name of the departure location.
User'sDepartureName	String	Departure-location name entered by the user.

Column Name	Data Type	Description
DepartureCode_duplicated_0	Int64	Duplicated departure-location code retained from the source data.
DepartureAttribute	String	Attribute of the departure location.
DepartureLat(JGS)	Float64	Latitude in decimal degrees using the Japanese geodetic datum indicated by the column name.
DepartureLon(JGS)	Float64	Longitude in decimal degrees using the Japanese geodetic datum indicated by the column name.
DepartureLat(WGS)	Float64	Latitude in decimal degrees using the World Geodetic System (WGS 84).
DepartureLon(WGS)	Float64	Longitude in decimal degrees using the World Geodetic System (WGS 84).
GoalCode	Int64	Identifier code of the goal location.
Goal	String	Name of the goal location.
User'sGoalName	String	Goal-location name entered by the user.
GoalAttributeCode	Int64	Destination attribute code: 110=Home, 120=Office/School, 130=Office/Company, 140=Private home, 150=Department store/Mall, 160=Supermarket/Grocery store, 170=Convenience store, 180=Entertainment facility, 190=Restaurant/Cafe, 200=Book/Stationery/CD store, 210=Clothing/Goods/Sports store, 220=Electronics/Home center, 230=Barber/Hair salon, 240=Hotel/Spa/Inn, 250=Other commercial facility, 260=Financial institution/Post office, 270=Hospital, 280=Public facility, 290=Park/Roadside station, 300=Station, 310=Bus stop, 320=Airport/Ferry terminal, 999=Other.
GoalAttribute	String	Attribute of the goal location.
GoalLat(JGS)	Float64	Latitude in decimal degrees using the Japanese geodetic datum indicated by the column name.
GoalLon(JGS)	Float64	Longitude in decimal degrees using the Japanese geodetic datum indicated by the column name.

Column Name	Data Type	Description
GoalLat(WGS)	Float64	Latitude in decimal degrees using the World Geodetic System (WGS 84).
GoalLon(WGS)	Float64	Longitude in decimal degrees using the World Geodetic System (WGS 84).
ArrivalCode	Int64	Identifier code of the arrival location.
ArrivalName	String	Name of the arrival location.
User'sArrivalName	String	Arrival-location name entered by the user.
ArrivalCode_duplicated_0	Int64	Duplicated arrival-location code retained from the source data.
ArrivalAttribute	String	Attribute of the arrival location.
ArrivalLat(JGS)	Float64	Latitude in decimal degrees using the Japanese geodetic datum indicated by the column name.
ArrivalLon(JGS)	Float64	Longitude in decimal degrees using the Japanese geodetic datum indicated by the column name.
ArrivalLat(WGS)	Float64	Latitude in decimal degrees using the World Geodetic System (WGS 84).
ArrivalLon(WGS)	Float64	Longitude in decimal degrees using the World Geodetic System (WGS 84).
compatibility	Int64	
CreationFlag	Int64	Record-creation flag from the source system.
ArrivalFlag	Int64	Arrival-status flag from the source system.
validity	Int64	Validity flag: 1=Valid, 0=Invalid.
TransportationCode	Int64	Transportation mode code: 0=--, 100=Car, 200=Train, 240=Bus, 300=Motorcycle, 410=Bicycle, 420=Walk, 500=Taxi, 600=Airplane, 700=Ship, 800=Waiting time, 999=Other.
Transportation	String	Recorded transportation-mode name.

Column Name	Data Type	Description
TransportationChange1_CD	Int64	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange1_Name	String	Name of transportation mode after change 1.
TransportationChange1_Time	Datetime	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange2_CD	Int64	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange2_Name	String	Name of transportation mode after change 2.
TransportationChange2_Time	Datetime	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange3_CD	Int64	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange3_Name	String	Name of transportation mode after change 3.
TransportationChange3_Time	Datetime	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange4_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange4_Name	String	Name of transportation mode after change 4.
TransportationChange4_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange5_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange5_Name	string	Name of transportation mode after change 5.
TransportationChange5_Time	string	Date and time in Japan Standard Time (JST, UTC +09:00).

Column Name	Data Type	Description
TransportationChange6_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange6_Name	String	Name of transportation mode after change 6.
TransportationChange6_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange7_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange7_Name	String	Name of transportation mode after change 7.
TransportationChange7_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange8_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange8_Name	String	Name of transportation mode after change 8.
TransportationChange8_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange9_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange9_Name	String	Name of transportation mode after change 9.
TransportationChange9_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange10_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange10_Name	String	Name of transportation mode after change 10.
TransportationChange10_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).

Column Name	Data Type	Description
TransportationChange11_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange11_Name	String	Name of transportation mode after change 11.
TransportationChange11_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange12_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange12_Name	String	Name of transportation mode after change 12.
TransportationChange12_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange13_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange13_Name	String	Name of transportation mode after change 13.
TransportationChange13_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
TransportationChange14_CD	String	Transportation mode code at this transfer. Use s the same code definitions as TransportationC ode.
TransportationChange14_Name	String	Name of transportation mode after change 14.
TransportationChange14_Time	String	Date and time in Japan Standard Time (JST, UTC +09:00).
Mesh3_Departure	String	Third-level Japanese standard grid-square code of the departure location.
Mesh3_Goal	String	Third-level Japanese standard grid-square code of the goal location.
Mesh3_Arrival	String	Third-level Japanese standard grid-square code of the arrival location.

Hash Value (BLAKE3)

bd517f04b2fda9e79526efced70f647affd53dfafd57486c3773ab9624e332a2

Last Updated: see Git history
©BinN, UTokyo