


Bitzoom Wallet Testing Guide

Your complete guide to setting up a test wallet for testing deposit and withdrawal on Bitzoom.



Step 1 — Install TronLink Wallet

Install the TronLink browser extension from the Chrome Web Store:


<https://chromewebstore.google.com/detail/tronlink/ibnejdfjmmkpcnlpebklmknkoeoihofec>


- Open the link above in Chrome
- Click **Add to Chrome** to install the extension
- Click the **puzzle icon** in the top-right corner of Chrome and pin TronLink for easy access

Step 2 — Create a Wallet

After installing TronLink, open the extension and create a new wallet.

- Click the **TronLink icon** in the Chrome toolbar
- Select **Create Wallet**
- Set a **wallet name** and **password**
- **Back up your seed phrase** — write it down and store it safely
- Confirm the seed phrase to complete setup





Step 3 — Your Wallet is Ready


After creating your wallet, you will see the main wallet screen.


- Check the **top-right corner** — it should show **GasFree**
- Your wallet is now created with **\$0** balance
- You will see a **Security Alert** warning you to back up your wallet
- Click **Back up** to proceed to the backup step

Step 4 — Back Up Your Wallet

Back up your seed phrase to keep your wallet safe.

- Click **Back up** from the security alert or go to Settings to back up
- Write down your **seed phrase** on paper and store it safely
- **Never share** your seed phrase with anyone
- Confirm the seed phrase to complete the backup





Step 5 — Enable Test Networks


By default, TronLink only shows the Mainnet. You need to enable test networks first.


- Open TronLink and click the **Settings icon** (gear) in the top-right corner
- Choose **Network**
- Toggle on **Show test network**
- Go back to the main screen

Step 6 — Switch to Nile Testnet

Now switch the active network to the Nile Testnet.

- On the main screen, click the **network icon** (next to the Settings gear icon) in the top-right corner
- Select **Nile Testnet** from the list
- You should see the network label change to confirm you are on the testnet





Step 7 — Copy Your Wallet Address

You will need your wallet address to receive test tokens.

- Open TronLink and make sure you are on **Nile Testnet**
- Click your **wallet address** to copy it to clipboard
- You will paste this address in the next step

Step 8 — Get Test TRX (Gas)

TRX is needed to pay for transaction fees (gas) on the TRON network.

Visit the Nile Testnet faucet to get free test TRX.

<https://nileex.io/join/getJoinPage>

- Open the faucet link above
- Find the **"Get 2000 test coins"** section
- Paste your **wallet address** into the Account Address field
- Complete the **reCAPTCHA** verification
- Click **Obtain** to receive 2000 test TRX




[Releases](#) [Faucet](#) [How to Join](#) [How to Run](#) [Proposals](#)

Get 2000 test coins

Test coins trx can be obtained by entering account address

Account Address



Obtain

Get 10,000,000 BTT test tokens

BTT test tokens (trc20, token address: TNuoKL1ni8aoshFL1ASca1Gou9RXwAzfn) can be obtained by entering account address

Get 1000 USDT test tokens

USDT test tokens (trc20, token address: TXYZopYRdj2D9XRtbG411XZZ3kM5VkAeBf) can be obtained by entering account address

Account Address



Obtain

Get 1000 JST test tokens

JST test tokens (trc20, token address: TF17BgPaZYbz8oxbjhriubPDsA7ArKoLX3) can be obtained by entering account address

Account Address



Step 9 — Get Test USDT

Scroll down on the same faucet page to get test USDT tokens.

- Find the **"Get 1000 USDT test tokens"** section
- Paste your **wallet address** into the Account Address field
- Complete the **reCAPTCHA** verification
- Click **Obtain** to receive 1000 test USDT
- Open TronLink to verify your USDT balance

Step 10 — Check Your Balance

Open TronLink to verify your test tokens have arrived.

- Click the **TronLink icon** in the Chrome toolbar
- You should see your **TRX** and **USDT** balances
- Use this wallet address for **deposit** and **withdrawal** testing on Bitzoom

