

2—FAULTS (continued)

REF NO	DESCRIPTION	SYMBOL	CARTOGRAPHIC SPECIFICATIONS*	NOTES ON USAGE*
2.10—Detachment faults (sense of slip unspecified) (continued)				
2.10.25	Master detachment fault (sense of slip unspecified) —Identity and existence certain, location accurate. Hachures on upper plate			May be used to show either normal (extensional) or thrust (compressional) offset. Hachures indicate overall fault type (master detachment fault); they are not placed at specific localities where observations have been made. In cross section, use paired arrows to show relative motion of master detachment faults (see Section 2.11).
2.10.26	Master detachment fault (sense of slip unspecified) —Identity or existence questionable, location accurate. Hachures on upper plate			
2.10.27	Master detachment fault (sense of slip unspecified) —Identity and existence certain, location approximate. Hachures on upper plate			
2.10.28	Master detachment fault (sense of slip unspecified) —Identity or existence questionable, location approximate. Hachures on upper plate			
2.10.29	Master detachment fault (sense of slip unspecified) —Identity and existence certain, location inferred. Hachures on upper plate			
2.10.30	Master detachment fault (sense of slip unspecified) —Identity or existence questionable, location inferred. Hachures on upper plate			
2.10.31	Master detachment fault (sense of slip unspecified) —Identity and existence certain, location concealed. Hachures on upper plate			May be used to show either normal (extensional) or thrust (compressional) offset. Ticks indicate overall fault type (listric fault at head of detachment fault); they are not placed at specific localities where observations have been made. In cross section, use paired arrows to show relative motion of listric faults at head of detachment faults (see Section 2.11).
2.10.32	Master detachment fault (sense of slip unspecified) —Identity or existence questionable, location concealed. Hachures on upper plate			
2.10.33	Listric fault at head of detachment fault (sense of slip unspecified)—Identity and existence certain, location accurate. Ticks on upper plate			
2.10.34	Listric fault at head of detachment fault (sense of slip unspecified)—Identity or existence questionable, location accurate. Ticks on upper plate			
2.10.35	Listric fault at head of detachment fault (sense of slip unspecified)—Identity and existence certain, location approximate. Ticks on upper plate			
2.10.36	Listric fault at head of detachment fault (sense of slip unspecified)—Identity or existence questionable, location approximate. Ticks on upper plate			
2.10.37	Listric fault at head of detachment fault (sense of slip unspecified)—Identity and existence certain, location inferred. Ticks on upper plate			
2.10.38	Listric fault at head of detachment fault (sense of slip unspecified)—Identity or existence questionable, location inferred. Ticks on upper plate			
2.10.39	Listric fault at head of detachment fault (sense of slip unspecified)—Identity and existence certain, location concealed. Ticks on upper plate			
2.10.40	Listric fault at head of detachment fault (sense of slip unspecified)—Identity or existence questionable, location concealed. Ticks on upper plate			

*For more information, see general guidelines on pages A-i to A-v.