

Navigation: Plugins >

Microsoft Word: Workstation PlugIn Options

Set the Workstation PlugIn options for your Word integration by selecting the PlugIn Workstation command on the Tools tab of the ribbon, then select Word from the pull down list.

Use Watcher

The "watcher" program should only be turned on if requested to do so by Synergis technical support staff. The Synergis Watcher is a debug program used to help identify issues related to the proper integration between Adept and an application. Be sure to turn off the "watcher" program when done, as it will affect performance if left running.

Navigation: Plugins >

Microsoft Excel: Workstation PlugIn Options

Set the Workstation PlugIn options for your Excel integration by selecting the PlugIn Workstation command on the Tools tab of the ribbon, then select Excel from the pull down list.

Use Watcher

The "watcher" program should only be turned on if requested to do so by Synergis technical support staff. The Synergis Watcher is a debug program used to help identify issues related to the proper integration between Adept and an application. Be sure to turn off the "watcher" program when done, as it will affect performance if left running.

Navigation: Plugins >

PDF Extraction: Workstation PlugIn Options

Set the Workstation PlugIn options for your PDF Extraction integration by selecting the PlugIn Workstation command on the Tools tab of the ribbon, then select PDF Extraction from the pull down list.

Use Watcher

The "watcher" program should only be turned on if requested to do so by Synergis technical support staff. The Synergis Watcher is a debug program used to help identify issues related to the proper integration between Adept and an application. Be sure to turn off the "watcher" program when done, as it will affect performance if left running.

Navigation: Plugins >

Properties: Workstation PlugIn Options

Set the Workstation PlugIn options for your Properties integration by selecting the PlugIn Workstation command on the Tools tab of the ribbon, then select Properties from the pull down list.

Use Watcher

The "watcher" program should only be turned on if requested to do so by Synergis technical support staff. The Synergis Watcher is a debug program used to help identify issues related to the proper integration between Adept and an application. Be sure to turn off the "watcher" program when done, as it will affect performance if left running.

Navigation: Plugins >

Administer PlugIns

Access the Administer PlugIn dialog by selecting the Administer PlugIns command.

You can learn about the current state of each PlugIn from this dialog. The columns of T (true) and F (false) to the right of each PlugIn indicate if the PlugIn is Loaded, Load on Startup (LOS) or Required.

To change features of a PlugIn, including to set it as Load On Startup or Required, click the Edit button. Load On Startup must be set in order for the PlugIn to be loaded. See [PlugIn Editor](#) for more details.

To add a PlugIn that is not yet on the list, click the Add button.

Order

Occasionally, you may need to control the order in which the PlugIns are executed. For example, if you have the Data Exporter and the Required Fields PlugIn, you need to move the Required Fields PlugIn higher in the list. Click the Up button so that this PlugIn checks for the Required fields first.

To test and troubleshoot, click the Load or Unload buttons. These should act immediately. After clicking Load or Unload, you can continue to use Adept to confirm the behavior of the PlugIn.

Note: *The Administer PlugIns dialog is modeless. This means that you can leave the dialog open while you continue to work in Adept.*

When you exit the dialog, either through Cancel or OK, your choice of Load or Unload buttons is ignored. After you click Cancel or OK, Adept will reload only the PlugIns for which "Load on Startup" is enabled.

Failure to Load

If the Load button seems to have no effect, you can learn more about the status of the PlugIn by clicking the Edit button. For example, attempting to load the Adept Word PlugIn when there is no instance of Microsoft Word loaded on the machine displays a message in the Message field of the PlugIn Editor.

Custom programmers will also use the Administer PlugIns dialog to integrate their Adept API applications in with the software. Since the dialog is modeless, software developers can use the Load and Unload commands during development and testing.

Navigation: Plugins >

PlugIn Editor

To add a PlugIn to Adept, enter data into the PlugIn Editor. PlugIns supplied by Synergis include a *.apd file. You can import this by clicking the Import button and browsing to the folder.

1. Click Import and browse to the Adept PlugIn Description file with the extension APD.
This contains all the parameters you need to set up the module.

Load On Startup

To activate a PlugIn, check the Load On Startup option.

Required

When you enable the Required option, the PlugIn must be loaded. If it is not, Adept refuses to start.

Interface Name

To install PlugIns manually, type the following line:

AP_your-PlugIn-name.PI_your-PlugIn-name

For example, to install the SOLIDWORKS integration, type the following line, exactly:

AP_SOLIDWORKS.PI_SOLIDWORKS

2. Do check the “Load on Startup” check box. Do NOT check the “Required” check box
3. Select OK

Export

If you are developing your own API application, you can create a *.apd file by using export.

Delete and Re-add a PlugIn

To update a PlugIn, you must delete it and re-add it. After you delete a PlugIn, you must completely exit the PlugIn Editor in order to finalize your change. Exiting the PlugIn Editor writes the changes to the Adept tables. If you need to add the PlugIn again, you can re-open the PlugIn Editor and click Add.

Navigation: Plugins >

PlugIn Overview and Options

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Most Adept PlugIns require you to set up your preferences for the way you want the PlugIn to work. Each PlugIn has different parameters, and specific instructions will be provided for each PlugIn.

If you will intend to store PlugIn data in Adept, decide if you will use an existing database field, or if you will add new fields. If using an existing field, check that the field width will accept the mapped property without truncating information

Several PlugIns share a number of common features. This topic provides an overview of some of these shared parameters. The PlugIns that have these shared features are:

[AutoCAD](#)

[Images](#)

[Inventor](#)

[Microsoft Excel](#)

[Microsoft Word](#)

[MicroStation](#)

[Properties](#)

[XML Properties](#)

[SOLIDWORKS](#)

[PDF Extraction](#)

To access the configuration window for each PlugIn, select the PlugIn from the Configure PlugIns command's fly menu on the System tab . See [AutoCAD DWG PlugIn Administration](#) to see an example of a PlugIn Administration dialog.

Extensions

This is a list of document extensions representing all the document types supported by the PlugIn. You must check the ones from which you want Adept to extract data. In the Properties PlugIn you can also add more document extensions to the list.

Options

This pane lists the options that are supported by this PlugIn. You must check the ones you want to operate when Adept examines each supported document type. Typical options include:

Extract attributes or properties

The values will be extracted into Extraction fields if present.

Extract Relationships

For supported CAD documents, Adept will extract the location of children documents.

Extract Thumbnails

For supported documents such as CAD, MS Office, and Raster, a thumbnail is extracted.

Update Document

When enabled, Adept can write values from the table out to the document.

Batch Open and Save

This instructs Adept to open the selected documents in the supported native application, and then saves and closes it. This is helpful for some operations, like upgrading documents to a more recent version of CAD software. In some cases such upgrades are required to maintain compatibility with the current integrations.

Control Opening

This option tells Adept that it's okay to open the application. This is necessary for normal functioning of the integration. If you don't have this option checked it may still be possible to open the application, but with unpredictable results. For example, in most cases a new instance of the application will be started each time an application is opened. In some cases, under the supervision of Adept Help desk, you can trouble shoot problems by turning off this option and allowing Windows to open the application.

Adept Extraction Fields

This lists all available Adept fields that are designated as extraction fields.

Available Data

This contains a list of properties or attributes from your documents. It is displayed to allow you to quickly and easily drag and drop document properties and associate them with extraction fields.

See the [PlugIn Scanner](#) to learn how to populate the Available Data list.

Mapping for Adept Extraction Field

This shows the linkage between an Adept extraction field and the property, attribute, or tag name in the document. You populate this list by dragging an available property to an available extraction field. When Adept synchronizes, checks in, or for any other reason scans a document, it checks for a mapping between an extraction field and a property, attribute, or tag. If it finds such a mapping, it performs the extraction or update and implements any other option you have specified.

Excel

Adept can address Excel values in three ways. You can extract Excel properties. You can extract or update Excel locations (for example, \$A\$1). Or you can extract or update Excel named locations.

Word

Adept can address Microsoft Word values in two ways. Write to or extract from Word properties. And write to or extract from Word bookmarks.

Navigation: Plugins >

PlugIn Scanner

Note: *To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.*

To populate the list of Available Data, use the Scan command. The Scan command lets you add the names of template documents to a list. Select the Add command to add the name of a document to this list and Remove to take one off the list. When you are ready, click OK.

Adept then examines each document in the list, and finds the properties, attributes, and so on in the document or documents you listed in the scanner. This data then is listed in the right-column of the PlugIn dialog under the heading "Available Data."

To link the available attributes, properties, or tags with the relevant data fields in Adept, first select the field on the left. Then from the list of available data in the right column, select the field you want to map and drag it into the middle column.

You can also right-click the property in the column labeled Available Data to manually add entries that cannot be scanned.

Navigation: Plugins >

PlugIn Info

In the Help tab, select "PlugIns..." to gain access to information about each PlugIn. Simply select the PlugIn from this list and click the button labeled, "Info."

Navigation: Plugins >

PlugIn Editor Info

To allow non-Administrators to display PlugIn information, the PlugIn dialog is made available in a read-only basis from the Help tab. This displays the information from the PlugIn editor in a Read Only format for information purposes. To edit this information, select [PlugIn Administration](#) from the Admin tab.

Navigation: Plugins >

PlugIn for Windows Images

The PlugIn for Windows Images manages thumbnail extraction from several document types to be used by Adept for Thumbnail display in the Data Card and the Document Dashboard.

The configuration dialog allows you to select the extensions of the documents which will be extracted by this PlugIn.

When you install this PlugIn Adept will automatically extract a "thumbnail" from any supported image document format that you check. Once the thumbnail has been stored in Adept, it will be displayed in the Data Card Thumbnail tab, in the Document Dashboard Thumbnail tab, and in other dialogs where thumbnails are displayed.

Realize that "thumbnails" can be quite large. To protect against excess storage requirements on your database server, set a maximum width and height.

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Navigation: Plugins >

PlugIn for PDF Extraction

When you load and enable this PlugIn, Adept will be able to extract Form Text Fields, Properties and Thumbnails from PDF documents. Select the Configure PlugIns command to open the Administration dialog. The Administration dialog allows control of what is extracted under Options.

When checking the option to extract thumbnails, a dialog will be presented where you define the quality of the thumbnail. This setting impacts the size of the image stored in the database and the time needed to perform extraction. Setting this above 50% may cause excessive database size resulting in longer database backups and longer extraction time. It is recommended to set this to 40% or less.

The bottom portion of the dialog allows you to map the properties in the external documents with the extraction fields in Adept.

See [PlugIn Scanner](#) to populate the list of Available Data.

As with other PlugIns, you will need to set up Extraction Fields and map them to the properties. Also see the [PlugIn Overview and Options](#) for more setup details.

Note: Only PDFs that are not secured can be extracted. Secure PDFs prevent the PlugIn from extracting any information successfully.

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Navigation: Plugins >

PlugIn for Properties

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Word, Excel and other documents contain built in properties, such as Author and Subject. You can also create your own Custom Properties such as Client or Project. This PlugIn for Properties allows you to extract these values and enter them into Adept fields. In addition you can update the Properties.

Not all Windows documents store properties with the same format. With this PlugIn, Adept extracts properties that conform to the STG Open Storage standard. To find out if Adept will extract document properties from your document type, conduct an experiment with a small document that has known property values, or check with the manufacturer of the software that created the document in question. Examples of STG Open Storage Properties include: Microsoft Word, Excel, Publisher, and PowerPoint.

Note: If you want support for documents from Microsoft Word or Microsoft Excel 2003 or greater, use the Word or Excel PlugIn. If you want support for XML documents, use the PlugIn for XML Properties.

Note: Many Office documents now are stored in XML format and have an additional "x" on the file extension. Should the Properties PlugIn fail to work as desired and the file you are extracting has the "x" appended to the extension, you should try using the PlugIn for XML Properties.

Setup

To extract properties from supported documents, use the PlugIn for Properties. Open the Administer PlugIn dialog by selecting the Administer PlugIns command. Select Adept PlugIn for Properties from the list of PlugIns then click Edit to open the PlugIn Editor. Check Load on Startup then click OK to close the dialog and enable the PlugIn. Click OK to close the Administer PlugIns dialog and install the PlugIn.

Select the Configure PlugIns command to open the Administration dialog for this PlugIn. You can add extensions of the documents from which you want Adept to extract properties by right-clicking in the Extensions pane. A small dialog appears that asks you if you want to add or delete an extension.

Note: If you add an extension that is not supported by the Open Storage format, the property extraction will fail. For example, Adobe Acrobat documents are not supported, and so, if you place "pdf" extension in this list, the PlugIn will generate error messages.

The bottom portion of the dialog allows you to map the properties in the external documents with the extraction fields in Adept.

See [PlugIn Scanner](#) to populate the list of Available Data.

As with other PlugIns, you will need to set up Extraction Fields and map them to the properties.

See the [PlugIn Overview and Options](#) for more setup details.

Navigation: Plugins >

PlugIn for XML Properties

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Use this PlugIn to extract properties from supported XML documents, such as docx and xlsx. This PlugIn works exactly like the PlugIn for Properties, enabling you to extract properties from the newer document formats and placing the values in Adept fields.


Note: Many Office documents now are stored in XML format and have an additional "x" on the file extension. Should the Properties PlugIn fail to work as desired and the file you are extracting has the "x" appended to the extension, you should try using the PlugIn for XML Properties.

To set up the PlugIn:

1. Open the Administer PlugIn dialog by selecting the Administer PlugIns command
2. Select Adept PlugIn for Properties from the list of PlugIns
3. Select the Edit button to open the PlugIn Editor
4. Check the option to Load on Startup
5. Select OK to close the PlugIn Editor dialog and enable the PlugIn.
6. Click OK to close the Administer PlugIns dialog and install the PlugIn.

Select the Configure PlugIns command to open the Administration dialog for this PlugIn.

The top portion of this dialog allows you to select extensions that are affected by the PlugIn, and also allows you to select the types of data to be extracted as well as to enable the Update Document feature. Update Document allows Adept to write values to the document.



The bottom portion of the dialog allows you to map the properties in the external documents with the extraction fields in Adept.

See [PlugIn Scanner](#) to populate the list of Available Data.

As with other PlugIns, you will need to set up Extraction Fields and map them to the properties. See the [PlugIn Overview and Options](#) for more setup details.

Navigation: Plugins >

PlugIn for Microsoft Word

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Use the PlugIn for Microsoft Word to read or write properties, Form Fields, and Content Controls to Word 2003 or above. To use this PlugIn you must also have Microsoft Word installed on your workstation.

Note: The PlugIn for Microsoft Word cannot [Extract](#) properties from MS Word versions previous to 2003. To do so, you need to load and configure the [Adept PlugIn for Properties](#).

Note: To write ([Update](#)) properties to Word 2003 or greater install the Word PlugIn. Adept cannot update properties or form fields in MS Office documents older than Office 2003.

Note: *If you are using Microsoft Office 2010 or higher, you may need to unblock older versions of Microsoft Word. To check or change File Blocking settings in Microsoft Office, click the File Menu, then click Options. On the left side, click Trust Center, and in that dialog click File Block Settings. Unblock the versions of Word that you need to synchronize.*

Feature description

Word documents contain some built in properties, such as Author and Subject. You can also create your own Custom Properties such as Client or Project. Word properties can be linked to form fields or Content Control fields inside Word.

When you [Synchronize](#) or [Check In](#) Microsoft Office documents, 2003 or greater, Adept checks to see if any properties match [Extraction fields](#) in your database. If there is a match between your Extraction fields and the Properties, Form Fields, and Content Control fields in the document, Adept copies the value out of the document into the database.

An effective way to use these properties is for your administrator to create [template documents](#) that contain predefined custom properties. When you create a new document with the [Document New](#) command, Adept creates a copy of the template. You can then add values to the properties in the document. When you check in the document, Adept will then automatically copy the values into the database.

Set Up

To set up the PlugIn, open the Administrator PlugIn dialog by selecting the Administer PlugIns command. Select Adept PlugIn for Word from the list of PlugIns then click Edit to open the PlugIn Editor. Check Load on Startup then click OK to close the dialog and enable the PlugIn. Click OK to close the Administer PlugIns dialog and install the PlugIn.

Select the Configure PlugIns command to open the Administration dialog for this PlugIn. Check the Extensions and Options as appropriate. When you have this PlugIn installed, you can set up your Extraction fields in Adept to link to Properties, Form Fields, and Content Controls in Word. Then, as with other Extraction fields, you can write (update) values from Adept to the Word document, or read values from the Word document to Adept.

Note: *It is recommended that you map to the form field or the Content Control field instead of the custom property. Mapping to the custom property and performing an Update Document will break any link that the custom property might have to a form field or Content Control field.*

See [PlugIn Scanner](#) to populate the list of Available Data.

As with other PlugIns, you will need to set up Extraction Fields and map them to the properties. Also see the [PlugIn Overview and Options](#) for more setup details.

Navigation: Plugins >

PlugIn for Microsoft Excel

Note: *To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.*

Excel documents contain some built in properties, such as Author and Subject. Use the PlugIn for Microsoft Excel to read or write properties. You can also create your own Custom Properties such as Client or Project. Excel properties can be linked to Locations or Named Locations inside Excel.

Note: To read ([Extract](#)) properties from MS Excel previous to 2003, you need to load and configure the [PlugIn for Properties](#).

Note: The PlugIn for Microsoft Excel requires that you install a copy of Microsoft Office on your workstation. If you are using Microsoft Office 2010 or higher, you may need to unblock older versions of Microsoft Excel. To check or change File Blocking settings in Microsoft Office, click the File Menu, then click Options. On the left side, click Trust Center, and in that dialog click File Block Settings. Unblock the versions of Excel that you need to synchronize.

When you [Synchronize](#) or [Check In](#) documents created by Microsoft Excel, 2003 or greater, Adept checks to see if any properties match [Extraction fields](#) in your database. If there is a match between your Extraction fields and the Properties or Locations or Named Locations in the document, Adept copies the value out of the document into the database.

An effective way to use these properties is for your administrator to create [template documents](#) that contain predefined custom properties. When you create a new document with the [New](#) command, Adept creates a copy of the template. You can then add values to the properties in the document. When you check in the document, Adept will then automatically copy the values into the database.

Export to Excel

In addition to importing from Excel, after you have installed the Excel PlugIn, you can export metadata from Adept into an Excel spreadsheet. First select the documents from any Adept window. Then select the Export to Excel command on the Collaborate tab of the ribbon. Using the dialog box in this PlugIn, you can specify which headers and fields are placed in the output document.

Note: This PlugIn always exports the date in the format that is set in the Windows options of the Workstation where the program is running, and does not use the date format specified for Adept.

Header

You can choose the headings first by right-clicking and selecting Show Main or Show All. This controls how many fields you can choose from. Then from the list, select the Headers you want included in the document. These will be saved into the Excel document.

For typical exports, you will usually only add the Display Name. This will provide a single row of headers that contains the display name at the top of each column. This is the format expected by users when exporting to Excel. Then if you choose to import this Excel document back into Adept, using the Data Import feature, Adept will interpret the headers.

The other header options will have value for programmers, data analysts, or for interpretation by computer programming in custom programs. Aliases refer to the fact that some values in the Adept Tables are references to fields in other tables. The Alias Table is the name of the table. You can select "Yes" or "No" for "Using Alias." "Yes" if you want to export the value contained in the alias, and "No" if you want to export the

number that is used for the link. You could include of each, one aliased and one not, to see both aspects of the data.

Select Fields

To decide which fields are exported, you may drag and drop fields from the left side into the right side. You can control the list that is displayed in this panel by right-clicking, and selecting Show All, Show Only System Fields, or Show Only User Fields.

To add fields from this list into the Export list on the right, select Add from this right-click menu. When you Add fields, they are displayed in the Report list on the right side of the dialog.

To remove fields from this list, you can right-click and select Remove. Fields in the right side can be dragged up and down to reorder the output You can also use the right-click menu to control Aliases.

Save Settings

You can optionally save an output setting document by selecting Save As from the File menu. By default this document is saved to your AdeptSupport folder. This document can be reused by using the Open command in the File menu.

Click Export to Execute

Once you have selected the fields, and click Export, this command works on the selected records in any Adept window. All selected records will be output into an Excel worksheet and immediately opened in Excel. From Excel the user may save the document or close without saving.

This feature will be used for generating extensive reports on documents and related information in Adept. It differs from the "Save List as Text" export option because "Export to Excel" only outputs the selected records, provides optional headings, and is not limited by the number of fields that can be displayed in an Adept window (currently limited to 24). "Export to Excel" also exports directly into an Excel document rather than to a tab-delimited text document.

Setup

Open the Administrator PlugIn dialog by selecting the Administer PlugIns command on the System tab of the ribbon. Select Adept PlugIn for Excel from the list of PlugIns then click Edit to open the PlugIn Editor. Check Load on Startup then click OK to close the dialog and enable the PlugIn. Click OK to close the Administer PlugIns dialog and install the PlugIn.

Select the Configure PlugIns command to open the Administration dialog for this PlugIn. Check the Extensions and Options as appropriate. When you have this PlugIn installed, you can set up your Extraction fields in Adept to link to Properties or Named Locations or Locations in Excel. Then, as with other Extraction fields, you can write values from Adept to the Excel document, or read values from the Excel document to Adept.

See [PlugIn Scanner](#) to populate the list of Available Data.

As with other PlugIns, you will need to set up Extraction Fields and map them to the properties. See the [PlugIn Overview and Options](#) for more setup details.

Navigation: Plugins >

Group Email Notification - Configure PlugIn

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using and disable ones you will not.

The Group Email PlugIn gives the user control over the content of the email and the people who will receive it, allowing you to specify email recipients using Adept groups or individual users. The email notification may simply contain a link to a document or may contain attached documents.

Open the Administrator PlugIn dialog by selecting the Administer PlugIns command. Select Adept PlugIn for Group Email Notification from the list of PlugIns then click Edit to open the PlugIn Editor. Check "Load on Startup" then click OK to close the dialog and enable the PlugIn. Click OK to close the Administer PlugIns dialog and install the PlugIn.

Select the Configure PlugIns command to open the Administration dialog for this PlugIn. Check the General and Settings tabs as appropriate. When you have this PlugIn installed, you can set up Extraction fields in Adept to link to Properties.

On the General tab, the Adept Administrator can set the options to determine which groups of users will activate this PlugIn.

Enable Group Email Notification for all Adept Users

This setting includes all users in the Adept system.

Enable Group Email Notification for Adept Groups

This setting restricts notification to members of selected groups.

Note: At least one group must be selected.

Disable Standard Adept "Send To" Command

The checkbox disables the standard Send To command on the Collaborate tab of the ribbon.

The Settings tab lists the Available Options, where the Adept Administrator can choose to activate any combination of the Format options on the user's dialog. In the Default Option section, the Adept Administrator chooses the default action when a user initiates the PlugIn. The bottom option allows the Adept Administrator to define what Adept command will activate the PlugIn.

Once the configuration is completed, select the OK button to save the changes and exit the dialog box. Selecting the Cancel button will cancel any changes made since the last save.

Navigation: Plugins >

Group Email Operation

All users for whom this PlugIn is enabled will be able to engage it at any time, by using a Group Email pick from the Collaborate ribbon. This option will initiate the Group Email dialog and the user may send an email without having to Approve, Assign, or Check In.

This PlugIn intercepts Check In, Assign or Approve Adept and prompts the user with a dialog box.

Group Name

Checking an available Group, all members of that Group will receive an email. Individual members may be unchecked.

User Name

Clicking the + next to Group will show all members of that Group. You can select only the users you want to receive the email.

Only the users who have valid email addresses defined in their Adept user account will be able to receive email notification.

Check the Documents(s) to Include

This section will list all the documents that were selected in one of the Adept windows before selecting Group Email. You can still uncheck any document(s) you don't want to include.

Format

Select an available method for sending the selected documents.

The Send button will not be enabled until users are identified for receiving the email and there are entries in both the Subject and Message areas.

After successful execution, a confirmation message will be displayed to the user.

Navigation: Plugins >

Outlook to Adept Add-in

To export email from Microsoft Outlook into Adept, install Adept's "Outlook to Adept" Add-in into Outlook. This Add-in will allow you to optionally export any attachment(s) to an email and save these into Adept, as well. Adept will maintain a relationship between the imported email and its associated imported attachments. Adept's Document Dashboard will then display the attachments as children to the saved email. Once they are safely saved in Adept, you can then delete them from Microsoft Outlook.

Now instead of depending on Microsoft Outlook to track emails, you can centralize them and make them available in a common, controlled location. With Adept's search capabilities, emails will become easier to manage and find.

Note: *This Add-in does not support Lotus Notes or Outlook Express.*

Installation

To install the Outlook to Adept Add-in, run AP_OutlooktoAdept.msi, located in the folder Program Files\Synergis\Adept10\Client\Install. This will install the Adept menu in Outlook.

Operation:

In Microsoft Outlook, select an email and then click the "Save to Adept" button.

If necessary, Adept changes special characters in the filename to underscores. Before saving, the user can also manually edit the name. The body of the email is saved in Adept in the format users select from the dropdown list (msg, rtf, html or plain text).

Note: *Outlook messages saved in HTML format cannot be viewed by the Adept Viewer.*

The user must select the Adept Library where the email is to be saved. The bottom section of the dialog lists the attachments to the email. Edit the name of attachments by double clicking on them. The Include checkbox instructs Adept to include the attachment(s) to this email. If you uncheck this, the Add-in will skip the attachment(s) and not save them. The child checkbox determines if Adept should build a relationship between the attachment(s) and the email.

Upon clicking OK, the documents are checked in and are displayed in an Adept Search Results. You can use the search results at this time to add data to the Data Cards individually or with Batch Update. If there is a workflow associated with the selected library, the new document(s) will have to pass through it.

If the name is duplicated, the Add-in traps it and asks you to change the document name. If multiple emails are selected the program would loop around again to do the second email then loop around to do the third email.

When all the information for the document is in Adept the user can then switch back to Outlook and manually delete or archive the email(s) because they are now being safely stored and tracked in Adept.

Navigation: Plugins >

Microsoft Outlook PlugIn

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Overview

The Outlook PlugIn can be used in conjunction with the “Outlook to Adept” Add-in. Emails and their attachments can be saved from Outlook to Adept. When the email is saved as a record in Adept, properties from the emails such as To, From, and Subject can be automatically inserted into Adept extraction fields using the Outlook PlugIn.

Note: To learn more about the Outlook to Adept Add-in see the Help Topic of that name.

Properties that can be extracted from an Outlook Email

Billing Info

CC

Categories

Companies

Creation Time

Creation Date

Deferred Delivery Time

Deferred Delivery Date

Flag Due By

Flag Due By Date

Flag Request

Last Modified Time

Last Modified Date

Received By

Received on Behalf of

Name

Date and Time - to be mapped to Adept Character Fields only

Date only portion of above - can be mapped to Adept Date fields

Date and Time - to be mapped to Adept Character Fields only

Date only portion of above - can be mapped to Adept Date fields

Date and Time - to be mapped to Adept Character Fields only

Date only portion of above - can be mapped to Adept Date fields

Date and Time - to be mapped to Adept Character Fields only

Date only portion of above - can be mapped to Adept Date fields

Received Time	Date and Time - to be mapped to Adept Character Fields only
Received Date	Date only portion of above - can be mapped to Adept Date fields
Reply Recipient Names	
Sender email address	
Sender SMTP email address	
Sender Name	
Sent On	Date and Time - to be mapped to Adept Character Fields only
Sent On Date	Date only portion of above - can be mapped to Adept Date fields
Sent on Behalf of	
Subject	
To	
Task Completed	Date and Time - to be mapped to Adept Character Fields only
Task Completed Date	Date only portion of above - can be mapped to Adept Date fields
Task Start	Date and Time - to be mapped to Adept Character Fields only
Task Start Date	Date only portion of above - can be mapped to Adept Date fields
Task Subject	

Note: In the CC and To fields only the displayed name is found and not necessarily the expanded email address.

Note: This PlugIn cannot extract BCC.

Note: This PlugIn cannot use the Update Document feature to push values from Adept back to the Outlook Email.

Note: All of the Date/Time type of properties offer two different ways to access them, one with just the date and the other with the date and time. These can only be mapped to a character field.

Note: When a field is mapped to an Adept field the string will get truncated if the Adept field is not large enough to capture the entire value.

Configure:

To configure this PlugIn, you will need to map Outlook Email Properties to Adept Extraction Fields. First select the Configure PlugIns command...

The resulting dialog displays a list of all the Adept Extraction Fields in the left column, and a list of all the Microsoft Outlook Email Property Fields in the right column.

To map an Extraction field to an Outlook property, select the Extraction field from the column on the left. The name of the Extraction field will be displayed above the middle column. Now review the Email Properties in the column on the right. Drag one or more properties from this list and drop it on to the middle column.

When you are finished mapping properties, click OK.

Navigation: Plugins >

Approval Authentication

Overview and Operation

When loaded and enabled by a System Administrator, invoking the commands listed below will display a password entry dialog box prior to displaying the typical dialog.

- Approve
- Reject
- Expedite Approve
- Reject To
- Expedite Reject
- Final Approve
- Create Version (Available only in Adept Desktop)
- Delete Version

If the user has selected more than one document before invoking the command, the password entry will apply to all selected documents when the command was invoked.

The password dialog box displays the Username of the user currently logged in as a read-only text box and prompts for that user's password. If the password is correctly entered then the command will continue. If the user enters an incorrect password then the dialog will appear again with a message stating "You have entered an invalid password." This dialog will allow for three attempts to enter the correct password. After the third incorrect entry, a warning message appears stating "You have entered 3 invalid password attempts. Your Adept command has been canceled". After closing this message, the user will not be permitted to invoke any workflow commands until they log out and log in again. Active Directory user accounts may become locked out by the domain after numerous failed attempts; contact your network administrator for further details. Canceling the dialog box will return the user to Adept, but will not retain any document selections.

A password must be entered whether Adept is configured for Adept or Windows Domain authentication. The Windows Domain account password will be required when using Active Directory accounts. In environments where SSO is configured, users must enter their Adept password. Windows passwords are case-sensitive; Adept passwords are not case-sensitive.

Configuration

This functionality is enabled by default when the Approval Authentication PlugIn is first loaded. The configuration applies globally to all users and all workflows. When this PlugIn is loaded and turned on, all users must enter their password when any of the above workflow commands are issued. If this PlugIn is disabled or not Loaded on Startup, no users will be prompted to enter a password when invoking the above workflow commands.

Please note that in environments where SSO is configured, each user account that may use the Desktop client must have the value "Adept" populated in the Active Directory Domain field of the user profile.

Navigation: Plugins >

AutoName Overview and Installation

The AutoName PlugIn will automatically generate names for new documents. Each predefined name format consists of one or more segments, in any order, that together create a document name to satisfy a variety of standard requirements. The segments can be based on user interaction, automatic increments, and fixed elements.

In addition, you can create a link between the segment value and an Adept field. When you do so, the value of that segment is automatically written into the field. This is useful because after AutoNaming a document, you will be able to search the database for that value or sort a column based on it.

After the AutoName PlugIn is installed and configured by the Administrator, users can initiate it by selecting the AutoName button in the Adept New document, Rename, and Copy dialogs.

Note: *Extreme caution must be used when making edits to restricted lists due to the ability for Adept to include these in the configuration of AutoName. It is the responsibility of the person making edits to ensure that those edits do not create incompatibilities with the usage of AutoName.*

Definitions

Format – A format is the rule you create for building up a document name. The format consists of a list of segments. When you select a format, it will be used to generate the names of new documents.

Segment – the PlugIn generates a document name by stringing together a sequence of segments. There are 6 types of segments. These can be strung together in any order.

To load the PlugIn, select the Administer PlugIns command on the System tab of the ribbon menu and locate Adept PlugIn for AutoName. For details, see the topic [Administer PlugIns](#).

[Next Topic: AutoName: Create/Delete Formats](#)

Navigation: Plugins >

AutoName Create/Delete Formats

To configure the PlugIn, select the Configure PlugIns command. You must be an Adept Administrator to access this command.

- Click OK to save changes
- Click Cancel to close and dismiss changes

Note: *You can sort the list of formats in ascending or descending alphabetical order by right-clicking on the list. From the context sensitive menu, select a sort-order option. This order defines the order users will see in the dialog when using the AutoName feature.*

To Create a New Format

Click “New” to create a new document naming rule. The first thing to enter is the name. Allowable names can include alpha-numeric characters, excluding special and invalid characters as defined in the Adept help document “Gatekeeper: Verify Name”. The name can be up to 32 characters long.

Enter a name and click OK or Cancel. When you click OK, you are taken to the Edit AutoName Format dialog where you can add segments. You must have an AutoGenerated segment before you can click OK to complete your AutoName format unless you have checked the option "Allow Format Without AutoGenerated Segment".

Edit or Delete

The Edit and Delete buttons become active when an existing format is selected in the list of formats. To edit or delete an existing format, select the format and click the appropriate button.

Disable/Enable

You can select a Format and click the Disable button. A Disabled AutoName Format will not be available to users. You can enable it by selecting it and clicking the Enable button.

[Next Topic: AutoName: Edit Format](#)

Navigation: Plugins >

AutoName Edit Format

To edit the Format, select the format name, and then click the Edit button. A dialog box shows the current definition for the selected format.

A completed AutoName format consists of a series of segments. You can see the entire AutoName the way it will be generated and also edit each individual segment.

Below the 'Max. Name Length' display is a drop down used to associate the final document name, minus any extension, to an Adept database field.

Note: *Within AutoName and most of the segments is the ability to associate the segment to an Adept data field. Adept data fields are populated by the AutoFormat information. Any existing data in an Adept data field will be overwritten. Adept data field content is never used as input to an AutoName format segment.*

The top of the dialog displays the format name, a preview of what the completed name will look like, and its length in number of characters. The dialog lists all the segments that comprise the format. In this dialog, the Adept Administrator can add a new segment, edit an existing segment, delete an existing segment, and move up or down the definition segments relative to each other.

Every AutoName Format must include an AutoGenerated segment. The OK button is not activated until the format contains such a segment or the option is checked for "Allow Format Without AutoGenerated Segment".

By enabling the Force to Uppercase option, the entire document name will be forced to uppercase when the user executes the AutoName PlugIn.

[Next Topic: AutoName Create/Edit Segments](#)

Navigation: Plugins >

AutoName Create/Edit Segments

When you select an existing AutoName Format, you can add new segments or edit existing ones.

Following is a description of the six segment types. All of these tabs include a Name field, and some include a place to add an Associated Adept field.

Name

Give each segment a name. The name will help you keep track of the segments so you can sequence them together in the desired order.

Associated with an Adept data field

Some segments can be associated with an Adept field. When you select an Associated Data Field, the data you enter into the segment will be copied into the Adept field when you create a new document.

Note: *To ensure control over Restricted Value fields, it is not advisable to associate a Free Text segment with a Restricted Value field.*

Note: *Although Adept permits associating segment values with fields defined as Restricted, Required, and Related, resulting behavior can be unpredictable. It is the responsibility of the administrator to ensure that those associations do not create incompatibilities with the usage of AutoName.*

To relate this segment to an Adept field, select a field from the dropdown list. If you associate this segment to a numerical Adept field, you cannot type alphabetic characters into the segment. When you select the associated Adept field name from the dropdown list, if the Segment Name is blank, the Adept field name is copied into the name to be used as a default for the segment name. You can always edit the Segment Name field to suit your needs.

AutoGenerated Sequence Tab

The AutoGenerated definition segment automatically generates a number by incrementing the previous value. The AutoGenerated Sequence is recommended. You can not complete or save an AutoName format without at least one AutoGenerated Sequence unless you have checked the option "Allow Format Without AutoGenerated Segment."

Associated Data Field: When you select a field here, AutoName will write the calculated value for this segment into the associated field. So if AutoName generates 372, that value will be entered into the segment, as well as written to the data field, in this example, Drawing Number.

Note: *If using AutoName and creating a new document "Out from Library", any associated data fields populated by AutoName will be on the resulting Out document's Data Card only. The In or Hold document's Data Card will not have its data fields populated.*

Length indicates the total number of characters allocated to this segment. If the "Zero-pad" option is enabled, this segment will automatically insert leading 0's in front of the generated number. If this option is not enabled, the number will only take up as many places as are needed.

Range: Insert the minimum and maximum. The first time a number is generated, it will add the step size to the minimum except if the minimum is zero.. For example, if the minimum is 0 and the step size is 1, the first document will use 0. If the minimum is 1 and the step size is 1, the first document will use 2. Every subsequent number will add the step size. If the generated number exceeds the maximum value of the range, an error will result, and you will need to see your Adept Administrator.

Step size: This is the number that will be added to the previous number to arrive at the new number. The default size for the Step is 1.

Note: *When using a step size other than 1, the resulting values generated may be different from what is desired or expected. You should test your AutoName format to ensure the resulting filenames are as desired and making adjustment in the AutoName format as needed.*

Zero Pad: When you enable this option, the auto-generated number will be padded with leading 0s so the length of the string is always the maximum length allocated for the segment. So for example, if AutoName generates the number 372, and Zero Pad is checked, then the value 0372 will be used for the segment.

Delimiter Tab

The delimiter definition segment requires that you give the segment a name.

In addition, you must enter the delimiter character.

The delimiter is limited to a single character such as underscore or hyphen, and must not include any of Microsoft Windows invalid characters (/ \ : * ? " < > |). Adept will reject any invalid or special characters.

Fixed Text Tab

A Fixed Text segment consists of a string of characters that you set during configuration. When the user creates a new document, this string is inserted into the document name.

The input is limited to alpha-numeric characters and is validated against Microsoft Windows invalid characters (/ \ : * ? " < > |) and Adept's known list of invalid or special characters.

Free Text Tab

A Free Text segment lets the user type in any text when creating the new document. The input is limited to alpha-numeric characters and is validated against Microsoft Windows invalid characters (/ \ : * ? " < > |) and Adept's known list of invalid or special characters.

Maximum Length

A maximum length must be defined for the free text input. If the "Max Length Required" option is enabled, the user must use all the available characters based on the maximum length. The maximum length for any Free Text segment entry is 32 characters.

Note: *Due to a restriction when storing the default value, a maximum of 31 characters will be stored. When using the AutoName format's Free Text segment to create a new document, the full 32 characters can be entered.*

Defined List Tab

The defined list definitions segment will allow the administrator to type in a list of values in a dialog box.

This segment lets the user select a word from a defined list. It is like the Restricted Segment, with the difference that a Defined List is created by the Administrators when configuring AutoName, while the Restricted List is created in Adept and is available for other Data Cards.

When the new document is being created, the user will be able to select one of the text items from this list, and that item will be inserted into this segment.

Note: *Any value in this list may exceed the maximum value that can be stored in the associated data field. In that case, the stored value will be truncated in the associated data field.*

Restricted List Tab

The restricted list allow users to pick a value from a list that has been defined in one of Adept's Restricted List fields. When you associate this segment with an Adept Restricted Field, the values from that Field are displayed. Select one as a default value. Select one of these to set the terms

[Next Topic: AutoName Operation](#)

Navigation: Plugins >

AutoName Operation

Accessing any AutoName format is accomplished by creating a New document or using the Copy or Rename commands. Selecting the New command opens the Create New Documents & Records dialog where you have the option to click the AutoName button. In the Copy and Rename dialogs, the AutoName button is available to assist in providing a new name for the selected file. If you click this button, the AutoName dialog will appear and allow you to automatically generate the name, which will then be inserted back into the New/Copy/Rename document's name. The actual appearance of segments will vary depending on how the Administrator set up this AutoName format.

Note: *although you may select documents in the list when copying and renaming, the AutoName selection will be applied to all documents in the list regardless of selection.*

Note: *If a configured AutoName format is not displayed in the list, please notify your Adept administrator. They must open the AutoName configuration dialog and select OK to migrate and re-save all formats.*

At the top of the dialog box is a representation of the document name with default values in places that require user input. The user must now complete any required segments that require typing in free form text or selecting from a drop down list. Once all the necessary information has been entered, the OK button will become active. Selecting the OK button will complete the command.

At any time, the user may select the Cancel button and the dialog box will be dismissed without any changes.

If you check the option to create a series of documents, only the numeric portion of the document name will be incremented. All other aspects of the document name, including any free text or restricted list text, will be used for all created documents.

When the AutoName document name is generated, the segment values are saved to the Adept Fields you have associated with the segment. If any of these fields are Extraction fields, then the value saved into the Adept Field will also be written out to the associated document. This will be done while still in the user work area so that Update Document permissions are not required. This will permit the population of the Adept Data Card data fields and mapped document attributes/properties via input to the AutoName PlugIn.

AutoName conditions: Multiuser

AutoName could be started by more than one user at the same time. The number displayed in the dialog is not committed to the database until the user selects OK. This creates the possibility that the number displayed in the preview will not be the same number as the number given to the actual document.

For example, two users could have the same preview number but only one of them will actually get that number. Or if a user defines a series of numbers and a second user reserves a number, there is a chance that the second user may get a number in the middle of the first user's series. The first user's series would skip that number.

AutoName conditions: Maximum reached

When the auto-generated numeric sequence reaches the maximum of the range, the next time a user attempts to create a new document using this format, a message is provided, notifying the user to contact their Adept Administrator to extend the range of the name or to suggest using an alternative format. Picking OK to this message will temporarily remove the format from the available formats list in AutoName and the user can cancel the Create New Documents & Records dialog and notify their Adept Administrator or select a different format.

Duplicate document names

Created document names are checked to be sure they are not duplicates within Adept. Should the generated document names contain one or more duplicate names, the user will be notified and given the option to continue with the generation of document names. In the case where one or more document names of a generated sequence are duplicate, the user will not be notified specifically of which names are duplicates.

Note: *If using AutoName and creating a new document "Out from Library", any associated data fields populated by AutoName will be on the resulting Out document's Data Card only. The In or Hold document's Data Card will not have its data fields populated.*

[For more information see AutoName Overview and Installation](#)

Navigation: Plugins >

AutoRevision PlugIn

Overview:

This PlugIn allows the user to automatically increment a document's field. You can set up the PlugIn so it operates on documents within particular Libraries and on documents with particular extensions. This feature supplements Adept's built-in Versioning increment which automatically increases Adept's built-in version number. You can set it up to increment alphabetically or numerically.

You can configure this AutoRevision feature to increment after the document is Checked In, Checked Out, Check Out from In, or Final Approve (returned to Library).

Installation:

This PlugIn is already installed. To Load it, select the Administer Plugins command. For details, see the topic on [Administer Plugins](#).

Configuration:

Configuration of this PlugIn can be done by an administrator. The Configuration screen is found under the Configure Plugins command

Libraries

The list displays all Libraries. The Libraries you select in this list will be operated on by the AutoRevision PlugIn.

Note: *You can only select Checked Libraries to be operated on by this PlugIn.*

Increment AutoRevision on

Select the Adept operation that will trigger AutoRevision to increment the revision designator.

- Check In
- Check Out
- Check Out from In
- Final Approval

Select Field for AutoRevision

Select the Adept field where you want the AutoRevision number to be saved. You will select it from a dropdown list of available Adept fields. You can pick one field of either character or numeric type. A numeric field can only hold numeric designations, whereas a character field can hold either numeric or alpha.

Only character and numeric fields of the required size are available in the drop down list. Fields that are designated as protected, indexed, restricted list, or extracted can be used and will be available in the list. Care must be used when selecting a field that is a restricted list or an extracted field to ensure the revision scheme chosen matches the value desired. When selecting an extraction field, the PlugIn will include an Adept Update Document command which may result in the document's mapped attribute/property being updated.

Choose AutoRevisoning Scheme

Choose whether you want the revision value to be alphanumeric or numeric.

Set to alphanumeric

A will increment to B, B will increment to C, etc.

1A will increment to 1B, 1B will increment to 1C, etc.

A1 will increment to A2, A2 will increment to A3, etc.

When A9 is incremented it goes to B0, B0 increments to B1, etc.

After Z, the next Revision designation is AA. After AZ, the next designation is BA.

Note: *I and O will be skipped.*

Alphanumeric is limited to a maximum of 2 characters

The last increment will be either Z9, 9Z, or ZZ depending on the sequence used.

The Adept field used must be a character field with a width of at least 1. An Adept field larger than 2 can be used but the PlugIn will only use 2 characters.

An alpha character must be used. Trying to use only a number value such as 1 will be incremented to A.

Set to numeric

1 will increment to 2, 2 will increment to 3, etc.

11 will increment to 12, 12 will increment to 13, etc.

1A will increment to 2 because it does not recognize the alpha character.

When 99999 is incremented it goes back to 1.

Numeric is limited to a minimum of 5 characters.

The Adept field used can be a numeric field having a minimum width of 5. Any numeric field with a scale greater than 0 will not be available in the list.

The Adept field used can be a character field having at least 5 characters.

Note: *If you switch this value, your previous Revision value will be reset to the beginning. So for example if your AutoRevisoning scheme is Alphanumeric and the revision letter for nozzle.dwg is "D," if you change the AutoRevisoning Scheme to Numeric, the next Revision will be "1".*

Apply AutoRevision to

Select the extensions of documents that will be affected by this PlugIn. Pick one of these three methods.

- All Document Extensions
- Document Extensions Listed
- Document Extensions NOT listed.

Two of these methods require that you build up a list of extensions. To add extensions to the list, click the '+' button. To remove extensions, click the '-' button.

Operation

After the AutoRevision PlugIn has been configured, no further action is required. A document from one of the designated Libraries, with one of the designated Extensions, will have the value in its specified revision field automatically incremented when the selected action has been performed.

Navigation: Plugins >

Bill of Material Automation

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

Definition

This PlugIn uses the part and assembly information from the Adept Document Dashboard to create a list in an Excel spreadsheet, including the count or quantity. This bill of material output is known as an "RB BOM". You can also use an existing SOLIDWORKS bill of material placed in a drawing or assembly document to create a bill of material in an Excel spreadsheet. This bill of material output is known as a "Document BOM" and is only available for SOLIDWORKS documents with a SOLIDWORKS bill of material (not an Excel-based bill of material) saved within the document.

Note: To use a SOLIDWORKS BOM, you must have either SOLIDWORKS or SOLIDWORKS Explorer installed on the workstation.

Initial Setup

If you were using Bill of Materials in Adept previous to Adept 8, when you upgrade to Adept 8.0 or higher, before using the Bill of Materials Automation PlugIn, you must re-extract all Inventor, SOLIDWORKS, and AutoCAD documents. This is because until Adept 8, Synergis Adept did not store the Count. A new Extract or Synchronize is necessary in order to allow Adept to populate the Count value.

Count or Quantity (RB BOM only)

The Count is based on the number of instances that have been inserted into the AutoCAD, SOLIDWORKS or Inventor document. This number can be modified by settings within the CAD application.

- SOLIDWORKS

Parts or assemblies will not be counted if the Display State is Suppressed, or if the property is set to "Exclude from Bill of Materials" or if it is a Virtual Component.

Known Issue: When you edit any SOLIDWORKS Configuration you must also activate the others

When using Bill of Material Automation with SOLIDWORKS configurations, when you make a change to a SOLIDWORKS configuration that would alter the Bill of Material output (e.g.: add a part, suppress a part, etc.), you must activate every configuration in the document, even if you did not edit it. Failure to do so will result in inaccurate quantities in the output.

- Inventor

Parts or assemblies will not be counted if they have a state of Reference or Phantom or if it is a Virtual Component.

- AutoCAD

If a document is Xref'd, Count will indicate the number of times it is inserted. Overlays and underlays are always "1."

You can view the Count in the Adept Document Dashboard by clicking the Drawing Info tab. You cannot see the Count on any Adept Data Card or Column, other than on the Drawing Info tab.

Operation

To access this command, select a document and then select Bill of Material from the Collaborate tab. This command acts on the currently selected document. The document may be selected in any Adept window. If your selection contains multiple documents or no documents a message is displayed:

You can only create Bill of Material output when you have rights to all children (RB BOM only)

To create a Bill of Material, you must have the appropriate Library Access Rights that entitle you to at least view all the children of the parent. If you do not have sufficient rights, you will see an error message. In no circumstances will you be able to obtain more information than you are allowed to obtain when using the Document Dashboard or the Adept Data Card.

Select BOM Type

If you have selected a valid document, a dialog will present options for you to specify the source and type of bill of material.

If selecting any document other than a SOLIDWORKS document, your only option will be to create the bill of material using Adept relationships. If you have selected a SOLIDWORKS assembly or drawing document, you will have the option to use the Adept relationships and the two additional options specific for SOLIDWORKS. Select the option you desire and select OK.

Step 1: Configure Creation when Using Adept Relationships

After you run the Bill of Material Automation PlugIn, a wizard will present options that control the formatting of the output document.

Set Columns

In the grid on the Wizard, define the columns that will appear on the report. If you want to include the count in your report, you must add a count (or quantity) column in this wizard. You may define the exported columns in three different ways.

- One by one, right-click on each column heading and from the drop-down list, select an Adept field to use for this column and then go onto Column B, C, etc. and do the same thing.

As you add fields, Row 1 (the column header) will display the Adept Display name for each field. Once a column is added, the Insert Column and Remove Column selections will also become available on these configured columns. Inserting a column adds a new column before the one you are on. Removing a column deletes this configured column.

Note: Column headings are editable, so if the Adept Data Field Display name is not what you want to see in the exported data, you may edit the text before you export.

- Choose an already designed [column set](#). This is also available from the right-click menu.
- At the bottom of the dialog under the Restore Settings section, select the option to Use Previous Settings.

This option allows you to browse out to an XML document that contains settings that were saved from a previous session of the Bill of Materials Automation PlugIn. This XML document sets all options and can be created by first manually setting up the dialog once and then saving the XML document. (The Save option is located on Step 2 of this Wizard.)

Suppress Children with Zero Quantity

If the count is zero, this option removes the item from the Bill of Materials.

Display only 1st Level children

In the Children section of the dialog, the user may specify if only the first level children of the selected parent are included in the output, or if the entire children multi-generational structure is included. There is no option to include only a certain number of children levels. It must be either first only or all levels.

Suppress Document Extensions

Choose this option to turn off the display of document extensions in the list and in the exported spreadsheet.

Indent Children

The Indent Children option controls whether the output is indented based on children level or held at the same indentation as the parent. If the Indent Children option is not enabled, all rows of information will be left justified.

If Indent Children is enabled, the Document Dashboard Export would output into Column A but children records will be indented based on their position in the hierarchy.

Information Source

This option allows you to select which information you want to export:

- When "Work in Progress" is selected, then the most current version of the children (regardless if they are approved or not) will be shown in the exported spreadsheet.
- When "Library" is selected then the latest approved version of the children will be exported.

Export Format

Select one of the Export Formats: Excel, Text (Comma delimited), and XML.

Restore Settings

This option allows you to browse out to a pre-configured XML document to import column and other settings you saved from a previous Bill of Material Automation session. Creating these documents is explained later in this document.

Step 1: Configure Creation when Using SOLIDWORKS Configurations

If you selected the option to use SOLIDWORKS configurations, the dialog presented has an additional option for selection of one or all configurations to be output.

By selecting a specific configuration, the output will include bill of material information based on that configuration. Other than the specification of a configuration, all other options in this dialog are the same as the previous section.

Step 2: Configure Output Settings

Clicking on the Next button brings you to Step 2 of the Bill of Material Automation Wizard.

Create Relationship of Spreadsheet to Selected Document

This option allows you to set the relationship of the exported XLS spreadsheet document. It can either stand alone with no relationships, or can be made part of a relationship with the document it is reporting on. Choose Parent to make the spreadsheet the parent of the selected document, or choose Child to make the spreadsheet the child of the selected document.

If you create a relationship, you can set the type of relationship to Float, Fixed, or Dock. At first, the option will be set to the current default. You can change it manually.

Spreadsheet Formatting Options

The spreadsheet options let you set basic formatting on the Excel spreadsheet.

Grouping

Activate Excel Grouping to group all the 1st level only children.

Center Cell Data

This option sets up the alignment in all cells in the Excel spreadsheet to be center justified.

If you choose the "Indent" option (available on page 1), then Column A will not be center justified but will remain at left justified so the Indent works.

AutoFit Columns

will automatically fit the column width to the size of the maximum data that is being placed into this field.

Underline and Bold Column headers will underline and bold the Adept display names used as the column headers.

Worksheet Name must be filled in and will name the tab for sheet 1. The default will always be the name of the selected document minus the extension.

Spreadsheet Name

Supply a name for the spreadsheet. The default will always be the name of the selected document with an XLS extension.

Location

Select an Adept Work Area where this Excel document will be saved.

Save Current Settings

Once the user sets configuration options and column headings to be used for output, the user may save this configuration in a document that can be re-used at a later time. The output format will be an XML compatible document. This XML document can be distributed across your organization so that all users can export in the same fashion. The XML document you save in this step can be imported later to reproduce the same Export definition. To locate the document, use the browse button. (...)

Finishing the Output

By selecting Finish, the output will be generated as specified and a message will be displayed

Step 1: Configure Creation when Extract from SOLIDWORKS

If you selected the option to extract from SOLIDWORKS, the dialog presented allows the user to select the SOLIDWORKS bill of material or revision listing to export or print.

Data Source

This option allows you to select the source of data for exporting or printing. Once selecting the appropriate radio button, the drop down will list each SOLIDWORKS bill or material or revision list contained in the document. If nothing appears in the drop down list, then there is no item in the document for export or printing. Once a bill of material or revision listing is selected, the grid will be populated with the information from the item in the document. An checkbox is available to include/exclude user information in the output header.

Export/Print

Selecting Export/Print opens a preview dialog where you can define many options via the toolbar for the output you desire.

All options in this dialog are part of the programming toolkit used by this program. You can save your settings so that you can easily apply them to any future output\; print your output, or export your output to a multitude of formats. The output document can be saved to any folder and you can create a relationship between the output document and the source document if so desired.

Navigation: Plugins >

Children Check Out PlugIn - Operation

Select documents from the Adept FileGuide or Search Results. Then select Check Out. When the Children Check Out PlugIn is enabled, the Children Check Out dialog appears.

When Children Check Out is not enabled, you will see the default Check Out dialog, which does not offer the option to check out children.

Children Check Out displays the Library Name, the Adept Status, and options that allow you to either Check Out or Copy the selected documents and their children. You can check either Check Out or Copy but not both. If you choose Copy, you can enter a value into Rename.

Note: *You must type the entire name, including the extension.*

The new name will take effect when you execute the command.

Important Note: *If a child of one of the selected documents is also included in the selection set, it will appear in the tree at the root level since it is a selected document. You will not be able to select the instance that is a child, because you will control the instance that is at the root level.*

Documents to Display

The documents initially selected in Adept when you choose Check Out, will be displayed in the Check Out dialog. The three options under the Documents to Display group may modify this list.

Note: *If a document is not listed, you cannot act on it. You can only copy or check out documents displayed in this list.*

Children

None

When this option is enabled, the display includes only the documents you selected.

First Level

When this option is enabled, the display includes the documents you selected and all of their first level children

All

When this option is enabled, the display includes the documents you selected and all generations of their children

Parents

In some cases you might want to display the parents of selected documents. This is useful when you want to check out drawings (parents) associated with parts and assemblies (children). When you indicate a document extension under the Parents option, this command will display parents with the specified extension.

The gray text in the background is there to show the format of the extensions. If you add more than one extension, separate them with semi-colons. You must precede each extension with a period. For example:
.DWG;.IDW

After you enter an extension in this field, click the refresh button to the right of the Parents field to refresh the display to include parents.

Exclude

Note: *You can only check out documents that are displayed in the tree. By excluding them from the list, you are removing them from the check out or copy out operation.*

Filtered

When this option is enabled, the Children Check Out dialog will no longer display children located in filtered Libraries. See the [Library Profile](#) for more information about Filtering. When you check or uncheck the Exclude Filter option, Adept must repaint the Children Check Out dialog, at which time all check boxes are reset.

Versioned

Don't include versioned documents in the display (only include the current version)

Manual

Don't include children whose association is based on manual relationships

Documents to Check Out or Copy

The "Documents to Check Out or Copy" Option affects all rows in the dialog. For example, in "Documents to Check Out or Copy", if you select Check Out from the dropdown list, and All from the option boxes, then all the documents in the entire list will be checked as well as all their children.

The "Documents to Check Out or Copy" options will override any individual selections you have already made. After setting all these options, you can manually change the checkboxes on any row.

Note: *Documents to Check Out or Copy options only act on documents already displayed.*

None: This clears all selections and blanks out all "rename to:" info

First Level: This applies the action you selected in the dropdown, either copy or check out, to all first-level documents that are already displayed. It will also include the documents you initially selected. All others will be cleared.

All: This applies the action you selected in the dropdown, either copy or check out, to all displayed documents.

Destination Work Area

In this drop down, the user will select the target Work Area for the selected documents from a list of their currently available Adept Work Areas. The list of Work Areas will be shown in the same format as the Work Areas are shown in the Adept Desktop Client. If you have several Work Areas with the same name, you can change this list to reflect the path. To do so, open the Work Area Window in Adept, and check the option that says Paths. With this option enabled, the Child Check Out drop down list will show the Work Area Path instead of just the Work Area name.

Adept Library Access Rights and Status Implications

While this PlugIn automatically finds and presents the children to the user, the Adept status and Library Access Rights determine what the user is actually allowed to do with documents. Adept Rights will apply to these children documents as well. The Adept program itself will control what the user can select prior to issuing the Check Out command. Each of the child documents will be evaluated to determine exactly which actions the user has the rights to perform on the documents. The relationship between Adept Rights, status, and the action of this PlugIn are described in more detail below:

Children in Libraries to Which the User Has No View Rights

It is possible that the child document could reside in a Library to which the user does not have View Rights. The user will not see those children.

Unresolved Children Records

Children documents that are unresolved do not have a corresponding record in the Adept database and therefore cannot be copied out or checked out. If an unresolved children document is included in the tree it will be disabled.

Documents with status of In

When a document has the Adept status of In, Adept will evaluate the user's Library rights for that document within that Library. If a user has Check Out Rights then the default action for that document will be set to Check Out and the user can change it to Copy. If the user does not have the Right to Check Out but does have the Right to Copy, then the default action for that document will be set to Copy. If the user does not have Check Out or Copy Rights then the document will be disabled and the user cannot include it in the Selection Set.

Documents with status of Out

When a document has the Adept status of Out then it will be evaluated to determine if it is:

- out to the current user or
- if the current Work Area is a Shared Work Area, it will be checked to see if this document is out in the current Shared Work Area

If either of these conditions is found to be true then the document will be disabled and the user cannot include it in the selection set. If this is not true then the Library Rights will be evaluated to determine if the user has the ability to copy the document. If the user has Copy Rights and the user chooses to include this document in the selection set then it will be allowed to be copied, but not checked out.

Documents with status of Arc

Documents with an Adept status of Arc will be disabled as you cannot check out or copy documents of this type.

Documents with status of Versioned

Versioned documents cannot be checked out of Adept. When a document has the Adept status of Versioned then it will be evaluated to determine if the user has Access Rights to copy this document. If the user has rights to copy this document and the user includes it in the selection set, it will be copied out to the selected Work Area. If the user does not have the Right to copy this document it will be disabled and cannot be included in the selection set.

Documents with status of Hold

When a document has the Adept status of Hold the Adept Workflow for the document will be evaluated to determine the user's rights to the document.

Documents with status of AssignHold

When a document has the Adept status of AssignHold the Adept workflow for the document will be evaluated to determine the user's abilities to the document.

Documents with status of New

When a document has the status of New, it will be disabled, since this type of document cannot be either checked out or copied.

Documents with status of Duplicate

When a document is found to have the status of Duplicate it will not be either checked out or copied.

Checking Out Children Documents on Workflow

Adept will evaluate the rights of each child document that is included in this list. This evaluation will include the rights to check the child out from a Workflow step. If the user has the right to Check Out the document, then the user can include this document and the Check Out will be the default selection. The user can change this to Copy instead. If the user does not have the right to Check Out the document but does have the Copy Rights, then the user can include this document and the Copy will be the only selection active. If the user does not have Check Out or Copy right to the document then the Include control for this document will be disabled.

Completing the Command

Once you fill in the grid with the selection, click OK. The program progresses thru the Check Out. If it tries to check out a document that already has a document of the same name in the Work Area, it displays the following message.

The user selects one of the options, and the command continues. All documents that can be checked out are checked out.

Prior to completing the command, the Work Area that is selected will be evaluated to make sure that filenames included in the selection set are not already present in that Work Area. If any duplicated filenames are found, a dialog will appear showing the filenames which will be duplicated and asking the user how to proceed. The user can choose to overwrite the duplicate, or else keep the duplicate and skip this record. The option lets you pick yes or no for each duplicated document, or yes to all or no for all.

If no duplicated filenames are found then the selected operations on the selection set will be performed and the records will be checked out or copied out as you have indicated in the dialog.

Stop at AutoCAD Overlays affects the list of children in Children Check Out

The list of documents displayed by the Children Check Out PlugIn is influenced by the state of the "Stop at" options in the Workstation tab of the Adept options dialog. When these options are enabled, Children Check Out will stop searching for children when it encounters one of these objects. When disabled, all children will be included in Children Check Out. For more information, see the topic [Options: Workstation](#).

Note: *In this release of Adept, the Children Check Out command does not use the options to Stop at SOLIDWORKS In-context Relationships or Stop at Inventor Substitute References.*

Navigation: Plugins >

Children Check Out Overview and Configuration

Note: *To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.*

Note: *You can turn off operation of this PlugIn from your own Workstation by selecting from the Edit Menu, the PlugIn*

Overview

When a user checks out documents, the "Children Check Out" PlugIn will list the children of the selected documents in the "Check Out Documents" dialog. The children in this list can either be from relationships that were automatically created in supported CAD applications such as AutoCAD, Inventor, and SOLIDWORKS or the children can be from relationships that were created manually, using the Create/Edit Relationships dialog.

Enable/Disable the PlugIn on a Workstation

Under Workstation Options for Children Check Out there is a checkbox to Include Children. When this checkbox is checked the Children Check Out PlugIn is active at check out. When it is unchecked the Children Check Out PlugIn is inactive. Also available in this dialog is an option to make the radio button and checkbox options persistent.

Configuration

When configuring this PlugIn, the Adept Administrator will choose one or both of the options to indicate which types of relationship to be included in the search for the purposes of checking out children with parent.

- Extracted relationships only
- Manual relationships only

Also, the Adept Administrator can configure this PlugIn to be engaged for specific groups, or for all users of Adept.

Navigation: Plugins >

Copy Fields To Parent: Overview & Config

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.

The Copy Fields to Parent PlugIn will copy Adept metadata from one or more Data Card fields of a child into the Data Card of the corresponding parent.

Note: This PlugIn is specifically designed to help manage the properties of the drawing document associated with a model. In Adept, the drawing document is the parent of the model document.

In SOLIDWORKS and Inventor, to create a 2D representation of your model, you typically generate a drawing document (IDW for Inventor or SLDDRW for SOLIDWORKS), and add a title block to the drawing. To reduce manual data entry, it is customary to automatically populate this title block with information you already entered in the properties of the model. For example, you may have already entered Revision “A” into the model’s property, so you want the title block of the drawing to automatically reflect this Revision letter without retyping it.

Both SOLIDWORKS and Autodesk Inventor allow you to set up an automatic link from the property in the model to the text field in the title block. The issue in Adept is that SOLIDWORKS and Inventor create this link in such a way that it is invisible to Adept, and so, while Adept extracts the property (in this example, the Revision letter “A”) from the model, Adept does not see any value for this property in the drawing.

Copy Fields to Parent automatically copies specified properties from the Data Card of the model to its corresponding field on the Data Card of the drawing.

Optionally you can Update Document to copy data into Drawing’s document property

After this PlugIn copies data into the drawing’s Data Card, you can optionally instruct it to perform an Update Document command, and push the data from Adept’s Data Card back into the property of the drawing document itself.

Note: In both SOLIDWORKS and Inventor documents, if the Property does not already exist, the PlugIn will create it and copy the value from the drawing’s Adept Data Card to the document property.

Configuration

You must be an Adept Admin to configure this PlugIn. To do so, access the configuration dialog from the Configure PlugIns command. The Copy Fields to Parent Configuration dialog opens:

- This dialog has a section (on the left) called Copy Fields to Parent that is a listing of checkboxes in alphabetical order of all available custom data fields that the Admin can select to have data copied from a child to a parent document Data Card. Scroll through the list with up or down arrows, or drag the scroll bar. There are no restrictions on the types of custom fields that can be enabled (i.e., data, date, extracted, numeric, restricted, text, etc.)
- To select the field, simply click the checkbox. Click again to uncheck the field. Once the Admin clicks on the desired field, it is highlighted indicating field selection.
You can right-click in this list of fields and select "Check All".
- A control box lets the Admin set a Maximum Number of Records to be Processed per execution of the command from 1 up to a 1000
- Choose which document type you intend to affect
SOLIDWORKS: Copy from *.SLDASM and *.SLDPRT to *.SLDRW
Inventor: Copy from *.IAM and *.IPT to *.IDW and *.DWG
- Update Extracted Fields in Parent Document
Perform Update Document in Parent
Overwrite Existing Data Card Metadata

Note: *The Admin can select any or all of these options as required*

OK Button:

- The OK button remains grayed out and inaccessible until valid choices in all configuration fields are made. At least one data field must be selected for the OK button to become functional.
- Clicking the OK button applies the selected options

Cancel:

- Click Cancel to discard the selected options. After clicking Cancel, there is no additional confirming dialog.

Navigation: Plugins >

Copy Fields To Parent: Operation

To access the Copy Fields to Parent command, select it from the Edit tab and select Start. It will be applied to all the documents you have selected at the time of execution. Having no documents selected will cause a dialog to let you know that to operate the command, you must select documents first.

After the command is executed, it gives a confirmation dialog. To find which documents were processed by running this command, look in the log document in the following directory:

C:\AdeptSupport\TmpFiles\[database]\[Username]Log.txt.

Executing this command applies only to the documents you have selected in any Adept window. The documents you select for this operation will be checked, and you will only be able to change ones for which you have the appropriate Library Access Rights. All documents that are processed will retain their changes and those changes cannot be undone.

Note: While this PlugIn is executing, the mouse cursor will remain active. DO NOT use the mouse to make any selections in the Adept window until the PlugIn completes its execution and you receive the completion dialog message.

Note: It is highly recommended you select the parent document(s) for execution of this PlugIn, rather than selecting the child document(s). This provides a more accurate selection of the documents that will be affected.

As the command executes:

- For each selected document, the PlugIn checks the document extensions. For every selected model, the PlugIn looks for a parent that is a drawing. For every drawing, the PlugIn looks for a child that is a model.
- If a valid parent document and a valid child document are found, and the user has sufficient rights to permit the copy, then the data is copied.
- If there is more than one valid parent or child document that meets the criteria, the first one will be used.

Note: There is no way to know which document will be first

If there are no children documents or appropriate parent documents with the proper document extension, then no action occurs.

Note: This PlugIn has been developed primarily to handle SOLIDWORKS and Inventor situations in which a drawing lacks document properties needed to fill in a document's Data Card. In the majority of such cases, there will be a single first level child document for the selected parent.

Rights Access

Any user can execute Copy Fields to Parent. However, successful completion of this command is determined by the user's right to edit Data Cards and to perform the Update Document command on the target documents. For example, if a user does not have the right to edit the Data Card of the parent document, then the command will not complete successfully. The same is true if the user wants to perform an Update Document. If a user does not have the proper right to perform the Update Document command, then that part of the command will not complete successfully.

Command Completion

At the completion of this command:

- There is a confirmation dialog and a log document is created:
C:\AdeptSupport\TmpFiles\[database]\[Username]Log.txt
- When the command completes execution, control will be returned back to the user
- All previously selected documents will remain selected

Error Handling

Any errors will be handled similarly to how errors are now handled with the Batch Update and Update Document commands; dialogs inform the user of their rights restrictions. See error examples below.

If a user attempts to execute this command using one or more documents where the user's rights are not sufficient to complete the command, the appropriate message dialog will be shown for that document. Clicking the OK button allows the command to continue execution.

Navigation: Plugins >

Copy Data Card Overview & Config

Overview

The Copy Data Card feature allows you to copy metadata from one Adept record and then paste that data into any number of others. The feature obeys all rights associated with Data Card data. For example, to paste into a Data Card, you must have the rights to edit the card.

The Administrator can configure the Copy Data Card feature to customize its appearance to users. This configuration might restrict access to some options, and force the behavior of others.

There are three such configuration options that control:

- copying memo fields
- overwriting fields that already contain data
- copying into extraction fields

The Copy Data Card function does not have any user interface. It simply copies the data into a buffer. When you Paste Data Card, it will present a user interface that lets you select which field to copy.

Configure the Copy Data Card Feature

Note: *This feature is implemented as a PlugIn. To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable ones you will not.*

To access the Options for this feature, select the Configure PlugIns command. In this dialog, you can set up what options the user will have at run time.

Always Paste / Always Ask User / Never Paste

- Memo Field
- Extraction Fields
- Fields containing data

Note: *Data will always be pasted into blank fields*

Updating Documents after Pasting Extraction Fields

If you use this feature to Paste values into Extraction fields, the modified value in the Data Card will no longer match the corresponding value in the document. In that case, you can cause Adept to perform an Update Document to push the data from the Data Card to the document. To ensure that this happens automatically, set the Update Documents option in the Paste dialog. Then after the Paste is performed, the data will be moved into the document immediately. This operation may take a few minutes, depending on the number of documents and the speed of your server and network.

User Rights Needed to Copy Data Cards

- To Copy values from a Data Card, users only need View Rights
- To Paste values into a Data Card, users need Edit Data Card Rights

- To Paste into Protected Fields, users need Edit Protected Field Rights
- To Paste into Extraction Fields, users need Update Documents rights

Navigation: Plugins >

Copy Data Card Operation

To Copy Metadata From a Record

1. Select only one record

Only one document can be selected during the Copy Data Card operation.

If you select many documents, an error results.

No data is copied and you must repeat the operation with only one document selected.

2. Select the Copy command in the Data Card panel on the Edit tab of the ribbon.

Selecting this menu item copies metadata into a buffer. If it succeeds, no message is displayed.

To Paste Metadata To a Record

1. Select one or more documents you want to paste into.
2. From the Edit tab, select the Paste command in the Data Card panel.

The resulting dialog offers options. You can copy the memo field, overwrite fields containing data, or write into Extraction fields. Some of these options across the top may be inactive, as determined by the Administrator. The "Select all" option is a toggle. Click once to select all. Click again to unselect all. The Update Document option is only active when you enable Extraction Fields.

Note About Update Document: *If you write into Extraction fields, then the data in your document could be different than the data in your Data Card. One solution to this difference would be to check the Update Document option. If you do so, Adept will attempt to update the field in the document. Keep in mind that if you have pasted this data card into a large number of documents, the update of each document could take time.*

Note: *When pasting to logical fields, the Overwrite option to paste into "Fields containing data" must be used. Logical fields always have a value even if the value is not shown in the Data Card.*

Each available field can be selected to paste, or unselected, in which case it will not be pasted.

If the Paste fails, a dialog will list the documents that were not successfully pasted. You can then proceed, pasting the remaining documents, with the rest or cancel the Paste operation.

Paste error report

Before the Paste operation is initiated, Adept checks to see if this is a legal operation. If so, the operation will succeed with no user interaction.

If the user did not have rights to paste into a field or Data Card, a dialog appears with a list of the error messages. You can either click OK to continue pasting the ones that will succeed or Cancel to stop the entire operation.

Navigation: Plugins >

Print or Publish with PublishWave PlugIn

When the PublishWave PlugIn has been installed and configured on the workstation, and when you have access to the PublishWave Server, you can send documents to the server where they will a) be printed through the native application or b) converted to a standard publishing format (PDF, DWF, or TIF) or c) simply passed through to an output location.

Users can initiate the PublishWave PlugIn by selecting Using PublishWave command on the Document tab of Adept. (The exact menu choice will depend on options selected when PublishWave was configured.)

When users select documents, and then selects the Print PublishWave command, the PlugIn displays a dialog called a Job Request.

This Job Request form lists the documents you selected, and allows you to enter parameters to control the overall job as well as to control the output of each document.

1. At the top of the form, select the PublishWave server.
2. On the right of the form, for each document, select parameters including size, scale, rotation, and location
3. The Device lets you select a printer, or select a conversion format if you are sending to a published document

The bottom parameters control the behavior of PublishToAdept.

When your Administrator has established the PublishToAdept program, you can set the parameters for this action in these fields in order to return your documents to an Adept Library.

Action

The Published document, once it is in the Output Location, is a candidate to be moved by PublishToAdept. This field instructs PublishToAdept to Check In, Copy In, or do nothing to the document in the Output Location.

None

The None option (default) will do nothing and all other settings in this section are grayed out.

Check In

When you select Check In, the published document is checked in to Adept, and the document in the Output Location is removed.

Copy In

When you select Copy In, the document in the Output Location is checked in to Adept, leaving behind a copy of the document in the work area. This will be useful when you want both copies, the one in the Output Location and the one checked into the Library.

Destination

This option specifies where the document will go when it is checked in to Adept. The options in this dropdown are Same Library (default) and Specified Library.

Same Library

Selecting this option indicates the Published document is to be checked into the same library as its source document

Specified Library

When you select Specified Library, the “Library” option becomes active and the user must select from the list

Library

If the user selects Specified Library for the destination, this option lists all libraries the user has rights to check into. If the user selects Same Library, then a dash "-" will be displayed in this area.

Relationship

When PublishToAdept checks the document into an Adept Library, this option creates a relationship between the published document and its source document. The Published document is the one that PublishWave has moved to the Output Location, and the Source is the document that you Published originally from Adept. The options are None, Parent, and Child.

None

If None, then no relationship is made. The default is None.

Parent

This option makes make the published document the parent of the source document.

Child

If Child, then the Published document is Child of the source document.

Include Metadata

When PublishToAdept checks the file into an Adept Library, the default is to give the checked in file the same metadata as the originating file. The “First Document” setting is used to have this occur. Should you want some custom metadata or none at all, those options can be specified and will be used when the file is checked in to Adept.

Metadata

Should you select “Custom” in the Include Metadata column, this option becomes available. You can define specific metadata for any and each Adept custom field. That metadata will be applied to the file being checked into Adept by PublishToAdept.

To learn more about the PublishToAdept options, review the document: PublishWave Server Administration User Guide.

Navigation: Plugins >

Required Fields Overview

Note: To enable or disable Adept PlugIns, see the topic [Administer PlugIns](#). To streamline Adept performance, only enable PlugIns you will actually be using, and disable those you will not.

With the Required Fields PlugIn, Administrators can require that Users complete specified fields in the Data Card before Check In, Check Out or Approval is permitted to continue. This will enforce Company standard data entry, improve the integrity of the database and improve searching. The Required Fields PlugIn integrates seamlessly with Adept's extraction and restricted fields.

Note: Extreme caution must be used when making edits to restricted lists and related fields due to the ability for Adept to include these in the configuration of Required Fields. It is the responsibility of the person making edits to restricted lists and related fields to ensure that those edits do not create incompatibilities with the usage of Required Fields.

Note: Do not configure a field configured as a Related Field as a Required Field. The two field types are incompatible and unexpected results will occur.

The following sections are available:


[Required Fields Configuration](#)

[Required Fields Operation](#)

Navigation: Plugins > [Required Fields Overview](#) >

Required Fields Configuration

Select the Configure Plugins command on the System tab of the ribbon. Then select the Required Fields PlugIn from the list. The following dialog will be shown.



Using this dialog, the Required Field settings are assigned to a library. When Library settings are applied to one library, the settings are inherited by all libraries below it in the hierarchical folders nested underneath it. The settings apply to directories down the tree, until a library is encountered in which different settings are assigned. Those new settings then apply further down the tree until yet another different setting is encountered.

Library Settings

Check the appropriate options to specify when Adept will request the value in the required fields.

Check In	When this option is checked, checking a document in to a Library (unchecked or checked) will trigger Required Fields.
Check Out	When this option is checked, checking a document out of a Library will trigger Required Fields.
Approve (Return to Library)	When this option is checked, approving a document on the last step when it is returned to a Checked Library will trigger Required Fields. Approve is defined as the last approval step where the document's status will change to IN. Any approvals inside a Workflow, where the document's status remains HOLD, will not engage the Required Fields PlugIn.

Required Fields Listing

A listing of all the available Custom Fields is displayed in the Required Fields listing section of the dialog box. Note that System Fields are not included in this list because these fields are not editable by Users. Also, Numeric and Logical fields will not be listed because these field types always return a value even when empty. To select which fields are required, check the box next to each desired value in the Required Fields Listing.

Note: Do not configure a field configured as a Related Field as a Required Field. The two field types are incompatible and unexpected results will occur.

Note: Although Adept permits fields defined as Required to also be configured as Restricted and Related fields, resulting behavior can be unpredictable. It is the responsibility of the administrator to ensure that those fields do not create incompatibilities with the usage of Required Fields.

Apply Required Fields

In this section, you can restrict the type of documents these Required Field rules apply to for the selected library. By specifying the document extensions, you can engage or disengage the Required Fields PlugIn for specific document types, even though they might reside in the same library.

All File Extensions

Selecting this option will cause the document's extension to be ignored and all documents will trigger Required Fields

To File Extensions listed

Selecting this option will cause Required Fields to be triggered for any document with an extension listed.

To File Extensions NOT listed

Selecting this option will cause Required Fields to be triggered for any document with an extension not listed.

Use the "+" () and "-" () buttons to add or subtract extensions to the list. The extension may be added with, or without the preceding period. The dialog will add the period if it is not found and will convert the extension to uppercase. You may enter more than one document extension.

See Also

[Required Fields Operation](#)

Navigation: Plugins > [Required Fields Overview](#) >

Required Fields Operation

When a command is performed that has been configured to engage the Required Fields PlugIn, Adept verifies that all the Adept data fields defined as 'required' have data present. If not, the User is prompted to complete any fields that are not already completed.

Within the dialog that lists the missing data, the user can edit the required fields. The document will not be moved forward in a Workflow until all required fields are completed.

For Check In and Approve, if the field is an extraction field for a document type that supports Update Document and the User has Update Document rights, the value entered will be updated in Adept as well as written out to the tag, attribute, or property in the document itself.

The Required Fields PlugIn engages only during the specified action (Check In, Check Out, or Final Approve to library) and does not prevent a user with the appropriate rights from editing those fields at any other time.

When files are being processed by Required Fields, the options to Cancel and Cancel All will be presented in the dialog. Selecting Cancel cancels only the current document and allows Required Fields to proceed to the next document. Selecting Cancel All cancels all subsequent documents from being processed by Required Fields.

Data changes in Adept are governed by the Adept Library Access Rights to Update Document, Edit Data Cards in Library, and Edit Protected Fields. Make sure any user who will need to fill in required fields has sufficient access rights. If a user does not have sufficient Library Access Rights, then they will not be able to satisfy the required field. Also be aware the Admin option settings for extraction of database fields will be applied. In the case of "Blank data in the database when the extraction item exists in the document and is blank," values entered by users who do not have update document rights could be blanked on final extraction.

Known limitation with using the Data Exporter with Required Fields

If you are using the Required Fields PlugIn on Check In or Approve, and the same data fields are selected in both Required Fields and the Data Exporter, the data in these fields is updated after the Data Exporter sends its output and will not be reflected in the Data Exporter output.

See Also

[Required Fields Configuration](#)