

OPERATING SYSTEMS Workshop 0

Much of the material on these slides comes from the recommended textbook by William Stallings

Week 01 Workshop 0 Outline

Operating System Overview

- Memory Hierarchy
- □ Cache Memory
- □ I/O Techniques
- Multiprocessors and Multicores
- Evolution of OS
- Serial Processing
- Batch Processing
- User Mode VS Kernel Mode
- Multi-Programming VS Uni-programming
- □ Time Sharing
- □ Fault Tolerance




Memory Hierarchy

- Major constraints in memory
 - amount
 - speed
 - expense
- Memory must be able to keep up with the processor
- Cost of memory must be reasonable in relationship to the other components





Memory Relationships





The Memory Hierarchy

Going down the hierarchy:

decreasing cost per bit

increasing capacity

increasing access time

 decreasing frequency of access to the memory by the processor




Figure 1.14 The Memory Hierarchy




Secondary Memory

- Also referred to as auxiliary memory
 - external
 - nonvolatile
 - used to store program and data files





Cache Memory




- Invisible to the OS
- Interacts with other memory management hardware
- Processor must access memory at least once per instruction cycle
- Processor execution is limited by memory cycle time
- Exploit the principle of locality with a small, fast memory




Principle of Locality

- Memory references by the processor tend to cluster
- Data is organized so that the percentage of accesses to each successively lower level is substantially less than that of the level above
- Can be applied across more than two levels of memory






(a) Single cache



(b) Three-level cache organization





- C: Number of slots
- M: Number of blocks

C<<M






Figure 1.17 Cache/Main-Memory Structure









Level 1


- 1,000 bytes
- Access time of T_1 =0.1 µs

Level 2

- 100,000 bytes
- Access time of T_2 =1 μ s.

If H = 0.95 , the average time to access a byte is $(0.95) (0.1 \ \mu\text{s}) + (0.05) (0.1 \ \mu\text{s} + 1 \ \mu\text{s}) = 0.095 + 0.055 = 0.15 \ \mu\text{s}$






I/O Techniques

- When the processor encounters an instruction relating to I/O, it executes that instruction by issuing a command to the appropriate I/O module
- Three techniques are possible for I/O operations:
 - Programmed I/O
 - Interrupt-Driven I/O
 - Direct Memory Access (DMA)






Programmed I/O

- The I/O module performs the requested action then sets the appropriate bits in the I/O status register
- The processor periodically checks the status of the I/O module until it determines the instruction is complete
- With programmed I/O the performance level of the entire system is severely degraded



Interrupt-Driven I/O



More efficient than Programmed I/O but still requires active intervention of the processor to transfer data between memory and an I/O module



Drawbacks



- Transfer rate is limited by the speed with which the processor can test and service a device
- The processor is tied up in managing an I/O transfer
 - a number of instructions must be executed for each I/O transfer



Direct Memory Access (DMA)

- Performed by a separate module on the system bus or incorporated into an I/O module
- When the processor wishes to read or write data it issues a command to the DMA module containing:
 - whether a read or write is requested
 - the address of the I/O device involved
 - the starting location in memory to read/write
 - the number of words to be read/written




Direct Memory Access

- Transfers the entire block of data directly to and from memory without going through the processor
 - processor is involved only at the beginning and end of the transfer
 - processor executes more slowly during a transfer when processor access to the bus is required
- More efficient than interrupt-driven or programmed I/O



Symmetric Multiprocessors (SMP)



- A stand-alone computer system with the following characteristics:
 - two or more similar processors of comparable capability
 - processors share the same main memory and are interconnected by a bus or other internal connection scheme
 - processors share access to I/O devices
 - all processors can perform the same functions
 - the system is controlled by an integrated operating system that provides interaction between processors and their programs at the job, task, file, and data element levels



SMP Advantages

- Performance
 - a system with multiple processors will yield greater performance if work can be done in parallel
- Availability
 - the failure of a single processor does not halt the machine
- Incremental Growth
 - an additional processor can be added to enhance performance
- Scaling
 - vendors can offer a range of products with different price and performance characteristics







Figure 1.19 Symmetric Multiprocessor Organization




Multicore Computer



- Also known as a chip multiprocessor
- Combines two or more processors (cores) on a single piece of silicon (die)
 - each core consists of all of the components of an independent processor
- In addition, multicore chips also include L2 cache and in some cases L3 cache








Evolution of Operating Systems

Stages include: Time Sharing Multiprogrammed Systems Batch Systems Simple Batch **Systems** Serial **Processing**



Serial Processing



Earliest Computers

- No operating system
- Programmers interacted directly with the computer hardware
- Computers ran from a console with display lights, toggle switches, some form of input device, and a printer
- Users have access to the computer in "series"

Problems

- Scheduling:
 - most installations used a hardcopy sign-up sheet to reserve computer time
 - time allocations could run short or long, resulting in wasted computer time
- Setup time
 - a considerable amount of time was spent just on setting up the program to run



Simple Batch Systems

- Early computers were very expensive
 - important to maximize processor utilization
- Monitor
 - user no longer has direct access to processor
 - job is submitted to computer operator who batches them together and places them on an input device
 - program branches back to the monitor when finished



Monitor Point of View

- Monitor controls the sequence of events
- Resident Monitor is software always in memory
- Monitor reads in job and gives control
- Job returns control to monitor




Figure 2.3 Memory Layout for a Resident Monitor



Processor Point of View

- Processor executes instruction from the memory containing the monitor
- Executes the instructions in the user program until it encounters an ending or error condition
- "control is passed to a job" means processor is fetching and executing instructions in a user program
- "control is returned to the monitor" means that the processor is fetching and executing instructions from the monitor program



Job Control Language (JCL)

Special type of programming language used to provide instructions to the monitor

₽

what compiler to use

Ŧ

what data to use

\$JOB \$FTN **FORTRAN** instruction \$LOAD \$RUN Data \$END

Desirable Hardware Features



- Memory protection for monitor
 - while the user program is executing, it must not alter the memory area containing the monitor
- Timer
 - prevents a job from monopolizing the system
- Privileged instructions
 - can only be executed by the monitor
- Interrupts
 - gives OS more flexibility in controlling user programs



Modes of Operation

User Mode

- user program executes in user mode
- certain areas of memory are protected from user access
- certain instructions may not be executed

Kernel Mode

- monitor executes in kernel mode
- privileged instructions may be executed
- protected areas of memory may be accessed



Simple Batch System Overhead

- Processor time alternates between execution of user programs and execution of the monitor
- Sacrifices:
 - some main memory is now given over to the monitor
 - some processor time is consumed by the monitor
- Despite overhead, the simple batch system improves utilization of the computer

Multiprogrammed Batch Systems


- Processor is often idle
 - even with automatic job sequencing
 - I/O devices are slow compared to processor

Read one record from file	15 μs
Execute 100 instructions	1 μs
Write one record to file	<u>15 μs</u>
TOTAL	31 μs
Percent CPU Utilization $=\frac{1}{31} = 0.032 = 3.2\%$	



Uniprogramming


 The processor spends a certain amount of time executing, until it reaches an I/O instruction; it must then wait until that I/O instruction concludes before proceeding






Multiprogramming

- There must be enough memory to hold the OS (resident monitor) and more than one user program
- When one job needs to wait for I/O, the processor can switch to the other job, which is likely not waiting for I/O





Multiprogramming



- Multiprogramming
 - also known as multitasking
 - memory is expanded to hold three, four, or more programs and switch among all of them



Multiprogramming Example

	JOB1	JOB2	JOB3
Type of job	Heavy compute	Heavy I/O	Heavy I/O
Duration	5 min	15 min	10 min
Memory required	50 M	100 M	75 M
Need disk?	No	No	Yes
Need terminal?	No	Yes	No
Need printer?	No	No	Yes

Table 2.1 Sample Program Execution Attributes






Figure 2.6 Utilization Histograms

THE UNIVERSITY OF NEWCASTLE AUSTRALIA

Effects on Resource Utilization

	Uniprogramming	Multiprogramming
Processor use	20%	40%
Memory use	33%	67%
Disk use	33%	67%
Printer use	33%	67%
Elapsed time	30 min	15 min
Throughput	6 jobs/hr	12 jobs/hr
Mean response time	18 min	10 min

Table 2.2 Effects of Multiprogramming on Resource Utilization

02/08/2018

Time-Sharing Systems

- Can be used to handle multiple interactive jobs
- Processor time is shared among multiple users
- Multiple users simultaneously access the system through terminals, with the OS interleaving the execution of each user program in a short burst or quantum of computation



Batch Multiprogramming vs. Time Sharing

	Batch Multiprogramming	Time Sharing
Principal objective	Maximize processor use	Minimize response time
Source of directives to operating system	Job control language commands provided with the job	Commands entered at the terminal

Table 2.3 Batch Multiprogramming versus Time Sharing



Compatible Time-Sharing Systems (CTSS)

- One of the first time-sharing operating systems (at MIT by Project MAC)
- Ran on a computer with 32,000 36-bit words of main memory, with the resident monitor consuming 5000 of that. To simplify both the monitor and memory management a program was always loaded to start at the location of the 5000th word
- System clock generates interrupts at a rate of approximately one every 0.2 seconds. At each interrupt OS regained control and could assign processor to another user (**Time Slicing**)
- At regular time intervals the current user would be preempted and another user loaded in. Old user programs and data were written out to disk. Old user program code and data were restored in main memory when that program was next given a turn.



Memory Requirements

• JOB1: 15000


• JOB2: 20000


• JOB3: 5000


• JOB4: 10000


Loading order


J1 > J2 > J3 > J1 > J4 > J2














Figure 2.7 CTSS Operation



Major Achievements

 Operating Systems are among the most complex pieces of software ever developed



Major advances in development include:

- Processes
- Memory management
- Information protection and security
- Scheduling and resource management



Different Architectural Approaches

- Demands on operating systems require new ways of organizing the OS
- Different approaches and design elements have been tried:
 - monolithic
 - microkernel architecture
 - multithreading
 - symmetric multiprocessing
 - distributed operating systems
 - object-oriented design



Fault Tolerance

- Refers to the ability of a system or component to continue normal operation despite the presence of hardware or software faults
- Typically involves some degree of redundancy
- Intended to increase the reliability of a system
 - typically comes with a cost in financial terms or performance
- The extent adoption of fault tolerance measures must be determined by how critical the resource is



Fundamental Concepts


- The basic measures are:
 - Reliability
 - R(t): defined as the probability of its correct operation up to time t given that the system was operating correctly at time t=0
 - Mean time to failure (MTTF)

$$MTTF = \int_0^\infty R(t)$$

- Mean Time To Repair (MTTR) is the average time it takes to repair or replace a faulty element
- Availability (A)
 - defined as the fraction of time the system is available to service users' requests

$$A = \frac{MTTF}{MTTF + MTTR}$$





$$MTTF = \frac{B1 + B2 + B3}{3}$$
 $MTTR = \frac{A1 + A2 + A3}{3}$

Figure 2.13 System Operational States



Availability Classes

Class	Availability	Annual Downtime
Continuous	1.0	0
Fault Tolerant	0.99999	5 minutes
Fault Resilient	0.9999	53 minutes
High Availability	0.999	8.3 hours
Normal Availability	0.99 - 0.995	44-87 hours

Table 2.4 Availability Classes

THE UNIVERSITY OF NEWCASTLE AUSTRALIA

Operating System Mechanisms

- A number of techniques can be incorporated into OS software to support fault tolerance:
 - Process isolation
 - Concurrency control
 - Virtual machines
 - Checkpoints and rollbacks



Summary

- Memory hierarchy is the solution to the conflicting trade-off among cost, capacity, access time
- Cash is invisible to OS but principles of cash is applied in virtual memory
- DMA frees processor from the burden of I/O
- OS evolved from batch processing to multi-programming to timesharing
- Fault tolerance is also a consideration in OS design



References

- Operating Systems Internal and Design Principles
- By William Stallings
 - Chapter 2

