



QConnect

Two Pi 4s — tick sheet

Print this and keep it next to the laptop

Version 1.0 · 09/16/2026

QCAI Support · 1-855-782-6824

Keep this next to the laptop. Full instructions are in the first-time setup guide; this page is just so you don't lose your place.

Date: _____ Done by: _____

Before you start

- ☐ Raspberry Pi Imager installed on the laptop
- ☐ Card reader working
- ☐ Wi-Fi name and password written down (optional but helpful)
- ☐ Network cable available (optional)
- ☐ Fleet system switched on, so cards can register

Pi one — name: _____ dealership: _____

- ☐ Power unplugged, memory card taken out
- ☐ Card erased (Imager → Erase)
- ☐ Raspberry Pi OS Lite 64-bit written, customisation settings cleared (including anything about SSH / remote access — leave it off)
- ☐ Card removed and reinserted; bootfs drive visible
- ☐ Prepare-Card.ps1 run, ended with "This card is ready."
- ☐ Card ejected safely and put back in the Pi
- ☐ Cable plugged in first (if using one), then power
- ☐ Waited four minutes through the automatic restart
- ☐ Appears online in the dashboard — connected by: cable / Wi-Fi / SIM
- ☐ Name written on the case

Notes: _____

Pi two — name: _____ dealership: _____

- ☐ Power unplugged, memory card taken out
- ☐ Card erased (Imager → Erase)
- ☐ Raspberry Pi OS Lite 64-bit written, customisation settings cleared (including anything about SSH / remote access — leave it off)
- ☐ Card removed and reinserted; bootfs drive visible
- ☐ Prepare-Card.ps1 run **separately** — card one not copied
- ☐ Ended with "This card is ready."
- ☐ Card ejected safely and put back in the Pi
- ☐ Cable plugged in first (if using one), then power
- ☐ Waited four minutes through the automatic restart
- ☐ Appears online in the dashboard — connected by: cable / Wi-Fi / SIM
- ☐ Name written on the case

Notes: _____

If a box is not ticked

Do not ship that Pi. A Pi that half-works on the bench never works at a dealership. Call QCAI Support on 1-855-782-6824 with the name on the case.