

```

1  //
=====
2  //  FILE: HUDPanelFinalizer_Control.cs
3  //  PATH: Engine/UI/HUDPanels/
4  //  MODULE: Finalizer Control Surface (Manual Override Input)
5  //
6  //  ROLE:
7  //      Provides the developer-facing manual override surface for the CASH HUD panel.
This module
8  //      exposes editable fields (geometry, colors, crosshair configuration) that can be
populated
9  //      either manually or via HUDConfigManager. The Finalizer Manager reads these
values and passes
10 //      them into the ColorParser and Resolver.
11 //
12 //  RESPONSIBILITIES:
13 //      - Store manual override fields for geometry, colors, and crosshair configuration.
14 //      - Provide a clean DTO (HUDPanelFinalizerControlData) for the Finalizer pipeline.
15 //      - Accept persisted configuration from HUDConfigManager.
16 //      - Surface error messages when color parsing fails.
17 //      - Enable/disable manual override mode deterministically.
18 //
19 //  NON-RESPONSIBILITIES:
20 //      - Color parsing (handled by HUDPanelFinalizer_ColorParser).
21 //      - Geometry/crosshair resolution (handled by HUDPanelFinalizer_Resolver).
22 //      - UIState construction (handled by HUDPanelFinalizer_UIStateBuilder).
23 //      - Rendering (handled by HUDPanel_CashUpdate and HUDManager).
24 //
25 //  ARCHITECTURAL NOTES:
26 //      - This module is intentionally simple and declarative.
27 //      - No implicit defaults: all values must be set explicitly by config or developer
input.
28 //      - Error messages are stored here so the Manager can surface them in diagnostics.
29 //
=====
=====
30
31 using System;
32 using SASZombieAssaultTD.Engine.Waves;
33
34 namespace SASZombieAssaultTD.Engine.UI.HUDPanels
35 {
36     public class HUDPanelFinalizer_Control
37     {
38         //
-----
-----
39         // Manual override flags
40         //
-----
-----
41
42         private bool _manualOverrideEnabled = false;
43         private string _errorMessage = null;
44
45         //
-----
-----
46         // Geometry (developer-facing)
47         //
-----
-----
48         public static HUDPanelFinalizer_Control Instance { get; set; }
49         public int X { get; set; } = 120;
50         public int Y { get; set; } = 540;
51         public int Width { get; set; } = 80;
52         public int Height { get; set; } = 40;
53

```

```

54      //
55      -----
56      // Color tokens (developer-facing)
57      // These are raw strings that ColorParser will validate and convert.
58      //
59      -----
60      public string FillColorToken { get; set; } = "#202020";
61      public string TextColorToken { get; set; } = "#00E0FF"; //changing this to a
62      different color will change the color of the cash text to better match the color
63      of the actual panel text. The default is a cyan color, but you can change it to
64      any valid color token (e.g., "red", "#FF0000", "255,0,0") to customize the text
65      color.
66      public string ItemPriceColorToken { get; set; } = "#00BFFF"; // Light blue,
67      matches original item prices
68      //
69      -----
70      // Crosshair configuration (developer-facing)
71      //
72      -----
73      public int CrosshairCenterX { get; set; } = 122;
74      public int CrosshairCenterY { get; set; } = 553;
75      public int CrosshairArmLength { get; set; } = 12;
76      public int CrosshairThickness { get; set; } = 3;
77      public Color CrosshairColor { get; set; } = Color.Lime;
78      public bool UseFlashColor { get; set; } = false;
79      public Color FlashColor { get; set; } = Color.Red;
80      //
81      -----
82      // Error message handling
83      //
84      -----
85      public void SetErrorMessage(string message)
86      {
87          _errorMessage = message;
88      }
89      public string GetErrorMessage()
90      {
91          return _errorMessage;
92      }
93      //
94      -----
95      // Manual override toggle
96      //
97      -----
98      public void SetManualOverrideEnabled(bool enabled)
99      {
100         _manualOverrideEnabled = enabled;
101     }
102     public bool IsManualOverrideEnabled()
103     {

```

```

102         return _manualOverrideEnabled;
103     }
104
105     //
-----
-----
106     // DTO Export
107     // Finalizer Manager calls this to obtain a clean snapshot of all manual fields.
108     //
-----
-----
109
110     public HUDPanelFinalizerControlData GetManualEntryData ()
111     {
112         return new HUDPanelFinalizerControlData
113         {
114             X = this.X,
115             Y = this.Y,
116             Width = this.Width,
117             Height = this.Height,
118
119             FillColorToken = this.FillColorToken,
120             TextColorToken = this.TextColorToken,
121             ItemPriceColorToken = this.ItemPriceColorToken,    // * REQUIRED
122
123             CrosshairCenterX = this.CrosshairCenterX,
124             CrosshairCenterY = this.CrosshairCenterY,
125             CrosshairArmLength = this.CrosshairArmLength,
126             CrosshairThickness = this.CrosshairThickness,
127
128             CrosshairColor = this.CrosshairColor,
129             UseFlashColor = this.UseFlashColor,
130             FlashColor = this.FlashColor
131         };
132     }
133
134     internal void ShowWaveNotification(WaveNotification notification)
135     {
136         throw new NotImplementedException();
137     }
138 }
139
140

```