12,319,459 members (73,729 online)





home

articles

quick answers

discussions

features

community

help

Search for articles, questions, tips

Articles » Languages » C / C++ Language » Memory Management



Tip/Trick

Stats

Browse Code

Revisions (4)

Alternatives

Comments (3)

Add your own alternative version

Tagged as

HTML C++

Windows

Dev

4.5K views

137 downloads 18 bookmarked

Posted 26 Oct 2014

The StorageManager class - easy data storing



SkyProgger, 26 Oct 2014

★★★★★ 5.00 (1 vote)

This article describes the StorageManager class I have developed. It's created to save data beyond the Programs lifespan, as easy

Download StorageManager.zip - 360.5 KB

Introduction

The StorageManager class was created to allow programmers to easy store Data. This is done by simulating a new area of memory (beneath datasegment, stack and heap). The Storage. The StorageManager provides some methods to access this area. Memory allocated within this area will be stored and reloaded when closing and restarting the program. The aim was to keep it as simple as possible for the users of this class, but also to allow some more specialized methods.

The Project itself includes a full HTML-documentation, created with Doxygen (http://www.stack.nl/~dimitri/doxygen/). So this article will only feature the basic functionality of the StorageManager. The files itself are attached as zipped archive.

Using the code

The StorageManager is a static class, which is located in the datasegment. So as soon as you include the .cpp file to your project, a StorageManager will be created. The Manager will Auto-Setup itself on Program start, loading all the data you stored before, and will auto-save it and clean itself up when the Program ends. But you can modify this behavior to customize the

The most common functions to use would be allocating and deallocating Storage. This can be done in various ways, depending on what you need, but the easiest (and most common) way is the following:

Hide Copy Code #include "StorageManager.h" #include <iostream> int main() std::cout << StorageManager::getLoadProtocol() << std::endl;</pre> int *ptr = StorageManager::getVariable<int>("Int-Variable", true, 11); std::cout << *ptr; (*ptr)++; return 0;

The getLoadProtocol function will simply print out a protocol, the Manager creates on loading a file. There you can find all Variables that have been loaded and, if occured, any loading errors. (Notice: The Manager called the load function on it's construction, so at this point, the protocol already exists)

But what is more interesting here is the getVariable function. In short, it will do the following: It first checks the Manager, if a variable with the name "Int-Variable" already exists. If yes, it will load it and return the pointer to it. If no, it will create a new one, and forward the 11 to the variables constructor. So in this case, the integer will be set to 11. The second parameter specifies how the Manager behaves, if a variable with the given name is found, but it's not an integer or an array. I set it to true, which means, the Manager will discard the old value in this case and replace it. The outcom of this program would be 11. But if you run it a second time, it will be 12 instead, then comes 13, ... As you can see: I created a Variable on the Storage, that lives beyond the programs lifespan. and each time I run the program, i increase it's value by 1. Thats basically it, thats the StorageManagers main functionality.

Please Notice: I did NOT delete the Memory I allocated, this is not a mistake. The Manager itself will care about Memory, and internally free it as soon as it's destructed. If you free the Pointer, this will remove it from the Storage, which means, it will be permanently deleted. It won't be stored anymore. To do this, call removeVariable, as done in the following example:

```
Hide Copy Code
#include "StorageManager.h"
#include <iostream>
int main()
    std::cout << StorageManager::getLoadProtocol() << std::endl;</pre>
    int *ptr = StorageManager::getVariable<int>("Int-Variable", true, 11);
```



```
std::cout << *ptr << std::endl;
  (*ptr)++;

std::cout << "delete the Int-Variable? (enter y to delete): ";
  if((char)cin.get() == 'y')
    StorageManager::removeVariable("Int-Variable");

return 0;
}</pre>
```

In this case, if you enter 'y', the Variable will deleted. Please notice, that this will cause ptr to get invalid, because it will be deleted. The pointers address will be added to the CorruptionList. Please check the full documentation, if you want to know more about this topic.

Of course, the Manager can do much more. The most remarkable would be:

- Storing arrays (They need a own method, getArray)
- Easy methods to copy or move pointers between the Storage and e.g. the Heap
- The StorageVariable class, which allows to store pointers (with some restrictions)
- Encryption of data stored. This feature needs the CryptoPP library(http://www.cryptopp.com/). On default, the parts using
 the the Library are excluded with preprocessor switches

History

- 25.10.2014: First Version of the StorageManager published, Vers 1.0

License

This article, along with any associated source code and files, is licensed under The Code Project Open License (CPOL)

Share

EMAIL TWITTER

About the Author



SkyProgger

No Biography provided

You may also be interested in...



Non-Tech Factors to Consider When Choosing Your Tech Stack



How-To Intel IoT Code Samples: Range Finder Scanner



How-To Intel® IoT Technology Code Samples: Doorbell in C++



Getting Started with React




A Beginners Guide to WebGL



10 Ways to Boost COBOL Application Development

Comments and Discussions



Use Ctrl+Left/Right to switch messages, Ctrl+Up/Down to switch threads, Ctrl+Shift+Left/Right to switch pages.

Permalink | Advertise | Privacy | Terms of Use | Mobile Web01 | 2.8.160531.1 | Last Updated 26 Oct 2014

Layout: fixed | fluid

Article Copyright 2014 by SkyProgger Everything else Copyright © CodeProject, 1999-2016