## BALANCE-LINE (SIMPLES) CONCEITO DE HIGH-VALUES

# IDENTIFICATION DIVISION.

PROGRAM-ID. BALANCE-LINE-SIMPLES.

AUTHOR. HIRO.

INSTALLATION. FATEC-SP.

DATE-WRITTEN. 17/09/2004.

DATE-COMPILED.

SECURITY. APENAS O AUTOR PODE MODIFICA-LO.

\*REMARKS. FAZ O BALANCE-LINE, GERANDO UM ARQUIVO DE SAIDA.

# **ENVIRONMENT DIVISION. CONFIGURATION SECTION.**

SOURCE-COMPUTER, IBM-PC.

OBJECT-COMPUTER. IBM-PC.

SPECIAL-NAMES. DECIMAL-POINT IS COMMA.

## INPUT-OUTPUT SECTION.

FILE-CONTROL.

SELECT MVTO ASSIGN TO DISK

ORGANIZATION IS LINE SEQUENTIAL.

SELECT ANT ASSIGN TO DISK

ORGANIZATION IS LINE SEQUENTIAL.

SELECT ATU ASSIGN TO DISK

ORGANIZATION IS LINE SEQUENTIAL.

#### DATA DIVISION.

FILE SECTION.

#### FD MVTO

LABEL RECORD ARE STANDARD

VALUE OF FILE-ID IS "MVTO.DAT".

01 REG-MVTO.

02 COD-MVTO PIC 9(04).

02 NOME-MVTO PIC X(30).

## **FD ANT**

LABEL RECORD ARE STANDARD

VALUE OF FILE-ID IS "ANT.DAT".

01 REG-ANT.

03 COD-ANT PIC 9(04).

03 NOME-ANT PIC X(30).

#### **FD ATU**

LABEL RECORD ARE STANDARD

VALUE OF FILE-ID IS "ATU.DAT".

01 REG-ATU.

03 COD-ATU PIC 9(04).

03 NOME-ATU PIC X(30).

# **WORKING-STORAGE SECTION.**

77 CH-MVTO PIC X(04) VALUE SPACES.

77 CH-ANT PIC X(04) VALUE SPACES.

## BALANCE-LINE (SIMPLES) CONCEITO DE HIGH-VALUES

## PROCEDURE DIVISION.

# **PGM-BALANCE-LINE.**

PERFORM INICIO.
PERFORM PRINCIPAL

**UNTIL** 

CH-MVTO EQUAL CH-ANT AND

CH-ANT EQUAL HIGH-VALUES.

PERFORM FIM. STOP RUN.

#### INICIO.

OPEN INPUT MVTO

ANT

OUTPUT ATU.

PERFORM LER-MVTO. PERFORM LER-ANT.

## **LER-MVTO.**

READ MVTO

AT END

MOVE **HIGH-VALUES** TO CH-MVTO.

IF CH-MVTO EQUAL **HIGH-VALUES** 

NEXT SENTENCE

**ELSE** 

MOVE COD-MVTO TO CH-MVTO.

## LER-ANT.

READ ANT

AT END

MOVE **HIGH-VALUES** TO CH-ANT.

IF CH-ANT EQUAL HIGH-VALUES

NEXT SENTENCE

**ELSE** 

MOVE COD-ANT TO CH-ANT.

#### PRINCIPAL.

IF CH-MVTO EQUAL CH-ANT

PERFORM IGUAL

**ELSE** 

IF CH-MVTO LESS CH-ANT

PERFORM MVTO-MENOR

**ELSE** 

PERFORM ANT-MENOR.

## **IGUAL.**

# BALANCE-LINE (SIMPLES) CONCEITO DE HIGH-VALUES

PERFORM GRAVA-MVTO.
PERFORM GRAVA-ANT.
PERFORM LER-MVTO
PERFORM LER-ANT

## **MVTO-MENOR.**

PERFORM GRAVA-MVTO. PERFORM LER-MVTO

## **ANT-MENOR.**

PERFORM GRAVA-ANT. PERFORM LER-ANT.

# **GRAVA-ANT.**

MOVE COD-ANT TO COD-ATU.

MOVE NOME-ANT TO NOME-ATU.

WRITE REG-ATU.

# **GRAVA-MVTO.**

MOVE COD-MVTO TO COD-ATU.

MOVE NOME-MVTO TO NOME-ATU.

WRITE REG-ATU.

## FIM.

CLOSE MVTO ANT

ATU.