```cobol
       IDENTIFICATION DIVISION.
       PROGRAM-ID.    NIVEL88.
       AUTHOR.        HIROMASA NAGATA.
       INSTALLATION. FATEC-SP.
       DATE-WRITTEN. 30/09/2005.
       DATE-COMPILED.
       SECURITY. APENAS O AUTOR PODE MODIFICA-LO.
      *REMARKS.   LE OS REGISTRO DO ARQUIVO DE ENTRADA E
      *           FAZ A VALIDACAO UTILIZANDO O NIVEL 88.

       ENVIRONMENT DIVISION.
       CONFIGURATION SECTION.
       SOURCE-COMPUTER. IBM-PC.
       OBJECT-COMPUTER. IBM-PC.
       SPECIAL-NAMES. DECIMAL-POINT IS COMMA.
       INPUT-OUTPUT SECTION.
       FILE-CONTROL.
           SELECT CAD-ENT  ASSIGN TO DISK
           ORGANIZATION IS LINE SEQUENTIAL.
           SELECT CAD-OK   ASSIGN TO DISK
           ORGANIZATION IS LINE SEQUENTIAL.
           SELECT CAD-RUIM ASSIGN TO DISK
           ORGANIZATION IS LINE SEQUENTIAL.
```

```cobol
DATA DIVISION.
FILE SECTION.
FD   CAD-ENT
     LABEL RECORD ARE STANDARD
     VALUE OF FILE-ID IS "CAD-ENT.DAT".
01   REG-ENT.
     02 COD-ENT   PIC 9(02).
     02 NOME-ENT  PIC X(30).
        88 NOME-INVALIDO    VALUE SPACES.
     02 SEXO-ENT  PIC X(01).
        88 SEXO-VALIDO      VALUE "F" "f" "M" "m".
     02 MES-ENT   PIC 9(02).
        88 MES-VALIDO       VALUE 1 THRU 12.
FD   CAD-OK
     LABEL RECORD ARE STANDARD
     VALUE OF FILE-ID IS "CAD-OK.DAT".
01   REG-OK          PIC X(35).

FD   CAD-RUIM
     LABEL RECORD ARE STANDARD
     VALUE OF FILE-ID IS "CAD-RUIM.DAT".
01   REG-RUIM        PIC X(35).
```

```cobol
WORKING-STORAGE SECTION.
77  FIM-ARQ      PIC X(03) VALUE "NAO".
77  CH-ERRO      PIC X(03) VALUE "NAO".


PROCEDURE DIVISION.
PGM-NIVEL88.
    PERFORM INICIO.
    PERFORM PRINCIPAL UNTIL FIM-ARQ EQUAL "SIM".
    PERFORM FIM.
    STOP RUN.


INICIO.
    OPEN INPUT  CAD-ENT
         OUTPUT CAD-OK
                CAD-RUIM.
    PERFORM LEITURA.


LEITURA.
    READ CAD-ENT
        AT END MOVE "SIM" TO FIM-ARQ.
```

```
PRINCIPAL.
    PERFORM CONSISTENCIA.
    PERFORM LEITURA.

CONSISTENCIA.
    MOVE        "NAO"  TO  CH-ERRO.
    PERFORM    VAL-NOME.
    PERFORM    VAL-SEXO.
    PERFORM    VAL-MES.
    IF         CH-ERRO EQUAL "SIM"
       PERFORM GRAVA-RUIM
    ELSE
       PERFORM GRAVA-OK.

VAL-NOME.
    IF NOME-INVALIDO
       MOVE    "SIM"  TO  CH-ERRO
    ELSE
       NEXT SENTENCE.
```

```
VAL-SEXO.
    IF SEXO-VALIDO
        NEXT SENTENCE
    ELSE
        MOVE "SIM" TO  CH-ERRO.

VAL-MES.
    IF MES-VALIDO
        NEXT SENTENCE
    ELSE
        MOVE "SIM" TO  CH-ERRO.

GRAVA-OK.
    MOVE  REG-ENT  TO  REG-OK.
    WRITE REG-OK.

GRAVA-RUIM.
    MOVE  REG-ENT  TO  REG-RUIM.
    WRITE REG-RUIM.
```

```
FIM.
   CLOSE CAD-ENT
         CAD-OK
         CAD-RUIM.
```