
VERSION 1.0 · USER MANUAL

BibleLive

A complete digital church media assistant: a unified library, voice-driven Scripture detection, five independent display outputs, and one-click live service control — fully offline, on one PC.

Desktop Edition · Windows 10 / 11 (64-bit)

1. What BibleLive Does

BibleLive is a complete digital church media assistant for Windows. It runs entirely offline on one PC and combines four engines under a single Live Service control room:

- **Content Engine** — the full KJV Bible (66 books) and a public-domain hymn collection ship built in. Import your own songs and documents (.txt / .docx) with license tracking.
- **Display Engine** — five independent Display Slots. Each slot outputs a fullscreen window on any monitor, with its own font, size and colors, AUTO/MANUAL/LOCK mode, and display profiles.
- **Voice Engine** — listens through a microphone or mixer, transcribes locally with Whisper (no cloud), and detects Bible references ("John 3:16", "John chapter three verse sixteen") and quoted verses.
- **Service Control** — start a service, approve AI suggestions, blank every screen in an emergency, and keep an automatic log of everything projected.

Everything the AI does is a **suggestion**. Nothing reaches a screen unless a rule allows it (Manual / Assisted / Automatic), and the operator can always take over. The AI only ever matches content that exists in the library — it never generates Scripture.

2. Installing on Another PC

Requirements: Windows 10 or 11 (64-bit). Nothing else: no internet and no extra runtimes. Use the **all-in-one package** (recommended) or the plain installer.

Item	Size	Purpose
BibleLive_0.1.0_x64-setup.exe	5 MB	The application installer
ggml-base.en.bin	148 MB	Voice model — needed only for speech features
Install-BibleLive.cmd	2 KB	One-click: installs the app, then copies the voice model

All-in-one (recommended)

- Copy the whole **BibleLive-FullSetup** folder to the target PC.
- Double-click **Install-BibleLive.cmd**. It installs the app silently and places the voice model in the right folder automatically.
- Launch **BibleLive** from the Start menu. The KJV and hymns are seeded on first start.

Voice-only extra step (plain installer)

If you install without the script, copy ggml-base.en.bin to %APPDATA%\BibleLive\models\ (create the folder if needed). Without it, everything works except listening and transcription.

Moving your library too

Your imported documents, display profiles and service history live in %APPDATA%\BibleLive\biblelive.db. Copy that one file to the same location on the new PC to clone your setup exactly.

3. The Library Tab

Browse and search everything installed. Filter by type (Bible, Hymn, Song, Book, Document), sort A-Z / Z-A / by date added, or use **canonical order** (Genesis to Revelation). When the Bible filter is active, Old Testament and New Testament sub-filters appear.

Searching

The search box searches **all content at once**. Type a reference ("John 3:16"), a quotation ("for God so loved the world"), or a hymn line ("amazing grace"). Results show highlighted snippets; click one to read the full chapter or song.

Importing your own content

- Click **+ Import / Add**, then paste text or pick a .txt / .docx file.
- Blank lines separate stanzas or sections; lines like "[Verse 1]" or "Chorus:" become section labels that the display engine can page through.
- Choose a license. Copyrighted or unknown-license content is automatically marked **private** as a safeguard.

4. The Displays Tab

Five Display Slots, each independently controlled. A slot is a fullscreen black window that shows scripture, lyrics, images or video on whatever monitor you assign it to.

Per-slot controls

- **Open output** — creates the fullscreen window on the chosen monitor (falls back to the primary monitor with a warning if it is missing).
- **AUTO / MANUAL / LOCK** — whether AI suggestions may target this slot; LOCK keeps content on screen no matter what.
- **Scripture / Lyrics / Media** — put content on the slot. Picking a verse loads its **whole chapter**; picking a song loads all its stanzas, so Prev/Next walks through them.
- **Style** — font family (12 choices), text size, text color and background color. Text auto-shrinks to fit any screen, so nothing ever overflows. Styles are saved into profiles.
- **Profiles** — save all five slots' monitor + mode + style layout under a name ("Sunday Service") and re-apply it in one click.

Keys inside a fullscreen output

Key	Action
Left / Right arrows	Previous / next verse or stanza on that display
Tab / Shift+Tab	Switch keyboard focus between open fullscreen outputs
M	Move this output to the next connected screen
Esc	Close the output (its content stays on the slot)

5. Global Hotkeys

These work system-wide, even when a fullscreen output has focus. They act on the **active display** — select it with Ctrl+Alt+1 to 5 (the card shows a gold star; the output shows a brief blue banner). Works with both the number row and the numeric keypad.

Keys	Action
Ctrl+Alt+1 ... 5	Select the active display
Ctrl+Alt+Right / Left	Next / previous verse or stanza on the active display
Ctrl+Alt+B	Blank / unblank the active display

If a combination clashes with other software, close that software during the service, or ask for the bindings to be made configurable.

6. The Voice Tab

One-time audio setup

- **Audio source** — pick the microphone the preacher uses. A USB microphone works; a Bluetooth headset works too (use its "Hands-Free" entry; connect it before opening the tab). Best results with larger churches: a speech-only **aux/bus output from the mixer** fed into the PC.
- **Source contains** — "Speech only" for a dedicated mic or aux channel; "Mixed church audio" if the PC receives the full worship mix.
- **Sensitivity** — lower = more sensitive. Raise it if silence or music triggers false detections.

The audio test — always run it before a service

Click **Run audio test** and say "Testing BibleLive". After 8 seconds the panel shows signal level, whether speech was detected, and what was recognized. This catches the classic problem of Windows listening to the wrong device.

Listening modes

Mode	Behavior
Manual	Suggestions queue up; you control everything
Assisted (default)	Detected verses appear as cards with SHOW / IGNORE
Automatic	High-confidence matches are pushed to displays without approval

During a service the system listens continuously but only works when it hears speech. A mute button is one click away. Everything is processed locally; no audio ever leaves the PC.

7. The Live Service Tab

The control room for running an actual service.

- **Start service** — name it (e.g. "Sunday Morning") or leave blank for an automatic date. A timer tracks the service.
- **Auto-recorded log** — every verse, song, image or video shown on any display is recorded with a timestamp. After the service it is saved; History lets you reopen any past service's log.

- **AI suggestions** — when the preacher says a reference, a card appears with the verse and a confidence score. SHOW puts it on Display 1; IGNORE dismisses it.
- **Display strip** — five tiles showing each slot's live status and current content. Click a tile to make it the hotkey target.
- **EMERGENCY BLANK ALL** — blacks out every display at once; Restore all brings everything back.

8. A Typical Service, Step by Step

Step	Action
1	Displays tab: open outputs for the slots you need (Display 1 minimum). Load a opening scripture or apply a saved profile.
2	Voice tab: run the audio test once. Then click Start listening.
3	Live Service tab: Start service. Keep this tab open — it is your control room.
4	During the sermon: when a suggestion card appears, click SHOW (or press nothing and let Automatic mode work). Use Ctrl+Alt+Right to walk through the chapter.
5	Worship: Lyrics picker on another display; Ctrl+Alt+2 to target it, arrows to change stanzas.
6	Emergency: Ctrl+Alt+B blanks the active display; EMERGENCY BLANK ALL blacks out every screen.
7	Afterwards: End service. The full log is saved under History.

9. File Locations and Troubleshooting

Where things live

Location	Contents
%APPDATA%\BibleLive\biblelive.db	Your whole library, profiles and service history
%APPDATA%\BibleLive\models\ggml-base.en.bin	The voice model (148 MB)
Display outputs	Open from the Displays tab; fullscreen windows on your monitors

Common problems

Problem	Fix
Voice tab says model not found	Copy ggml-base.en.bin into %APPDATA%\BibleLive\models\ (the all-in-one installer script does this for you).
No speech detected in the audio test	Wrong input device selected, or input muted in Windows sound settings. Check the device shows a level meter in Windows while you speak.
Bluetooth microphone missing	Connect it first, then reopen the Voice tab. Use the "Hands-Free" entry, not "Stereo". If still missing: Control Panel > Devices and Printers > device Properties > Services > enable Hands-Free Telephony.
Hotkeys do nothing	They are global while BibleLive runs — check no other app has claimed them, and that a display is active (gold star). Digits above the letters and the numpad both work.
A display shows only black	That is the blank state. Press Unblank on its card, or Ctrl+Alt+B. Content stays on the slot.
Preacher talks but nothing happens	Check the mode is not Manual-with-stop, that listening is on (red dot), and that he is actually quoting a verse the library contains. Partial quotes and paraphrases arrive in a later version.

BibleLive v1.0 — offline-first, local-data-first. Your library belongs to your church, on your machine.