

String 1 - Before

```
1.  STRING Field1 DELIMITED BY SPACES INTO Field2.  
    DISPLAY Field2.
```

This is the destination string

String 1 - After

1. `STRING Field1 DELIMITED BY SPACES INTO Field2.`
`DISPLAY Field2.`

The delimiter is encountered after “Where”.
The text in Field2 that is not explicitly
overwritten, is left intact.

Whereis the destination string

String 2 - Before

```
2. STRING Field1 DELIMITED BY SIZE INTO Field2.  
   DISPLAY Field2.
```

This is the destination string

String 2 - After

```
2. STRING Field1 DELIMITED BY SIZE INTO Field2.  
   DISPLAY Field2.
```

DELIMITED BY SIZE, strings the entire contents of Field1 into Field2

Where does this **goat**ion string

String 3 - Before

3. MOVE 6 TO StrPtr.

```
STRING Field1, Field3 DELIMITED BY SPACE  
    INTO Field2 WITH POINTER StrPtr  
    ON OVERFLOW DISPLAY "String Error"  
    NOT ON OVERFLOW "No Error"  
END-STRING.  
DISPLAY Field2.
```

This is the destination string

String 3 - After

3. MOVE 6 TO StrPtr.

STRING Field1, Field3 DELIMITED BY SPACE
INTO Field2 WITH POINTER StrPtr
ON OVERFLOW DISPLAY "String Error"
NOT ON OVERFLOW "No Error"
END-STRING.
DISPLAY Field2.

The WITH POINTER phrase, means that characters are inserted into Field2 starting at character position 6

This WhereHereestination string

String 4 - Before

```
4.  STRING Field1, Field2, Field3  
    DELIMITED BY SPACES INTO Field4  
    END-STRING.  
    DISPLAY Field4
```



String 4 - After

```
4. STRING Field1, Field2, Field3  
    DELIMITED BY SPACES INTO Field4  
END-STRING.  
DISPLAY Field4
```

WhereThisHere

String 5 - Before

5. MOVE 4 TO NewPtr.

STRING Field1 DELIMITED BY "this"

Field3 DELIMITED BY SPACE

"END" DELIMITED BY SIZE

INTO Field2

END-STRING.

DISPLAY Field2

This is the destination string

String 5 - After

5. MOVE 4 TO NewPtr.

```
STRING Field1 DELIMITED BY "this"  
      Field3 DELIMITED BY SPACE  
      "END"   DELIMITED BY SIZE  
      INTO Field2  
END-STRING.  
DISPLAY Field2
```

This was a trick question.
Even though 4 is moved to the
NewPtr, there is no WITH
POINTER phrase in the
STRING statement.
So moving 4 to NewPtr has no
effect.

Where does HereENDation string

String 6 - Before

```
6. MOVE 4 TO NewPtr.  
   STRING Field1 DELIMITED BY "this"  
       Field3 DELIMITED BY SPACE  
       "Tom"   DELIMITED BY SIZE  
   INTO Field2 WITH POINTER NewPtr  
   ON OVERFLOW DISPLAY "String Error"  
   NOT ON OVERFLOW DISPLAY Field2  
END-STRING.  
DISPLAY Field2.
```

This is the destination string

String 6 - After

```
6. MOVE 4 TO NewPtr.  
   STRING Field1 DELIMITED BY "this"  
       Field3 DELIMITED BY SPACE  
       "Tom"   DELIMITED BY SIZE  
   INTO Field2 WITH POINTER NewPtr  
   ON OVERFLOW DISPLAY "String Error"  
   NOT ON OVERFLOW DISPLAY Field2  
END-STRING.  
DISPLAY Field2.
```

Because there are valid characters in the source strings that have not been transferred to the destination string, the ON OVERFLOW activates.

Thi**Where** he destination string