

# Using the SET verb

## **Click to view.**

When viewing , left click (or press the Page Up key) to see the next frame and right click (or press Page Down) to see the previous frame.

```
01 EOF-Flag      PIC 9 VALUE 0.  
   88 EndOfFile      VALUE 1.
```

EOF-Flag

0

EndOfFile



```
READ InFile  
  AT END MOVE 1 TO EOF-Flag  
END-READ  
PERFORM UNTIL EndOfFile  
  Statements  
  READ InFile  
    AT END MOVE 1 TO EOF-Flag  
  END-READ  
END-PERFORM
```

The only problem with this arrangement is readability.

It's not obvious what effect moving 1 to EOF-Flag will have without looking up its definition.

EOF-Flag

1

EndOfFile

```
01 EOF-Flag      PIC 9 VALUE 0.  
   88 EndOfFile          VALUE 1.
```

```
READ InFile  
  AT END MOVE 1 TO EOF-Flag  
END-READ  
PERFORM UNTIL EndOfFile  
  Statements  
  READ InFile  
    AT END MOVE 1 TO EOF-Flag  
  END-READ  
END-PERFORM
```



```
01 FILLER      PIC 9 VALUE 0.  
88 EndOfFile   VALUE 1.  
88 NotEndOfFile VALUE 0.
```

**FILLER**

**0**

**EndOfFile**

**NotEndOfFile**

```
READ InFile  
  AT END SET EndOfFile TO TRUE  
END-READ  
PERFORM UNTIL EndOfFile  
  Statements  
  READ InFile  
    AT END SET EndOfFile TO TRUE  
  END-READ  
END-PERFORM  
SET NotEndOfFile TO TRUE
```

When we need to reserve an area of storage but don't need to refer to it by name we can give it the dummy name - FILLER. This saves us the bother of having to make up a dummy name.

```
01 FILLER      PIC 9 VALUE 0.  
88 EndOfFile   VALUE 1.  
88 NotEndOfFile VALUE 0.
```

**FILLER**

**1**

**EndOfFile**

**NotEndOfFile**

```
READ InFile  
  AT END SET EndOfFile TO TRUE  
END-READ  
PERFORM UNTIL EndOfFile  
  Statements  
  READ InFile  
  AT END SET EndOfFile TO TRUE  
END-READ  
END-PERFORM  
SET NotEndOfFile TO TRUE
```

Setting EndOfFile to TRUE forces the condition value into the associated data-item.

```
01 FILLER      PIC 9 VALUE 0.  
88 EndOfFile   VALUE 1.  
88 NotEndOfFile VALUE 0.
```

**FILLER**

0

**EndOfFile**  
**NotEndOfFile**

```
READ InFile  
  AT END SET EndOfFile TO TRUE  
END-READ  
PERFORM UNTIL EndOfFile  
  Statements  
  READ InFile  
  AT END SET EndOfFile TO TRUE  
END-READ  
END-PERFORM  
SET NotEndOfFile TO TRUE
```

When NotEndOfFile is set to TRUE it forces the condition value 0 into the data-item and this has the effect of unsetting EndOfFile.