
Game flow charts: how to read them

How a player moves through Lakbay Salita, starting at the Main menu

Symbols



Where a flow begins or ends



A game screen (a Unity scene); the colour shows the part of the game



Something the player taps, types or drags




Something the game does (a script step)



A yes / no or multi-way choice, made by the game or by the player




A window on top of a screen (settings, result card, pause window)



Data kept on the player's computer



Continues at the node with the same letter (off-page or distant link)



Solid arrow: the next step. Label = the choice or the button.

Dashed arrow: a return, a back step or an optional path.

Colour key (screens)

- Main menu, Language hub
- Wordle
- Crossword
- Word Search
- Learn cards
- Phrasebook and Sentence builder
- Library
- Profile and settings

Contents

2 Overview: the whole game from the Main menu
3 Main menu
4 Settings window and Profile
5 Play flow: hub, start screen, puzzle, result
6 Wordle gameplay
7 Crossword gameplay
8 Word Search gameplay
9 Learn cards
10 Phrasebook: topics and phrase cards
11 Sentence builder
12 Library
13 Where progress is saved


Reading tips:

- Scene names are shown in grey-style text under screen titles, exactly as in the Unity project.
- Language index: 0 Cebuano, 1 Ilonggo, 2 Tagalog.
- Every screen except the Main menu has a back button (top left).

Source: the scenes and scripts of the Lakbay Salita Unity project (October 2026).

Overview: the whole game from the Main menu

Every screen the player can reach and how the screens connect (details on the next pages)




Also:

- Result card: Back to games returns to the Language hub; See in Library opens the Library with the word searched.
- Profile: the Favorites card opens the Library.
- Opening any game counts the day for the day streak.
- All progress is saved automatically (page 13).

Back buttons return to the previous screen; the Main menu is reached again from the Hub, Library, Phrasebook and Profile.

Main menu

Scene 1 Main_menu: the start of every session and the way to every other screen




Notes:

- The sky changes by device clock: morning 05:00-10:59, noon 11:00-15:59, afternoon 16:00-18:59, night 19:00-04:59.
- The Phrasebook opens in the language used last time (Cebuano the first time).
- The Settings window and the destination screens return here with their Back / Done button.

Settings window and Profile


The gear chip and the Profile chip of the Main menu



Settings are saved at once; Reset progress keeps the Library favorites.

Play flow: hub, start screen, puzzle, result


The path shared by Wordle, Crossword and Word Search





P = Play scene, S = Start screen, H = Language hub (letters are links inside this page).


Wordle gameplay

Inside the scene Wordle - Play (one scene plays every level)










R = Result card (page 5): a win shows the word, its meaning, time, tries and streak; a loss shows the answer. Solving also adds the word to Words learned.

R = Result card (page 5). Dictionary check is off by default because the dictionary lacks some valid words.

Crossword gameplay

Inside the scene Crossword - Play (one scene plays every puzzle)




Notes:

- After every change the game checks the words; words that become correct are struck through in the clue list.
- The Keypad switch shows an on-screen keyboard (off by default, remembered); the physical keyboard always works.
- Hint, Check and Reveal are the only helpers and carry no penalty.

R = Result card (page 5)

Word Search gameplay

Inside the scene WordSearch - Play (one scene plays every puzzle)




Notes:

- No tries and no time limit; the stopwatch only records the time.
- Words run across, down or diagonally down-right.
- Win also adds the words to Words learned (Profile).

R = Result card (page 5). A = back to 'What does the player do?'. Word Search has no tries and no time limit.

Learn cards

Scene Learn - Cards: meet the words before playing them




Notes:

- The three sets A, B and C are the same word sets as the three Word Search puzzles of the topic (7 to 8 words each).
- Next, Back and the set chips keep the player on the Learn card.
- P = Play scene (page 5).
- A 'Tap to hear' speaker button is built for the card but switched off until recordings exist.

The cards are optional: every topic card also has a Play button.

Phrasebook

Scenes Phrasebook - Topics and Phrasebook - Cards (the Sentence builder is on page 11)




Notes:

- 53 phrases in 7 topics: Greetings, Thanks and sorry, About me, Food and market, Directions, Numbers and time, Help and safety.
- 'Tap to hear' (speaker) is built for phrases and tiles but switched off until recordings exist.

B = Sentence builder (page 11). The language chosen here is remembered for the next visit.

Sentence builder

Scene Phrasebook - Builder: put the words of a phrase in the right order




Notes:

- Next sentence = the next phrase of the topic, then the first phrase of the next topic; after the very last phrase the button reads Back to topics.
- Try again reopens the same sentence.
- See in Phrasebook opens the phrase card; Back arrow or Esc returns to the topics screen.

4 tries and 2 hints per sentence. The result card is shown after a win or when the tries run out.

Library

Scene 4 Library_menu: the dictionary of 63,540 words




Also on the Library screen:

- Word of the day, shown on the left.
- Recent searches (tap one to search again).
- Favorites list (tap one to open it).
- Both 'house' and 'balay' find the same entry, because search covers the English meaning, the word and the definition.

The Library screen is built in code when the scene starts; it needs no editor setup other than the three dictionary files.

Where progress is saved

What the player does, what is stored on the computer, and where it is shown



PlayerPrefs hold the lists and settings; player_data.json holds the profile (name, avatar, counts, learned words).