

Getting Started

- [Getting Started](#)
 - [Introduction](#)
 - [API Server](#)
 - [Identity Provider](#)
 - [Temp File Storage](#)
 - [Database](#)
 - [SCIM](#)
 - [Configuration](#)
 - [Logging](#)
 - [Example](#)
-

Introduction

The OnBase Document Management API is a Representational State Transfer, or REST, API offering programmatic access to an OnBase database. It includes endpoints for various OnBase activities including, but not limited to, viewing and uploading Document content and Document metadata, viewing and replacing Keyword data on a Document, executing Custom Queries, and retrieving various OnBase configuration items, such as Document Types, Keyword Types, File Types, and others.

API Server

The Document Management API lives on the OnBase API Server. It is a home for RESTful services for customers desiring a more traditional deployment. Most configuration of the Document Management API will take place under the OnBase API Server. For more information about the OnBase API Server, see the [OnBase API Server](#)

Identity Provider

The Document Management API requires an instance of the Hyland Identity Provider or IdP. The Hyland IdP will authenticate and authorize the current user. For more information on the Hyland IdP, see the [Identity and Access Management Services Module Reference Guide \(MRG\)](#).

Temp File Storage

The Document Management API uses a temp file storage solution for uploading Documents and retrieving partial content of Documents. The OnBase API Server comes with a temp file storage solution that will work with the Document Management API. For more information about the Temp File Service API, see the [OnBase API Server Module Reference Guide \(MRG\)](#).

Database

The Document Management API requires an OnBase Database. It requires no extra database set up or configuration.

SCIM

The Hyland SCIM (System for Cross-domain Identity Management) server is required to use the Hyland IdP to authenticate users in OnBase. It is installed as part of the API Server. For more information about the Hyland SCIM server, see the [Identity and Access Management Services Module Reference Guid \(MRG\)](#).

Configuration

There are several configuration files in the API Server that are utilized by the Document Management API. These can be found in the config folder of the API Server. First is 1_server.json. There are items for the IdP address, the address for the Temp File Service, and the tenant. Next is 5_document_management.json. It has two options: AllowedOrigins and IdP Scope Name. Allowed Origins is a semicolon separated list of the origins allowed for cross-origin resource sharing, or CORS. It is optional. If no list is supplied, no cross-origin resource sharing will be allowed. The IdP Scope Name is the name of the scope of the API resources that a client can access from. Scopes are configured on the IdP and this name needs to match one on the IDP being used. It is required. Finally, there is 5_tempfs.json. There are options for the IdP Scope Name and the tenant for the Temp File Service. This is different from the tenant for the server as a whole. For more information about these items and configuring the API Server in general, see the [OnBase API Server Module Reference Guide \(MRG\)](#).

Logging

Logging in the Document Management API is quite flexible. It can be routed to several different services with a configurable minimum level. Logging is built around Microsoft.Extensions.Logging.ILogger and Serilog so it can log to the ELK stack ("ELK" is the acronym for three open source projects: Elasticsearch, Logstash, and Kibana), or file (among others) as well as the Hyland Diagnostics Console where logs will appear under the API Server tab. Logging can be configured through the API Server in the configuration file 0_logging.json. Out-of-the-box, there should already be a route for configured for the Diagnostics Console and example, commented-out routes for writing to Console and File.

Example

Here's a diagram showing how the pieces work together. This is for a request for a Document content range, to show the Temp File Service.

