CAPPA hardworker License Guide

Buying renewing and activating a license

> All screenshots use fictional wallets and an example invoice. Do not pay the illustrated 979.42 NACKL. Pay only the amount in your own active invoice.


1 Open the license screen

A license is required only for mining. There is no license-imposed limit on saved wallets; public wallet information can load without a license. Select 1–200 wallets for an automatic purchase.

Select the wallets to license
Load your wallets, then use the checkboxes in Subscription / payment to select up to 200. Other loaded wallets may stay; unselected wallets are not licensed by this payment.

Wait for levels
Every selected wallet needs a valid address and level. The server verifies identity and level, allowing a price declaration up to one level below the verified level. Wait if information is missing.

Open the menu
Open the menu and click Enter / Renew License. Subscription / payment opens by default. License code remains the manual alternative.



The public 1.0.88 license card; all shown data is fictional.

- An existing license does not automatically license unrelated newly added wallets. Saving a wallet does not give it mining permission.
- Automatic renewal preserves the previous licensed wallet addresses and count. Contact support before changing the licensed group or replacing a wallet.
- An existing manual license no longer blocks automatic renewal: its signature is verified on the server and its remaining term is preserved. If verification fails, no new payment is created; retry or contact support instead of deleting records.

2 Prepare your payment

Choose your options first. Preparing the payment creates an invoice; it does not send funds from your wallet.

Choose currency and duration

Select NACKL or SHELL and 30, 60 or 90 days. Total remaining automatic-license time cannot exceed 90 days, including early renewal. Options that exceed the limit are disabled.

Click Prepare payment

The service verifies selected wallets and calculates the current price before creating the invoice. Use only Amount to pay, CAPPA recipient address and Time left to pay in your own app. Currency and duration remain fixed until that invoice is resolved.

Use the current invoice

The five-minute payment window begins when the invoice is created. Use the amount and address displayed in your own miner, not a screenshot or an old invoice.



Example: two of three loaded wallets selected; 30 days, a fictional 979.42 NACKL invoice and a 05:00 payment window.

- Send exactly both decimal places. For example, an active invoice for 979.42 needs 979.42, not 979 or 980. The pictured invoice is only an example.
- Do not create or pay a second invoice to fix a pending payment.

3 Send check and start

Send the payment yourself from your Acki Nacki wallet. The miner does not ask for your seed phrase or private key.

Approve the exact transfer


Use the Acki Nacki network, the selected NACKL or SHELL token, the displayed recipient and the exact invoice amount. Check these in the wallet before approving. This version has no verified payment QR that fills in the amount automatically.

Click Check payment

Click Check payment. Approval can usually take about 10 minutes; congestion or unavailable data may take longer. It requires at least five minutes after receipt plus successful chain checks. An in-window payment remains checkable after the countdown reaches zero. Do not pay again.

Start after activation

Wait for License verified and applied. Close the panel and press START ALL. A newly applied entitlement enables licensed AUTO preferences once, but does not start mining for you. Only licensed eligible wallets may run.



Example of a verified and applied license. The zero countdown does not invalidate a payment received in time.

- Five minutes is the sending window, not a promise of license approval within five minutes. About 10 minutes is also an estimate, not a guaranteed deadline.
- Payment confirmed and license applied are separate steps. If the latter is missing, keep checking the same invoice instead of sending more funds.

4 Problems and manual activation


Keep the original transaction ID and invoice details if a payment needs review. Never send your seed phrase or private key.

Use a manual license code

Choose License code. Copy Device ID for the license issuer, obtain a code for this device, paste it into Activation / license renewal code and click Apply code. This path remains an alternative; an unresolved automatic invoice may temporarily lock it.

After an ordinary reinstall

On the same Windows user profile, preserved device authentication can recover owned invoices and the current license. A different computer, Windows profile, or deleted authentication data is not guaranteed to recover automatically. Do not repurchase merely because recovery is still pending.



Manual activation remains available. This form follows the WebView language: Turkish when that language is Turkish, otherwise English.

- Countdown 00:00: do not send a new payment. If you already paid in time, check the same invoice. If unpaid, wait for the service to finish the unpaid check before preparing another.
- Verification unavailable: retry the check later. The message does not mean that payment failed or that you should pay again.
- Request cancellation: hides the invitation to pay, but is not an instant financial cancellation or refund. A payment already sent can still be detected; wait for resolution.
- A disabled duration means that renewal would exceed 90 remaining days. Choose an allowed duration or renew later.