

- General Options
- Diagram Options
- Object Display Options
- Connector Display Options
- Communication Message Colors
- XML Specifications

XML Specifications

Many of the model development and management tasks you perform operate either directly or indirectly with XML. You can set defaults on a number of settings to standardize the way in which you use XML in your own modeling activities. You can override several of these settings on any specific XMI import or export, especially when publishing a model Package in XMI to another modeling language or tool.

Access

Ribbon	Start > Appearance > Preferences > Preferences > XML Specifications
Keyboard Shortcuts	Ctrl+F9 XML Specifications

Notes



- If 'Export Alternate Images' is set, and you have Packages in your model under Version Control, then any alternative images used in those Packages are also exported to the Version Control repository when you check in the Packages; in this case, you would only select the checkbox if the alternative images are subject to frequent change
Otherwise, do not select this option and instead use the 'Settings > Model > Transfer > Export Reference Data' and 'Import Reference Data' ribbon options to manage alternative images

Set XML Specification Options

Field/Button	Action
Editor	Specify the default editor for reviewing any XML documents you o the system. Either: - Type in the location of the editor .exe file, or - Click on the  button and browse for the location
Code Page	Defaults to windows-1252; if you do not want to use this Code Pag your preferred code page reference. Setting a null encoding string results in the encoding tag being ent from the XML output.

Book a Demo

	Click on the Default button to restore the setting to the default Co
Format XML Output	Select the checkbox to set formatting of your XML output into hurr form as the default. Deselect the checkbox to show the XML as unformatted code.
Use DTD	Select the checkbox to default to using a Data Type Definition (DTI imports and exports. A DTD validates the correctness of the mode that no syntactical errors have occurred. Deselect the checkbox to set the default to not using a DTD.
Export Diagrams	Select the checkbox to default to including diagrams when you exp another format or tool.
Export Alternate Images	Select the checkbox to export any alternative images used in the n you export to XML.
Validate XML against Schema/DTD	Select the checkbox to validate the XML format against the schem Definition when loading an imported XML file.
Import using single transaction	Select the checkbox to make all XML import operations and all Pas from Clipboard operations default to being performed within a sin transaction. Deselect this checkbox to make all XML imports and paste Package default to being performed data item by data item, so that one fai block the whole operation (recommended for large imports/copie In either case, in any specific XML import operation the setting can overridden.
Write Log	Select the checkbox to write the execution activity to a log file or export XML. Deselect the checkbox to not record the activity of the import file.
Export Diagram Images	Select the checkbox to export diagrams as images when you expor

Image Type	If you select the 'Export Diagram Images' option, click on the drop-down and select the image format to export to. Select from metafile, bit and .jpeg.
Create placeholders for missing External References during XMI 1.1/2.1 and Native File Import	Select the checkbox to show, during the import of an Enterprise Architect exported XMI 1.1/2.1 or Native XML/XEA file, any missing: • Diagram elements, using a Boundary element as a placeholder • Diagram connectors, using a Dependency connector as a placeholder When importing an Enterprise Architect-exported XMI 1.1/2.1 or Native XML/XEA file with cross-Package references, use this option to visualize diagram items that are not yet in the model. A sample scenario would be, as shown here, exporting 'Package2' from 'Master.EAP' and importing it into 'New.EAP' - the Classes 'Class2' and the connector between them are shown using a placeholder diagram 'Package2'. Master.EAP :  New.EAP :  If the file is for a Package under Package Control or Version Control, the checkbox is not selected, it is overridden if the 'For all packages, create placeholders for external references' checkbox is selected on the 'Package Control Settings' dialog and/or 'Package Control Options' dialog.
Prefix Enterprise Architect Tagged Values in XMI 1.0 with ea\$	Select the checkbox to prefix any Enterprise Architect Tagged Values in XMI 1.0 you create, with ea\$.

Update Last Save Time	Select the checkbox to update the timestamp of the last time each Package was saved.
Report Cross Package Reference Deletions (XMI 1.1)	Select the checkbox to report any Package cross-references that w deleted when a Controlled Package from an 'incomplete' model is XMI 1.1.
Default XML Directory	Type in the location of the default XML directory to use when imp exporting XML, or click on the  button and browse for the local
Close	Click on this button to save the changes you have made, and to clc 'Preferences' dialog.

Learn more

- [Model Exchange in XMI Format](#)
- [Export MOF Model to XMI](#)
- [Export Reference Data](#)
- [Import Reference Data](#)

PrevNext

stay in touch

Products Enterprise Architect Pro Cloud Server Prolaborate	UML at a Glance UML Tools PHP UML Modeling Business Process Modeling Model Driven Architecture Requirements Management Software Development	Solutions Corporate Government Small/Medium Enterprise IT Professionals Trainers Academic	Resources UML 2.0 Tutorial Corporate Resources Developer Resources Media Resources	Support Online Manual User Forum Report a Bug Feature Request Compare Editions System Requirements	Global Partners Trainers Resellers Sister Companies Technical Partners Standards Organi
--	--	--	---	---	---