

Understood.

Your new NO_QTY philosophy is changing from:

“Cycle carry-forward planning model”

to

“Controlled WO execution model”

And honestly, this flow is much closer to real factory execution.

Your New Intended Flow (summarized)

Structure

- One NO_QTY SO → Many RS
 - One RS → Many WO
 - WO creation = MANUAL by user
 - WO should NOT auto-create from RS lock
-

New Operational Logic

Requirement Sheet (RS)

RS becomes:

- planning container
- target requirement
- execution bucket

Example:

- RS = 10000
-

Work Orders

User manually creates WOs under that RS.

Example:

- WO1 = 3000
- WO2 = 4000
- WO3 = 3000

This is now operator/planner-controlled.

Good decision.

Critical New Rule

WO completion depends on production completion

Example:

- WO1 = 3000
- Production done = 2500

Result:

- WO1 remains OPEN
- Remaining 500 stays inside SAME WO
- No carry-forward to next RS

This is the biggest conceptual change.

Meaning:

- shortage belongs to WO
- not RS cycle carry-forward

Very important difference.

Execution Sequence

User cannot move to next WO until previous WO completes

You said:

“after complete production only WO will close. & then only we give him WO2”

Meaning:

- sequential WO execution inside RS

So:

- WO2 blocked until WO1 completed
- WO3 blocked until WO2 completed

This becomes controlled shop-floor sequencing.

RS Auto Close Logic

RS closes only when:

- all WOs completed
AND
- total RS qty fulfilled

Example:

RS = 10000

WO1 = 3000 ✓

WO2 = 4000 ✓

WO3 = 3000 ✓

Then:

- RS auto-close

Correct.

Important Design Impact

This completely removes:

- old NO_QTY carry-forward logic
- Next RS shortage calculations
- WO auto-generation
- operator-first carry-forward model
- RS-to-RS pending propagation

Now pending qty lives inside:

- OPEN WO

not:

- next RS

This is a major architectural simplification.

My Important Questions (VERY important before implementation)

1. Can user create next RS while previous RS still OPEN?

You said:

“user can create RS any time”

So example:

SO:

- RS1 = 10000 (still open)
- RS2 = 5000 (new customer demand)

Question:

Should this be allowed?

OR

Should only one ACTIVE RS exist at a time?

This is the biggest pending clarification.

2. If WO1 partially produced and machine breaks for 3 days...

Should planner:

- continue same WO later
OR
- split remaining into new WO?

Example:

WO1 = 3000

Produced = 2500

Pending = 500

Can user:

- keep WO1 open only
OR
- create WO1A = 500?

Need your philosophy.

3. Is dispatch allowed before full RS completion?

Example:

RS = 10000

WO1 completed = 3000 QC passed

Can dispatch happen immediately?

I assume YES.

Please confirm.

Overall

This new model is:

- much more production-realistic
- easier to audit
- easier for operators
- easier for dashboards
- easier for planning
- closer to manufacturing ERP standards

And most importantly:

It removes the confusing RS carry-forward math that was creating continuous ambiguity.