VNC Bench Manager

EXE User Guide — v1.0

VNC Bench Manager

EXE User Guide — v1.0

1. About

VNC Bench Manager is a Windows desktop application for organizing and launching VNC bench connection files.

This guide is specifically for the **compiled `VNC_Bench_Manager.exe`**. No Python installation or source code is required to use the application.

---

2. Requirements

- Windows PC
- `VNC_Bench_Manager.exe`
- VNC `.vnc` files
- A VNC client/application associated with `.vnc` files in Windows

The application itself does not require Python to be installed.

---

3. Recommended Folder Structure

Keep the EXE and project folders together:

```
VNC_Bench_Manager/
│
├── VNC_Bench_Manager.exe
│
├── Honda/
│   ├── Bench01.vnc
│   ├── Bench02.vnc
│   └── Bench03.vnc
│
```

```
├── DRT Automation/
│   ├── Bench01.vnc
│   └── Bench02.vnc
│
├── OSV Automation/
│   └── Bench01.vnc
│
└── CNT PF23/
    └── Bench01.vnc
```

Important

The application uses the **folder containing `VNC_Bench_Manager.exe`** as its main application folder.

Therefore:

- Keep project folders beside the EXE.
- Do not put project folders inside `dist`.
- Do not move the EXE away from the project folders unless you also move the project folders with it.

---

4. Starting the Application

1. Open the `VNC_Bench_Manager` folder.
2. Double-click:

VNC_Bench_Manager.exe

3. The application opens and automatically detects project folders.
4. Each project appears as a tab.

No installation wizard is required.

---

5. Main Screen


The application contains:

- **File** menu
- **Project** menu
- Project tabs
- Bench buttons
- Vertical scrollbar


- Status/footer area

Example:

Project Tabs



Bench Buttons



---

6. Open a VNC Bench

To connect to a bench:

5. Select the required project tab.
6. Find the required bench.
7. **Left-click the bench button.**

The `.vnc` file is opened using the Windows file association.

For example:

Honda → Bench01

opens:

Honda\Bench01.vnc

The configured VNC application then handles the connection.

---

7. Scroll Through Benches

If a project contains many VNC files, use:

Mouse Wheel

Move the mouse over the bench area and scroll the mouse wheel.

Scrollbar

Use the vertical scrollbar on the right side of the project area.

This allows projects containing many benches to be managed without changing the window size.

---

8. Add a VNC File

Use:

File → Add VNC File

Then:

8. Select an existing project or enter a project name.
9. Enter the desired bench name.
10. Select the `.vnc` file.
11. Confirm the operation.

The application copies the selected VNC file into the selected project folder.

Example:

Selected project:

Honda

Bench name:

Bench15

Result:

Honda\Bench15.vnc

Existing Bench

If a VNC file with the same name already exists, the application asks whether you want to overwrite it.

---

9. Create a New Project

A project is represented by a folder beside the EXE.

You can create a new project using the application's project management functionality.

For example:

VNC_Bench_Manager.exe

HondaDRT AutomationNew Project```

The new project appears as a project tab.

---

10. Rename a Bench

To rename a bench:

12. Right-click the bench button.
13. Select **Rename**.
14. Enter the new name.
15. Confirm the rename.

Example:

Bench01.vnc

becomes:

Bench_Main.vnc

The physical VNC file is renamed inside the project folder.

---

11. Delete a Bench

To delete a bench:

16. Right-click the bench button.
17. Select **Delete**.
18. Confirm the deletion.

The corresponding `.vnc` file is removed from the project folder.

Important: Deletion affects the actual file on disk.

---

12. Project Menu

Select the required project tab and use the **Project** menu.

Available project operations include:

Project

├— Project Settings

├— Refresh Project

├— Open Project Folder

└— Delete Project

---

13. Project Settings

Open:

Project → Project Settings

The settings window shows information such as:

- Project Name
- Project Folder
- Number of VNC benches

You can also rename the project.

When a project is renamed, its physical folder is renamed as well.

Example:

Old:

DRT Automation

New:

DRT Automation V2```

---

14. Refresh Project

Use:

Project → Refresh Project

This reloads the selected project's VNC files.

Use this when:

- A VNC file was copied manually.
- A VNC file was renamed outside the application.
- A VNC file was deleted outside the application.
- The displayed bench list does not match the folder.

---

15. Refresh All Projects

If available in the application, use the refresh-all function to rebuild the project list and tabs from the folders beside the EXE.

This is useful after creating, renaming, or removing project folders manually.

---

16. Open Project Folder

Use:

Project → Open Project Folder

This opens the selected project's Windows Explorer folder.

You can then view or manage the actual `.vnc` files.

---

17. Delete a Project

To delete a project:

19. Select the project.
20. Open **Project**.
21. Select **Delete Project**.
22. Confirm the deletion.

Warning

Deleting a project removes the **actual project folder and its VNC files**.

For example:

DRT Automation ├— Bench01.vnc

├— Bench02.vnc

└— Bench03.vnc

Deleting the project removes that folder and its contents.

Use this function carefully.

---

18. Adding VNC Files Manually

You can also copy VNC files directly into a project folder using Windows Explorer.

Example:

VNC_Bench_Manager└— Honda ├— Bench01.vnc

├— Bench02.vnc

└— Bench03.vnc

After manually changing files, use:

Project → Refresh Project

to update the display.

---

19. Backup

The application stores the project configuration as normal folders and `.vnc` files.

To back up your benches, copy the project folders.

Example:

HondaDRT AutomationOSV AutomationCNT PF23```

You can copy these folders to another drive or backup location.

---

20. Moving the Application

To move VNC Bench Manager to another PC:

23. Copy `VNC_Bench_Manager.exe`.
24. Copy all project folders.
25. Keep the same folder structure.

Example:

New PC

└── VNC_Bench_Manager ├── VNC_Bench_Manager.exe

├── Honda ├── DRT Automation ├── OSV Automation └── CNT PF23```

Then double-click the EXE.

---

21. VNC File Association

When a bench is clicked, VNC Bench Manager opens the corresponding `.vnc` file through Windows.

If clicking a bench does not launch the VNC application:

26. Locate a `.vnc` file in Windows Explorer.
27. Right-click it.
28. Select **Open with**.
29. Select the appropriate VNC Viewer/application.
30. Set it as the default application for `.vnc` files if required.

Then try the bench button again.

---

22. If Projects Are Not Visible

Check the following:

Check 1 — EXE location

Make sure the project folders are beside the EXE:

VNC_Bench_Manager.exe

HondaDRT Automation```

Check 2 — Folder type

Each project must be a folder.

Check 3 — Refresh

Restart the application or use the project refresh function.

Check 4 — Folder contents

Make sure the project contains `.vnc` files if you expect benches to appear.

---

23. If a Bench Does Not Open

Check:

- The `.vnc` file still exists.
- The VNC application is installed.
- Windows has a default application associated with `.vnc`.
- The VNC configuration contains the correct host/connection information.

You can test the file directly by double-clicking the `.vnc` file in Windows Explorer.

---

24. Important Safety Notes

VNC files can contain connection information and may contain authentication credentials depending on how they were created.

Do not share VNC files publicly unless you have verified that they do not contain sensitive credentials.

Store the application and VNC files in a location accessible only to authorized users.

---

25. Quick Reference

---

26. Recommended Final Deployment

For normal use, keep only the following required items in the deployment folder:

VNC_Bench_Manager/

│

├── VNC_Bench_Manager.exe

│

├── Honda/

├── DRT Automation/

├── OSV Automation/

└── CNT PF23/

The Python source code, PyInstaller files, `build` folder, and `dist` folder are **not required for normal EXE users**.

VNC Bench Manager v1.0

© 2026 CB

Quick Reference

Action	How
Start application	Double-click VNC_Bench_Manager.exe
Open bench	Left-click bench
Scroll benches	Mouse wheel / scrollbar
Add VNC	File → Add VNC File
Rename bench	Right-click → Rename
Delete bench	Right-click → Delete
Project settings	Project → Project Settings
Refresh project	Project → Refresh Project
Open folder	Project → Open Project Folder
Delete project	Project → Delete Project