File Name: netcat.conf

**File Location:** /usr/local/Flume/conf/

## **File Content**

# Naming the components on the current agent NetcatAgent.sources = Netcat NetcatAgent.channels = MemChannel NetcatAgent.sinks = LoggerSink

# Describing/Configuring the source
NetcatAgent.sources.Netcat.type = netcat
NetcatAgent.sources.Netcat.bind = localhost
NetcatAgent.sources.Netcat.port = 44467
NetcatAgent.sources.Netcat.channels = MemChannel

# Describing/Configuring the sink
NetcatAgent.sinks.LoggerSink.type = logger
NetcatAgent.sinks.LoggerSink.channel = MemChannel

# Describing/Configuring the channel
NetcatAgent.channels.MemChannel.type = memory
NetcatAgent.channels.MemChannel.capacity = 1000
NetcatAgent.channels.MemChannel.transactionCapacity = 100

## **Execution**

Open a terminal and execute the agent

\$: cd \$FLUME\_HOME

./bin/flume-ng agent --conf \$FLUME\_CONF --conf-file \$FLUME\_CONF/netcat.conf --name NetcatAgent -Dflume.root.logger=INFO,console

```
gomathis@impc3120a: /usr/local/Flume
File Edit View Search Terminal Help
ounters:{} } }} channels:{MemChannel=org.apache.flume.channel.MemoryChannel{name
: MemChannel}} }
2017-07-27 11:25:25,374 (conf-file-poller-0) [INFO - org.apache.flume.node.Appli
2017-07-27 11:25:25,375 (lifecycleSupervisor-1-0) [INFO - org.apache.flume.instr
umentation.MonitoredCounterGroup.register(MonitoredCounterGroup.java:119)]    Monit
ored counter group for type: CHANNEL, name: MemChannel: Successfully registered
new MBean.
2017-07-27 11:25:25.377 (lifecycleSupervisor-1-0) [INFO - org.apache.flume.instr
umentation.MonitoredCounterGroup.start(MonitoredCounterGroup.java:95)] Component
type: CHANNEL, name: MemChannel started
017-07-27 11:25:25,377 (conf-file-poller-0) [INFO - org.apache.flume.node.Appli
017-07-27 11:25:25,377 (conf-file-poller-0) [INFO - org.apache.flume.node.Appli
ation.startAllComponents(Application.java:182)]                               Starting Source Netcat
017-07-27 11:25:25,378 (lifecycleSupervisor-1-1) [INFO - org.apache.flume.sourc
.NetcatSource.start(NetcatSource.java:155)] Source starting
017-07-27 11:25:25,380 (lifecycleSupervisor-1-1) [INFO - org.apache.flume.sourc
 .NetcatSource.start(NetcatSource.java:169)] Created serverSocket:sun.nio.ch.Ser
rerSocketChannelImpl[/127.0.0.1:4447]
2017-07-27 11:25:55,443 (SinkRunner-PollingRunner-DefaultSinkProcessor) [INFO -
} body: 68 61 6F 0D
                                                  hao. }
```

## Check whether Sink and source has started

## Now open an another terminal and type

telnet localhost 4447 (The port number which you assigned in the netcat.conf file

```
gomathis@impc3120a: ~

File Edit View Search Terminal Help
gomathis@impc3120a: ~$ telnet localhost 4447
Trying 127.0.0.1...
Connected to localhost.
Escape character is '^]'.
hao
OK
```

It should show "Connected" status.

Type any word or sentence and that should reflect in the agent terminal