

Lab Task # 7

Subject: Computer Networks



Submitted by:

Mian Daniyal Hassan

Sap ID:

70150006

Major:

**BS Computer
Science**

Section:

(C)

Date:


20th May, 2026

Submitted To:


Muhammad Shahzad

Lab Task Week-7

Topology Pic:



1. VTP-Server



The screenshot shows a network device's command-line interface (CLI) with a dark background. At the top, there is a title bar with a close button and a window icon. Below the title bar, there is a navigation menu with four tabs: "Physical", "Config", "CLI" (which is selected and highlighted in blue), and "Attributes". The main area of the window displays the CLI output. The output shows the configuration of VTP (VLAN Trunking Protocol) on a device named "VTP-SERVER". The configuration includes enabling VTP, setting the mode to server, and configuring the domain name to "UOL". The output also shows the state of the VTP protocol on various interfaces.


```
Physical Config CLI Attributes

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up

VTP-SERVER>enable
VTP-SERVER#
VTP-SERVER#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
VTP-SERVER(config)#
VTP-SERVER(config)#
VTP-SERVER(config)#interface FastEthernet0/1
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/2
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/3
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/2
VTP-SERVER(config-if)#
VTP-SERVER(config-if)#exit
VTP-SERVER(config)#interface FastEthernet0/1
VTP-SERVER(config-if)#vtp mode server
Device mode already VTP SERVER.
VTP-SERVER(config)#vtp domain UOL
Changing VTP domain name from uol to UOL
VTP-SERVER(config)##SW_VLAN-6-VTP_DOMAIN_NAME_CHG: VTP domain name changed to UOL.
```

Lab Task Week-7


2. VTP-Transparent



The screenshot shows a window titled "VTP-Transparent" with tabs for Physical, Config, CLI, and Attributes. The CLI tab is active, displaying a terminal session. The user enters 'en' to enter enable mode, then 'conf t' to enter configuration mode. They then set the VTP mode to transparent and the domain name to uol. The output shows that the device mode was already VTP transparent and the domain name was already set to uol.

```
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#
VTP-TRANSPARENT#en
VTP-TRANSPARENT#conf t
Enter configuration commands, one per line. End with CNTL/Z.
VTP-TRANSPARENT(config)#vtp mode transparent
Device mode already VTP TRANSPARENT.
VTP-TRANSPARENT(config)#vtp domain uol
Domain name already set to uol.
VTP-TRANSPARENT(config)#
```

3. VTP-client-cs (sw1)



The screenshot shows a window titled "sw1" with tabs for Physical, Config, CLI, and Attributes. The CLI tab is active, displaying a terminal session. The user enters 'en' to enter enable mode, then 'show vtp status' to display the current VTP configuration. The output shows that the device is in VTP client mode with domain name uol. They then enter 'conf t' to enter configuration mode.


```
VTP-CLIENT-CS>en
VTP-CLIENT-CS#show vtp status
VTP Version          : 1
Configuration Revision : 0
Maximum VLANs supported locally : 255
Number of existing VLANs : 5
VTP Operating Mode    : Client
VTP Domain Name       : uol
VTP Pruning Mode      : Disabled
VTP V2 Mode           : Disabled
VTP Traps Generation  : Disabled
MD5 digest            : 0xEC 0xA1 0x08 0xF4 0xCC 0x42 0x01 0x16
Configuration last modified by 0.0.0.0 at 0-0-00 00:00:00
VTP-CLIENT-CS#conf t
Enter configuration commands, one per line. End with CNTL/Z.
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
VTP-CLIENT-CS(config)#
```

Copy Paste


CS

- PC-PT — 10.0.0.1

Lab Task Week-7




- **PC-PT — 10.0.0.2**



Lab Task Week-7

4. VTP-client-se (sw2)



```
sw2
Physical Config CLI Attributes


port type.

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to
down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to
up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to
down
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/2, changed state to
up

VTP-CLIENT-SE>en
VTP-CLIENT-SE#show vtp status
VTP Version                : 1
Configuration Revision      : 0
Maximum VLANs supported locally : 255
Number of existing VLANs    : 5
VTP Operating Mode          : Client
VTP Domain Name              : uol
VTP Pruning Mode             : Disabled
VTP V2 Mode                  : Disabled
VTP Traps Generation        : Disabled
MD5 digest                   : 0xEC 0xA1 0x08 0xF4 0xCC 0x42 0x01 0x16
Configuration last modified by 0.0.0.0 at 0-0-00 00:00:00
VTP-CLIENT-SE#
```


SE

- PC-PT — 11.0.0.1




- PC-PT — 11.0.0.2

Lab Task Week-7



5. VTP-client-maths (sw3)



Math

- PC-PT — 13.0.0.1

Lab Task Week-7

13.0.0.1

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☒ DHCP ☒ Static

IPv4 Address 13.0.0.1

Subnet Mask 255.0.0.0

Default Gateway 0.0.0.0

DNS Server 0.0.0.0

IPv6 Configuration

☒ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::290:CFF:FED4:D9B2

Default Gateway

DNS Server

802.1X

☒ Use 802.1X Security

Authentication MD5

Username

Password

- **PC-PT — 13.0.0.2**

13.0.0.2

Physical Config Desktop Programming Attributes

IP Configuration

Interface FastEthernet0

IP Configuration

☒ DHCP ☒ Static

IPv4 Address 13.0.0.2

Subnet Mask 255.0.0.0

Default Gateway 0.0.0.0

DNS Server 0.0.0.0

IPv6 Configuration

☒ Automatic ☒ Static

IPv6 Address

Link Local Address FE80::209:7CFF:FE54:B03D

Default Gateway

DNS Server

802.1X

☒ Use 802.1X Security

Authentication MD5

Username

Password

Top