HotSpot Component

Here is the user story and acceptance criteria for the enhanced hotspot component.

User Story

Title: Enhanced Hotspot Component with Content Pop-ups

As a Sitecore Content Editor,

I want to configure image hotspots to display a content pop-up containing a headline, text, and an optional image,

So that I can provide users with immediate, rich product details directly on the page without forcing them to navigate away.

Acceptance Criteria

1. Backend Configuration (Content Editor)

- **AC 1.1: Data Template extension:** The existing Hotspot data template (used for both single images and mason galleries) is extended to include the following new optional fields:
  - *Pop-up Headline* (Single-Line Text)
  - *Pop-up Copy* (Rich Text)
  - *Pop-up Image* (Image field)
- **AC 1.2: Existing Field Retention:** The existing fields for "Position X-axis (%)" and "Position Y-axis (%)" and the existing product link field remain unchanged and functional.

2. Frontend Behavior (User Experience)

- **AC 2.1: Triggering the Pop-up:** If a hotspot datasource has data in the new Headline or Copy fields, clicking the hotspot icon opens a modal pop-up layer over the current page view instead of navigating away.
- **AC 2.2: Pop-up Content Display:** The modal pop-up displays the configured Headline, Rich text copy, and the optional Image (if provided in the backend).
- **AC 2.3: Closing the Pop-up:** The modal pop-up includes a clear "Close" (X) button. Clicking the close button or clicking anywhere outside the modal area (the backdrop) closes the pop-up.

- **AC 2.4: Legacy Fallback:** If the new content fields are empty, but the legacy product link field is populated, the hotspot behaves as it currently does (navigates to the product page).

3. Responsiveness & Layout

- **AC 3.1: Responsive Positioning:** The positioning of the hotspot icons (defined by the X/Y percentages) remains accurate relative to the underlying image content across all standard breakpoints (desktop, tablet, and mobile), even as the host image resizes. The component supports **various positioning options** on **desktop and mobile**.
- **AC 3.2: Mobile-Friendly Pop-up:** On mobile devices, the pop-up modal is sized appropriately for smaller screens (e.g., utilizing near full width with scrolling if the text is long), ensuring all content is readable and the close button is easily accessible. On **mobile**, clicking **two or more hotspots** opens a **modal window** displaying product information.
- **AC 3.3: Gallery Support:** The behavior described above functions correctly whether the hotspot is placed on a standalone image component or within a mason gallery component.
- **AC 3.4: Clustering:** Hotspots that are **44 pixels apart and less** should **cluster** and be **positioned accordingly**.

Adaptations to be discussed for content hotspots:

- The **headline link (title)** in a hotspot behaves like a **standard hyperlink** (**hover and focus states**) - Q: should the headline be a link?
- Hotspots setting is available on **ImageBlock** and **Masonry Gallery** - Q: more needed?

Current implementation in Sitecore

Ticket: NEO-398: Content component - Hotspots - MGL prio. 128 DEPLOYED IN PRODUCTION

Example Masonry Gallery



Frontend view & backend view Craft CMS




Click on the hotspots to discover each button's functionality in detail.
Starting the Purefoam experience
GROHE
Battery check
To check the battery level, press and hold the button for over 3 seconds.
If only one LED lights up, the battery level is between 1% and 20%. This indicates that it's time to charge the battery.
> 3s
1% - 20% LED
21% - 40% LED
41% - 60% LED
61% - 80% LED
81% - 100% LED
GROHE Purefoam


Click on the hotspots to discover each button's functionality in detail.
Starting the Purefoam experience
GROHE
Select duration
Press the button to enter the foam production duration mode.
Each press increases the duration, which is reflected on the LED indicator.
The minimum duration is 4 seconds, and the maximum is 15 seconds.
< 3s
4s LED
7s LED
10s LED
12s LED
15s LED
GROHE Purefoam

Hotspots | Content | Component Settings | Module Settings

Heading (optional)

Heading

Heading

Text Alignment	Left / Center / Right
Overline	
Headline	Starting the Purefoam experience
Subline	

Settings

Headline Hierarchy	Fließtext / H2 / H3 / H4 / H5 / H6
Headline Size	H1 / H2 / H3 / H4 / H5 / H6

+ Headline Settings

+ Heading

Image

01 hotspot im...

Hotspots

Hotspot	Set hotspot position
Hotspot-Type *	Overlay **Contents** Purefoam - Foam activation + Add an entry + Overlay / Tooltip

Hotspot	Set hotspot position
Hotspot-Type *	Overlay **Contents** Purefoam - Select duration + Add an entry


+ Overlay
Tooltip
+ New Hotspot
Hotspots
Content
Component Settings
Module Settings
Heading (optional)
Heading
Heading
Text Alignment

GROHE Training Companion

Entries > Nuggets >

- Dashboard
- Entries
- Globals
- Categories
- Assets
- Users
- Access Management
- Architect
- Feed Me
- SCORM Exporter
- Tracking
- Translation Service
- GraphQL
- Utilities 1
- Settings
- Plugin Store
- IdP-User-Export
- Cachewarmer
- Deleting old Neo blocks

Purefoam - Select duration

EN-GB – Current | Preview | View | Create a draft | Save

Title *
Purefoam - Select duration

Productline Theme
Standard

Color Theme
Light

Category & tags

Content Categories *	Tags
PUREFOAM ✖	+ Add a tag
+ Add a category	

Nugget Meta Information

Overline	
Headline *	Select duration
Subline	
Keyvisual	+ Add an asset / Upload a file
Searchable? *	
Reading Time	min.

Content Builder

Text / Media — Content

Heading (optional)

Heading

Heading

Text Alignment	Left / Center / Right
Overline	
Headline	Select duration
Subline	

Settings
+ Headline Settings

+ Heading

Text

Source | Styles

Press the button to enter the foam production duration mode.

Each press increases the duration, which is reflected on the LED indicator.

The minimum duration is 4 seconds, and the maximum is 15 seconds.

Button
+ Link Button | Sound Button | Simple Overlay | Complex Overlay

Image — Content | Component Settings

Image *

01 Duration ✖

+ Media

+ Add a block

Related Content
+ Add an entry

Slug	purefoam-select-duration
Author	EJ Eugen Jakob ✖
Post Date	2/25/2025 10:28 AM ✖
Expiry Date	

STATUS
EN-GB

NOTES ABOUT YOUR CHANGES

ACCESS GROUPS
GROHE ✖
+ Choose

TRANSLATION SERVICE

You can check, if all (sub-)elements are available in the target language.

Check if available and create them

Here an export process is initiated that can take some time. If the process is finished, you could download the export in the Translation Service module.

Create new translation export