

CAM BOT v3 · Deployment Infrastructure Document

Server Details

| Item | Value | |-----|-----| | Cloud | Google Cloud Platform (GCP) | | VM Name | instance-20260524-112031 | | Machine | f1-micro (0.25 vCPU, 614MB RAM) | | OS | Debian 12 (Linux 6.1) | | External IP | 136.111.68.229 | | Internal IP | 10.128.0.2 | | Region | (as selected during creation) | | Cost | ~\$7.11/month (~Rs 600/month) | | Username | ai18developer | | Password | ai18developer |

SSH Access

From Laptop

```
ssh -i ~/.ssh/id_ed25519_gcp ai18developer@136.111.68.229
```

SSH Key Location (Laptop)

```
Private: C:\Users\HP\.ssh\id_ed25519_gcp
Public:  C:\Users\HP\.ssh\id_ed25519_gcp.pub
```

Public Key (added to server)

```
ssh-ed25519
```

```
AAAAC3NzaC1lZDI1NTE5AAAAIFZb7TntdZyx/iigUklKemPbFk+ZTsn/LX7AT7zTruXa chittoorvamsi@gmail.com
```

From Mobile (Terminus App)

```
Host: 136.111.68.229
Port: 22
Username: ai18developer
Auth: Password (ai18developer) or import private key from laptop
```

From GCP Console

```
GCP Console · Compute Engine · VM instances · Click "SSH" button
```

Server File Structure

```
/home/ai18developer/trading-bot/
├── venv/                    · Python virtual environment
├── live/
│   ├── __init__.py
│   ├── config.py           · Strategy params + API config
│   ├── strategy.py         · Signal detection + exit logic
│   ├── upstox_client.py    · Upstox API (data, orders, positions)
│   ├── trader.py           · Live trading orchestrator
│   ├── auth_server.py      · OAuth2 daily login
│   └── notify.py           · Telegram notifications
```

run_live.py	· Entry point (paper/live)
run_auth.py	· Daily Upstox login
bot.py	· Original backtest bot
data/	
5min/	· 47 CSV files (4 years of 5-min data)
journal/	· Daily trade journals

Upstox API Setup (YOU NEED TO DO THIS)

Step 1: Create Upstox Developer App

- 1 Go to: <https://account.upstox.com/developer/apps>
- 2 Login with your Upstox trading account
- 3 Click "New App"
- 4 App Name: CAM Bot
- 5 Redirect URL: <http://localhost:5000/callback>
- 6 You will get:

- **API Key** (client_id)
- **API Secret** (client_secret)

Step 2: Set Environment Variables on Server

```
ssh -i ~/.ssh/id_ed25519_gcp ai18developer@136.111.68.229
cat > ~/trading-bot/.env.live << 'EOF'
UPSTOX_API_KEY=your_api_key_here
UPSTOX_API_SECRET=your_api_secret_here
UPSTOX_REDIRECT_URI=http://localhost:5000/callback
CAPITAL=100000
DATA_DIR=/home/ai18developer/trading-bot/data/5min
JOURNAL_DIR=/home/ai18developer/trading-bot/journal
TOKEN_FILE=/home/ai18developer/trading-bot/data/upstox_token.txt
EOF
```

Step 3: Daily Token Refresh

Upstox tokens expire at 3:30 AM IST daily. Before market opens:

```
cd ~/trading-bot && ./venv/bin/python run_auth.py
```

This opens browser for Upstox login. After login, token is saved automatically.

Note: For automated daily token refresh on server (no browser), you need to manually paste the token each morning until we set up headless OAuth.

Cron Job (Auto-Run)

```
Schedule: 10:10 AM IST, Monday-Friday
Command: cd /home/ai18developer/trading-bot && ./venv/bin/python
run_live.py
```

Log: /home/ai18developer/bot.log

View Cron

```
crontab -l
```

View Bot Log

```
tail -f ~/bot.log
```

Manual Run

```
cd ~/trading-bot
./venv/bin/python run_live.py           # Paper mode,
Rs 1L
./venv/bin/python run_live.py --capital 200000    # Paper, Rs
2L
./venv/bin/python run_live.py --live --capital 100000 # LIVE Rs 1L
```

Telegram Notifications (Optional)

Step 1: Create Telegram Bot

- 1 Open Telegram, search @BotFather
- 2 Send: /newbot
- 3 Name: CAM Bot Alerts
- 4 You get a **Bot Token**

Step 2: Get Chat ID

- 1 Send any message to your bot
- 2 Visit: <https://api.telegram.org/bot<TOKEN>/getUpdates>
- 3 Find "chat":{"id": YOUR_CHAT_ID}

Step 3: Add to Environment

```
# Add to .env.live:
TELEGRAM_BOT_TOKEN=your_bot_token
TELEGRAM_CHAT_ID=your_chat_id
```

Git Branches

Branch	Purpose	Status	production-v2	Strategy code + backtest results	FROZEN · never modify	live-trading-v1	Live deployment code	Active	main	Original code	Untouched

Repository

Remote: [git@github.com:chittoorking/stock_market.git](https://github.com/chittoorking/stock_market.git)

Daily Workflow

Time	Action	How
8:30 AM	Refresh Upstox token	Manual: run_auth.py or paste token
10:10 AM	Bot starts automatically	Cron job
10:15 AM	Scans 45 stocks for signals	Automatic
10:16 AM	Places orders (paper/live)	Automatic
10:17-3:00 PM	Monitors positions every minute	Automatic
3:00 PM	Closes all positions	Automatic
3:01 PM	Writes journal	Automatic
Evening	Check results	tail ~/bot.log or Telegram

Security Notes

- 1 **NEVER commit .env.live to git** · contains API secrets
 - 2 **Change server password** from default after setup
 - 3 **SSH key** is stored at ~/.ssh/id_ed25519_gcp on your laptop
 - 4 **Upstox token** expires daily · even if leaked, it's useless after 3:30 AM
 - 5 **GCP firewall** · only SSH (port 22) is open by default. Bot doesn't need any open ports.
-

Troubleshooting

Bot didn't run today

```
# Check cron log
grep CRON /var/log/syslog | tail -10
# Check bot log
tail -50 ~/bot.log
# Run manually
cd ~/trading-bot && ./venv/bin/python run_live.py
```

Upstox token expired

```
# Check token
cat ~/trading-bot/data/upstox_token.txt
# Refresh: paste new token manually
echo "NEW_TOKEN_HERE" > ~/trading-bot/data/upstox_token.txt
```

Server disk full

```
df -h
# Clean old logs
truncate -s 0 ~/bot.log
```

Server down / restarted

Bot auto-starts via cron on next weekday at 10:10 AM. No action needed.

Cost Summary

Item	Monthly Cost	----- -----	GCP VM (f1-micro)	Rs 600 (~\$7.11)	Upstox API	Free	Telegram	
Free	Total 	Rs 600/month 	Bot Income 	Rs 2,40,000/month 				

Document generated: 2026-05-24 Server setup completed and verified.