# **Documentation**

#### Goal

Use tip strips, descriptions, and the VI properties to document a VI, as well as block diagram labels to fully document your code.

#### **Scenario**

Document the VI created from Numeric Data Types. You modify it to be user-friendly and easy for another developer to understand your VI.

## Design

The finished VI will look like Figure 1 and Figure 2.



Figure 1. Completed Front Panel






Figure 2. Completed Block Diagram

## **Implementation**

The files that you need to complete this exercise are here: <NI eLearning>\LV Core 1\Documenting Code\Exercise.

- 1. Open Meal Calculator.vi.
  - ☐ Open LabVIEW.
  - ☐ Select File»Open.
  - □ Navigate to Meal Calculator.vi from the <Exercise> directory and click **OK**.
- 2. Save the VI.
  - ☐ Select File»Save.
- 3. Add a title on the front panel.
  - □ Double-click the front panel to create a free label.
  - ☐ Type Order Your Meal Here.
  - ☐ Place the free label on the top of your VI.

4.	Between the Main Enum control and the # of Mains control, make a free label and enter x.	
5.	Repeat step 4 for the Drink Enum control and Side Enum control.	
6.	Add a System Chiseled Line decoration to the front panel.	
		Size and position the decoration to create a boundary above the Total Price indicator.
		Create another free label and enter the text Your total comes to, and place it beside the Total Price indicator.
7.	Set up the default tax value.	
		Type 8.5 inside the Tax Percentage control.
		Right-click the control and select <b>Data Operations»Make Current Value Default</b> .
8.	Add a free label to the block diagram.	
		Double-click the block diagram to create a free label.
		Type This part of the code calculates the main choices.
		Place this label on top of the part of the code where the main choices are calculated.
9.	Repeat step 8, for Side, Drink and Tax parts of the code.	
10.	Add labels on the block diagram.	
		Right-click the output wire of the Multiply function that calculates the Main choices.
		Select Visible Items»Labels.
		Type Price of Mains.
11. Repeat step 10, for		peat step 10, for Side and Drink wires.
12.	. Add a label on a function.	
		Right-click the Arithmetic Compound function and select <b>Visible Items»Label</b> .
		Type This function adds it up all together.

- 13. Modify the VI documentation.
  - ☐ Select File»VI Properties.
  - ☐ From the Category pull-down, select **Documentation**.
  - ☐ Enter the description text as shown in Figure 3.
  - ☐ Click **OK**.




Figure 3. VI Properties Panel

#### Test

- 1. Check the documentation of the VI by pressing <Ctrl-H> to bring up the Context Help menu.
- 2. Drag your mouse and place it on the VI icon on the top-right side of the block diagram or the front panel.




Figure 4. Context Help Window

- 3. Compare your VI to the provided solution VI.
- 4. Close the VI when you are finished.

### **End of Exercise**

## **Notes**