Nintendo TWL-System Photoshop Plug-Ins

Installation

Confidential

These coded instructions, statements, and computer programs contain proprietary information of Nintendo and/or its licensed developers and are protected by national and international copyright laws. They may not be disclosed to third parties or copied or duplicated in any form, in whole or in part, without the prior written consent of Nintendo.

Table of Contents

1	Preface	
2	Installing the Plug-Ins	<u>5</u>
	2.1 How to Install the Windows Version of the Plug-In	
	2.1 Flow to install the willdows version of the Flag-in	
3	How to Uninstall the Plug-Ins	6

1 Preface

These plug-ins are for use with the Windows 32-bit versions of Adobe Photoshop: CS2 (9.0.2), CS3 (10.0.1), and CS4 (11.0.1). Proper operation is not guaranteed in other versions.

2 Installing the Plug-Ins

2.1 How to Install the Windows Version of the Plug-In

- 1. Make sure that Photoshop is closed. If Photoshop is running, shut it down.
- 2. Copy files.

Plug-in files can be found within the %TWLSYSTEM ROOT%\tools\3DPlugins\Photoshop directory.

Copy all the files in the NNS_Photoshop_Plugin\File Formats folder into one of the following folders:

- For Photoshop CS2:
 - <Photoshop installation folder>\Plug-Ins\Adobe Photoshop Only\File Formats
- For Photoshop CS3:
 - <Photoshop installation folder>\Plug-Ins\File Formats
- For Photoshop CS4:
 - <Photoshop installation folder>\Plug-Ins\File Formats

Copy all the files in the NNS Photoshop Plugin\Filters folder into one of the following folders:

- For Photoshop CS2:
 - <Photoshop installation folder>\Plug-Ins\Adobe Photoshop Only\Filters
- For Photoshop CS3:
 - <Photoshop installation folder>\Plug-Ins\Filters
- For Photoshop CS4:
 - <Photoshop installation folder>\Plug-Ins\Filters

This completes the installation.

3 How to Uninstall the Plug-Ins

- 1. Make sure that Photoshop is closed. If Photoshop is running, shut it down.
- 2. Delete all the files you copied during the installation.

This completes the uninstall procedure.

Windows is the registered trademark of Microsoft Corporation (USA) in the U.S. and other countries.

Photoshop and Adobe are registered trademarks or trademarks of Adobe Systems, Incorporated.

All other company and product names in this document are the trademarks or registered trademarks of the respective companies.

Installation

© 2004-2009 Nintendo

The contents of this document cannot be duplicated, copied, reprinted, transferred, distributed, or loaned in whole or in part without the prior approval of Nintendo.