

# Fundamentals of Data Communications CSCI 5010

**IPv4** Addressing

Levi Perigo, Ph.D.
University of Colorado Boulder
Department of Computer Science
Network Engineering

### Review



# IPv4 Addressing

- IP address
  - Public & Private
- Networks and Subnets
  - Network Number & Broadcast
- Subnet Masks
  - Slash notation
    - Number of hosts (-2)

# Why IP Addresses?

- They uniquely identify each device on an IP network.
  - IP address is to Layer 3, what MAC is to Layer 2
- Every host (computer, networking device, printer, scanner, peripheral, etc.) must have a unique address.
- IP addresses are assigned by the organization/administer (typically)



#### **IP Address**

- IP network addresses consist of two parts:
  - network ID
  - host ID



- Similar to the address of a house:
  - The network portion is like the city, state, zip code
  - The host portion is like the house and street number
- IPv4 addresses have 32 binary bits
  - Binary = 0s and 1s
- Divided into four "sections" called octets
- Displayed in dotted decimal format
  - 192.168.154.218



#### Powers of 2

Power of 2	Calculation	Value
20		1
21	2	2
<b>2</b> <sup>2</sup>	2 * 2	4
<b>2</b> <sup>3</sup>	2 * 2 * 2	8
24	2 * 2 * 2 * 2	16
<b>2</b> <sup>5</sup>	2 * 2 * 2 * 2 * 2	32
<b>2</b> <sup>6</sup>	2 * 2 * 2 * 2 * 2 * 2	64
<b>2</b> <sup>7</sup>	2 * 2 * 2 * 2 * 2 * 2 * 2	128



### Decimal vs. Binary Numbers

- Decimal numbers are represented by the numbers 0 through 9.
- Binary numbers are represented by a series of 1s and 0s.
  - Machines/Computers read binary

Decimal	Binary
0	0
1	1
2	10
3	11
4	100
5	101
6	110
7	111
8	1000
9	1001

Decimal	Binary
10	1010
11	1011
12	1100
13	1101
14	1110
15	1111
16	10000
17	10001
18	10010
19	10011



# IP Address Format: Dotted Decimal Notation 128 64 32 16 8 4 2


	Example				
An IP address is a 32-bit binary number	10101100	00010000	10000000	00010001	
For readability, the 32-bit binary number can be divided into four 8-bit octets	10101100	00010000	10000000	00010001	
Each octet (or byte) can be converted to decimal	172	16	128	17	
The address can be written in dotted decimal notation	172.	16.	128.	17	

The binary-to-decimal and decimal-tobinary conversion will be detailed later



#### IP Address

 Certain IP addresses (network and broadcast) are reserved and cannot be assigned to individual network devices.



 IP addresses are broken down into ranges called classes



#### IP Address Classes: The First Octet

#### A B C ... Easy as 1 2 3

Class A ... First 1 bit fixed

 $0 \times \times \times \times \times \times$ 

Host

Host

Host

Class B ... First 2 bits fixed

10xxxxxx

Network .

Host

Host

Class C ... First 3 bits fixed

110xxxxx

Network . Network

Host



# IP Address Ranges

IP Address Class	First Octet Binary Value	First Octet Decimal Value	Possible Number of Hosts
Class A	1-126	1-126 <u>0</u> 00000001 to <u>0</u> 1111110* 16	
Class B	128-191	10000000 to 10111111	65,534
Class C	192-223	11000000 to 11011111	254

\*127 (01111111) is a Class A address reserved for loopback testing and cannot be assigned to a network.



#### IP Addresses: Public vs. Private

 Internet hosts require a globally unique, public IP address

 Private hosts can have any valid private address that is unique within the private network

# Private IP Addresses (RFC 1918)

Class	Private Address Range				
А	10.0.0.0 to 10.255.255.255				
В	172.16.0.0 to 172.31.255.255				
С	192.168.0.0 to 192.168.255.255				



#### Public IP Addresses

Class	Public IP Ranges					
Α	1.0.0.0 to 9.255.255.255 11.0.0.0 to 126.255.255.255					
В	128.0.0.0 to 172.15.255.255 172.32.0.0 to 191.255.255.255					
С	192.0.0.0 to 192.167.255.255 192.169.0.0 to 223.255.255.255					



# Exercise



# **Decimal-to-Binary Conversion**

Base <sup>Exponent</sup>	2 <sup>7</sup>	2 <sup>6</sup>	2 <sup>5</sup>	2 <sup>4</sup>	<b>2</b> <sup>3</sup>	2 <sup>2</sup>	2 <sup>1</sup>	2 <sup>0</sup>
Place Value	128	64	32	16	8	4	2	1
Example: Convert decimal 35 to binary	0	0	1	0	0	0	1	1

$$35 = 2^{5} + 2^{0}$$
  
 $35 = (32*1) + (2*1) + (1*1)$   
 $35 = 0 + 0 + 1 + 0 + 0 + 0 + 1 + 1$   
 $35 = 00100011$ 



# Decimal-to-Binary Conversion

· 128 64 32 16 8 4 2 1

## Binary-to-Decimal Conversion

Base <sup>Exponent</sup>	2 <sup>7</sup>	2 <sup>6</sup>	2 <sup>5</sup>	2 <sup>4</sup>	2 <sup>3</sup>	2 <sup>2</sup>	2 <sup>1</sup>	2 <sup>0</sup>
Place Value	128	64	32	16	8	4	2	1
Example: Binary Number	1	0	1	1	1	0	0	1
Decimal Number Total: 185	128	0	32	16	8	0	0	1

```
1\ 0\ 1\ 1\ 1\ 0\ 0\ 1 = (128 * 1) + (64 * 0) + (32 * 1) + (16 * 1) + (8 * 1) + (4 * 0) + (2 * 0) + (1 * 1)

1\ 0\ 1\ 1\ 1\ 0\ 0\ 1 = 128 + 0 + 32 + 16 + 8 + 0 + 0 + 1

1\ 0\ 1\ 1\ 0\ 0\ 1 = 185
```




# Binary-to-Decimal Conversion

· 128 64 32 16 8 4 2 1

# Subnetting and Subnet Masks

- Networks are often divided into smaller subnetworks (subnets)
  - Subnets can improve network performance, management, and security
    - Broadcast domain
- A subnet address extends the network portion
  - Borrows bits from the original host portion and designates them as the subnet field
- Determining the optimal number of subnets and hosts depends on the type of network and the number of host addresses required.

IP Address Class	First Octet Binary Value	First Octet Decimal Value	Possible Number of Hosts	
Class A	1-126 <u>0</u> 0000001 to <u>0</u> 1111110* 16,777,2			
Class B	128-191	10000000 to 10111111	65,534	
Class C	192-223	11000000 to 11011111	254	



Network

Network

Host



110xxxxx


Class C ... First 3 bits fixed

# Subnetting and Subnet Masks

- Subnet mask
  - The "tool" that the router uses to determine which bits are routing (network and subnet) bits and which bits are host bits.
- End systems use subnet masks to compare the network portion of the local network addresses with the destination addresses of the packets to be sent.
- Routers use subnet masks to determine if the network portion of an IP address is on the corresponding routing table or if the packet needs to be sent to the next router.

#### What does a Subnet Mask do?

- Tells the router the number of bits to look at when routing
- Defines the number of bits that are significant
- Used as a measuring tool, not to hide anything





#### Octet Values of a Subnet Mask

128	64	32	16	8	4	2	1		
1	0	0	0	0	0	0	0	=	128
1	1	0	0	0	0	0	0	=	192
1	1	1	0	0	0	0	0	=	224
1	1	1	1	0	0	0	0	=	240
1	1	1	1	1	0	0	0	=	248
1	1	1	1	1	1	0	0	=	252
1	1	1	1	1	1	1	0	=	254
1	1	1	1	1	1	1	1	=	<b>255</b>

Subnet masks, like IP addresses, are represented in the dotted decimal format like 255.255.255.0



# Slash Notation or (CIDR)

Bits used for mask	Default netmask	Subnet binary
/8	255.0.0.0	1111111.00000000.00000000.00000000
/16	255.255.0.0	1111111111111111100000000.00000000
/24	255.255.255.0	11111111.1111111.11111111.00000000

Network: 172.16.56.0

Computer 1: 172.16.56.40

Computer 2: 172.16.56.55

Printer 1: 172.16.56.100

IP address: 172.16.56.40

Mask: 255.255.255.0

Binary mask: 111111111.11111111.1111111.00000000



25

#### Possible Subnets and Hosts for a Class C Network



Number of Bits Borrowed (s)	Number of Subnets Possible <sup>(2<sup>s</sup>)</sup>	Number of Bits Remaining in Host ID (8-s=h)	Number of Hosts Possible Per Subnet (2 <sup>h</sup> - 2)	
1	2	7	126	
2	4	6	62	
3	8	5	30	
4	16	4	14	
5	32	3	6	
6	64	2	2	
7	128	1	2	

D	Onlandation	Makes
Power of 2	Calculation	Value
20		1
2 <sup>1</sup>	2	2
22	2 * 2	4
23	2 * 2 * 2	8
24	2 * 2 * 2 * 2	16
2 <sup>5</sup>	2 * 2 * 2 * 2 * 2	32
2 <sup>6</sup>	2 * 2 * 2 * 2 * 2 * 2	64
27	2 * 2 * 2 * 2 * 2 * 2 * 2	128



## How many Networks or Hosts?




Power of 2	Calculation	Value
20		1
2 <sup>1</sup>	2	2
2 <sup>2</sup>	2 * 2	4
2 <sup>3</sup>	2 * 2 * 2	8
24	2 * 2 * 2 * 2	16
2 <sup>5</sup>	2 * 2 * 2 * 2 * 2	32
2 <sup>6</sup>	2 * 2 * 2 * 2 * 2 * 2	64
27	2 * 2 * 2 * 2 * 2 * 2 * 2	128

128 64 32 16 8 4 2 1




# Subnetworks (Subnets)

- Smaller networks are easier to manage.
- Overall traffic is reduced.
- You can more easily apply network security policies.




#### **End System Subnet Mask Operation**






#### How Routers Use Subnet Masks





#### Applying the Subnet Address Scheme



#### \*Remember: Reserved Address

Network Addresses 32 Bits -**Network** 0000000000000000 Broadcast Addresses 32 Bits ———— **Network** 11111111111111111



# Eight Easy Steps for Determining Subnet Addresses

IP Address: 192.168.221.37 Subnet Mask /29

Step	Description	Example	
1.	Write the octet that is being split in binary.	Fourth octet: 00100101	
2.	Write the mask or classful prefix length in binary.	Assigned mask: 255.255.255.248 (/29) Fourth octet: 11111000	
3.	Draw a line to delineate the significant bits in the assigned IP address. Cross out the mask so you can view the significant bits in the IP address.	Split octet (binary): 00100100 Split mask (binary): 11111000	



# Eight Easy Steps for Determining Subnet Addresses (Cont.)

Step	Description	Example	
4.	Copy the significant bits four times.	00100 000 (network address) 00100 001 (first address in subnet) 00100 110 (last address in subnet) 00100 111 (broadcast address)?  Completed Subnet Addresses	
5.	In the first line, define the network address by placing all zeros in the significant bits.		
6.	In the last line, define the broadcast address by placing all ones in the significant bits.	Network address: 192.168.221.33 Subnet mask: 255.255.255.248 First subnet: 192.168.221.32 First host address: 192.168.221.3 Last host address: 192.168.221.3	
7.	In the middle lines, define the first and last host number.	Drag depot addraga, 100 160 201	
8.	Increment the subnet bits by one.	0010 <mark>1</mark> 000 (next subnet)	



# Example: Applying a Subnet Mask for a Class C Address

IP Address 192.168.5.139 Subnet Mask 255.255.255.224

IP Address	192	168	5	139	
IP Address	11000000	10101000	00000101	100 <mark>01011</mark>	
Subnet Mask	11111111	11111111	11111111	111 <mark>00000</mark>	/27
Subnetwork	11000000	10101000	00000101	10000000	
Subnetwork	192	168	5	128	
First Host	192	168	5	10000001=129	
Last Host	192	168	5	10011110=158	
Directed Broadcast	192	168	5	10011111=159	
Next Subnet	192	168	5	10100000=160	



#### Subnet Calculator

#### You must know the following:

- What is an IP address?
- Why and how is it used?
- What is a subnet?
- What is a subnet mask?
- How is a subnet mask used?

Use a subnet calculator

# Dynamic Host Configuration Protocol (DHCP)

### Every device needs an IP address

Used to be manual on every machine

### Dynamically assigns IP addresses


- IP address
- Subnet mask
- Default-gateway
- Primary DNS server
- Secondary DNS server

#### Server service

Windows, Linux, Router


#### UDP

Ports 67 & 68



## DHCP – (DORA)

- Client
  - Discover Request (Broadcast)
- Server
  - Offer
- Client
  - Request
- Server
  - Acknowledgement



# Why IPv6

- IPv4 address depletion
  - Developing countries
  - Mobile IP
  - -loT
  - Rise in price of v4 addresses (commodity)
  - NAT workarounds
- End-to-end connectivity
- Security

## Barriers to IPv6

- Not compatible with IPv4
- IPv6 Security
  - Firewalls
  - Tunneling
- Trained and experienced professionals to support IPv6
- Buy in
  - ISP vs. Business



# IPv4 and IPv6 Comparison

Feature	IPv4	IPv6
IP Address Length	32 bits	128 bits
IP Security (IPSec) Header	Optional	On through traffic
Support		
Prioritized Delivery Support	Some	Expanded
Packet Fragmentation	Performed by hosts and	Performed by hosts only
	routers	
Minimum MTU	576 bytes	1280 bytes
Checksum in Packet Header	Yes	No
Options in Packet Header	Yes	No
Link-Layer Address Resolution	ARP (broadcast)	Multicast ND messages
Multicast Membership Protocol	Internet Group Management	Multicast Listener Discovery
	Protocol(IGMP)	(MLD)
Router Discovery	Optional	Required
Uses Broadcast Messages	Yes	No
Configuration	Manual, Dynamic Host	Manual, Automatic, DHCP
	Control Protocol (DHCP)	version 6 (DHCPv6)
Domain Naming System (DNS)	Uses A records	Uses AAAA records
Queries		
DNS Reverse Queries	Uses IN-ADDR.ARPA	Uses IP6.ARPA



## **Transition Mechanisms**

### Dual stack

Both stacks can operate independently or in parallel

### Tunneling

- ISATAP
- Teredo
- 6to4
- 6over4
- 6rd (IPv6 Rapid Deployment)

### Transition


NAT64

# IPv6 Advantages

- Increased address space
- Streamlined IP header
- End-to-end connectivity
- Removal of IP broadcasts
- Mobile IPv6



## Addressing



- •IPv4 32 bits, 2<sup>32</sup>
- =~ 4,200,000,000 possible addressable nodes
- •IPv6 128 bits, 2<sup>128</sup>
- = 340,282,366,920,938,463,463,374,607,431,768,211,456 nodes



## IPv6 Address Syntax

- IPv6 address in binary form
- Divided along 16-bit boundaries



# IPv6 Address Syntax

- Each 16-bit block is converted to hexadecimal and delimited with colons
  - Each 16-bit block is called a hextet
  - 2001:0DB8:0000:2F3B:02AA:00FF:FE28:9C5A
- Leading zeroes in any 16 bit hextet can be omitted (or reduced)
  - 2001:0DB8:0000:2F3B:02AA:00FF:FE28:9C5A
  - 2001:DB8:0:2F3B:2AA:FF:FE28:9C5A



# Addressing Tricks – Compressing Zeros

- A single contiguous sequence of 16-bit blocks set to 0 can be compressed to "::" (double-colon)
  - Example:
    - FE80:0:0:0:2AA:FF:FE9A:4CA2 becomes FE80::2AA:FF:FE9A:4CA2
    - FF02:0:0:0:0:0:2 becomes FF02::2
    - FF02:0:0:0:0:0:0 becomes FF02::
  - Double-colon "::" can appear once in an address
  - Cannot use zero compression (double-colon) to include part of a 16-bit block
    - FF02:30:0:0:0:0:5 does not become FF02:3::5, but FF02:30::5



# Addressing Tricks – Compressing Zeros

- A hextet with all zeros can be reduced to a single zero
  - This is used when the double-colon has already been used
    - 2001:DB8::12:0000:0000:FE becomes 2001:DB8::12:0:0:FE
- Typically, upper vs. lower case doesn't matter



# IPv6 Challenges

IPv6 awareness

Measuring adoption

Security

Security Tools

# Questions?



## Lab



# **Appendix**



## Time Savers: Subnet number

### "Magic number" Strategy

- Use mask to determine trouble byte
  - /10 255. **1100 0000** . 0. 0
  - /20 255.255. 1111 0000 .0
  - /14 255. 1111 1100 .0.0
  - /29 255.255.255. 1111 1000
- Determine decimal value of such
  - · 192
  - · 240
  - · 252
  - · 248

## Time Savers: Subnet number

- "Magic number" Strategy ... cont
  - Subtract decimal value from 256
    - 256 192 = 64
    - 256 240 = 16
    - · 256 252 = 4
      - \_
    - 256 248 = 8
  - Find multiple of magic number closer but not greater than IP address value on similar octet, each multiple is a valid subnet

**Magic Number** 

- 100.100.100.100 /17
  - $-255.255.1000\ 0000.0\ 128\ 256-128 = 128$
  - Subnets 0 and 128
  - 100.100.0.0 is the subnet number

## Time Savers: Subnet number

### More examples

- 100.100.100.100 /18
  - -255.255.11000000.0192256-192 = 64
  - Subnets 0,64,128,192
  - 100.100.64.0 is the subnet number
- 100.100.100.100/19
  - -255.255.11100000.0224256-224 = 32
  - Subnets 0,32,64,96,128,160,192,224
  - 100.100.96.0 is the subnet number
- 100.100.100.100/20
  - -255.255.11110000.0240256-240 = 16
  - Subnets 0,16,32,48,64,80,96,112,128......
  - 100.100.96.0 is the subnet number

## Time Savers: Subnet Broadcast

#### 100.100.100.100 /18

- -255.255.11000000.0192256-192 = 64
- Subnets 0,64,128,192
- 100.100.64.0 is the subnet number
- 100.100.127.255 is the subnet broadcast address

### 100.100.100.100/19

- -255.255.11100000.0224256-224 = 32
- Subnets 0,32,64,96,128,160,192,224
- 100.100.96.0 is the subnet number
- 100.100.127.255 is the subnet broadcast address

### • 100.100.100.100 /20

- -255.255.11110000.0240256-240 = 16
- Subnets 0,16,32,48,64,80,96,112,128......
- 100.100.96.0 is the subnet number
- 100.100.111.255 is the subnet broadcast address

