

HARC Membership		
P *	Member Call Sign	Integer
	Member First Name	TEXT
F	Primary Key	Integer
🔑 HARC Membership PK (Member Call Sign)		

qso table v007		
P *	Primary Key	Integer
	My Grid	TEXT
	My Call Sign	TEXT
	My Radio	TEXT
	Call Sign	TEXT
	'first name'	TEXT
	'last name'	TEXT
	'street'	TEXT
	'city'	TEXT
	'county'	TEXT
	'state'	TEXT
	'postal country'	TEXT
	'zip'	TEXT
	'grid'	TEXT
	'dxcc country'	TEXT
	'iota'	TEXT
	'sota'	TEXT
	'cq zone'	TEXT
	'itu'	TEXT
	'ten ten'	TEXT
	'email'	TEXT
	'url'	TEXT
	'mode'	TEXT
	'band rx'	TEXT
	'band tx'	TEXT
	'rst sent'	TEXT
	'rst received'	TEXT
	'qsl via'	TEXT
	'qsl sent'	TEXT
	'qsl received'	TEXT
	'srx'	TEXT
	'stx'	TEXT
	'comments'	TEXT
	'satellite'	TEXT
	'qso start'	REAL_0_0_0
	'qso done'	REAL_0_0_0
	'latitude'	REAL_0_0_0
	'longitude'	REAL_0_0_0
	'tx frequency'	REAL_0_0_0
	'rx frequency'	REAL_0_0_0
	'azimuth'	REAL_0_0_0
	'elevation'	REAL_0_0_0
	'power'	REAL_0_0_0
	'srx numeric'	Integer_0_0_0
	'stx numeric'	Integer_0_0_0
	'dxcc id'	Integer_0_0_0
	'contest id'	TEXT
	'my sota'	TEXT
	'skcc'	TEXT
🔑 qso table v007 PK (Primary Key)		

Additional QSO Details		
FF *	Primary Key	Integer
F *	Repeater Code	Integer
F *	Radio Type Code	Integer
F *	Power Type Code	Integer
F *	Antenna Type Code	Integer
🔑 Additional QSO Details PK (Primary Key)		

Repeater Types		
P *	Repeater Code	Integer
	Repeater Description	TEXT
	Repeater Call Sign	TEXT
	Repeater TX Frequency	REAL
	Repeater RX Frequency	REAL
	Repeater CTCSS	REAL
	Repeater Latitude	REAL
	Repeater Longitude	REAL
	Repeater Allstar Node Number	Integer
	Repeater Echolink Node	Integer
🔑 Repeater Types PK (Repeater Code)		

Radio Type		
P *	Radio Type Code	Integer
	Radio Type Description	TEXT
🔑 Radio Type PK (Radio Type Code)		

Antenna Type Code		
P *	Antenna Type Code	Integer
	Antenna Type Description	TEXT
🔑 Antenna Type Code PK (Antenna Type Code)		

Power Type Code		
P *	Power Type Code	Integer
	Power Type Description	TEXT
🔑 Power Type Code PK (Power Type Code)		