

ScrollReader Guide

Version 1.3.1 · WotLK 3.3.5a · Uncapped server · by Mhortai

What it does

Bulk-reads (consumes) scrolls from your bags — **every copy of a type in one press** — via the Uncapped server's mass-consume verb (SCRALL), the same mechanism behind the Dashboard's "Use in bulk" buttons. Six scroll types are covered:

- 1 **Wildcard Transmog Scroll**
- 2 **Sealed Traveler's Map**
- 3 **Scroll of Mastery**
- 4 **Scroll of the Delver**
- 5 **Scroll of Reach**
- 6 **Scroll of Bounty**

Client addons cannot loop item uses (each use of a spell-casting item requires its own hardware event), so the addon names the item and the server eats the whole stack in one call per type.

The bar (new in 1.2.0)

A draggable horizontal bar of **six buttons**, one per scroll type, each showing the item's icon and a live **count badge** of how many you hold. Press a button — or its keybind — to bulk-read that type instantly (no confirmation). Empty types render greyed. Drag anywhere on the bar (or its buttons) to move it; position is remembered.

Keybinds

Each of the six buttons can be bound to a key: **ESC** → **Key Bindings** → **scroll to the "ScrollReader" section** ("Read all: Scroll of Mastery" etc.). A button's tooltip shows its current binding. Keybinds act exactly like clicks — immediately.

Flow (every trigger)

- 1 Press a bar button / its keybind (one type), or the minimap button / /sr (all six types at once).
- 2 One SCRALL : <entry> request per type goes out **immediately** — **no confirmation dialog** (removed in 1.2.3 by owner choice; the scrolls are destroyed with no undo, so treat keybinds with respect).
- 3 The server's SCRDONE reply reports spent/remaining; a chat line summarizes it. When the **Uncapped Dashboard** is loaded, its [Scrolls] line appears instead (ScrollReader stays quiet to avoid duplicates).

Item entries are resolved live from your bag links by exact title — you can only bulk what you hold, so bags are always a sufficient source of the ID.

Dungeon-exit auto-read (new in 1.3.0)

About **5 seconds after you leave a 5-man dungeon** (party instance), ScrollReader checks your bags for **Scroll of Mastery** and **Scroll of the Delver**. Any of those two you hold **300 or more** of gets bulk-read automatically — no press needed. Other types are never auto-read.

- It **spam-pushes**: SCRALL is re-sent every 1.2s until your bags are empty of that type, even if the server answers "none used", up to 40 sends per type. One summary line at the end.
- SCRALL consumes the **whole stack**, not just 300 — 300 is only the trigger.

- Combat holds it; it resumes when combat ends.
- On by default. `/sr` `dungeon` toggles it.

Minimap button

Reads **all six types at once**, immediately (no confirmation). Free-form left-drag placement (exact position, no ring snapping; safe with scaled minimaps), with a badge showing the grand total held. *(The separate on-screen master button was removed in 1.2.2 — the bar and the minimap button cover both workflows.)*

Slash commands

Command	Effect
<code>/sr</code> or <code>/scrollread</code>	Read ALL six types at once
<code>/sr</code> <code>count</code>	Held counts per type, with item entry IDs
<code>/sr</code> <code>bar</code>	Show/hide the six-button bar
<code>/sr</code> <code>minimap</code>	Show/hide the minimap button
<code>/sr</code> <code>dungeon</code>	Toggle dungeon-exit auto-read (Mastery/Delver at 300+)
<code>/sr</code> <code>reset</code>	Reset all positions to defaults and show everything

Behavior notes

- **Combat:** everything greys out and presses (clicks and keybinds) do nothing while in combat.
- **Server whitelist:** all six types are bulk-whitelisted server-side as of 2026-09-14 (Wildcard Transmog Scroll = entry 500201, Sealed Traveler's Map = 500200). The server still accepts or rejects each entry independently; a rejection answers "none could be used" plus a server explanation line.
- **Maps ([#1350] server rules):** consumed at most **500 per server call**, they require **every eligible flight path known** first, each keeps its normal socket-scroll chance, and they are consumed even when they award nothing. When you hold more than 500, ScrollReader **auto-repeats the call** until your bags are empty of them, then prints one summary line — e.g. "read 1398 Sealed Traveler's Map over 3 calls." The repeat loop watches your bags, not the server's remaining count, so copies in your bank can't spin it.
- **Combat pauses the queue:** requests waiting to be sent (including auto-repeat calls) hold while you're in combat and resume when it ends.
- **Counts are descriptions, not instructions:** the server consumes what is actually in your bags at execution time; SCRDONE reports what really happened.
- **Matching is exact and case-sensitive** — variant titles are ignored by design.
- A 6-second **reply watchdog** covers the edge case of a server build with no SCROLL handler at all (this realm answers rejections properly, so you should never see it).

Saved variables

ScrollReaderDB stores positions and visibility (minimap button, bar) and the dungeon auto-read toggle. Delete it (or `/sr` `reset`) to restore defaults.

Changelog

v1.3.0 — 2026-09-27

- **New: dungeon-exit auto-read** (idea borrowed from UncappedAutoScroll). ~5s after leaving a party instance, Scroll of Mastery and Scroll of the Delver are bulk-read automatically when 300+ are held. The chain spam-pushes SCROLL (keeps re-sending even on used=0) until bags are clean, capped at 40 sends per type. Combat holds it. On by default; /sr dungeon toggles.
- A type whose chain is already running is no longer queued twice.
- Reply-watchdog timeout now also clears that type's chain state.

v1.2.3 — 2026-09-14

- **Confirmation dialog removed** for all six types, by owner decision: every trigger (bar click, keybind, minimap, /sr) sends SCROLL immediately. The SCRDONE chat line is the receipt. Map auto-chain unchanged. Note this deliberately trades away the accidental-keypress safety net.

v1.2.2 — 2026-09-14

- **Removed the on-screen master button** (the standalone floating scroll icon). The bar covers per-type reading and the minimap button (or /sr) covers read-everything; the extra button was redundant. Its stale saved-variables entry is cleaned on load, and /sr button is gone from the slash commands.

v1.2.1 — 2026-09-14

Server landed bulk support for both custom scrolls (Wildcard Transmog Scroll = 500201, Sealed Traveler's Map = 500200, per Dashboard [#1350]/[#1360]); this patch adapts to the maps' server rules.

- **Auto-chain for the 500-per-call map cap:** one confirmation covers the full stack, and ScrollReader re-sends SCROLL until your **bags** are empty of that type (bag scan as the loop condition, deliberately — SCRDONE's held counts bank copies SCROLL can't touch, and chaining on it would loop forever). A used=0 reply ends a chain; a 40-send budget caps it outright. One summary line replaces per-call chatter ("read 1398 ... over 3 calls").
- **Map-aware confirmation:** confirming >500 maps notes the 500-per-call rule and the auto-repeat.
- **Combat holds the send queue** (new sends and chained re-sends) and resumes after; previously only button presses were gated.
- Manual updated: whitelist now fully live; map rules (flight-path requirement, no-award consumption, socket-scroll chance) documented.

v1.2.0 — 2026-09-14

Six-type keybindable bulk bar.

- **New: the bar** — a draggable horizontal bar of six buttons (Wildcard Transmog Scroll, Sealed Traveler's Map, Scroll of Mastery, Scroll of the Delver, Scroll of Reach, Scroll of Bounty), each with the item's live icon, a held-count badge, and a tooltip showing its current keybind. Press = bulk-read that type via SCROLL. Empty types grey out. Dragging any part moves the bar; position persisted (/sr bar toggles it).
- **New: keybindings** — Bindings.xml exposes one binding per type under ESC → Key Bindings → ScrollReader ("Read all: <scroll>"). Keybinds behave exactly like clicks, confirmation dialog included (dialog-every-press was the chosen policy).
- **Master buttons widened:** the minimap and on-screen buttons (and /sr) now sweep **all six types** in one confirmation; their badges show the grand total held.
- Icons resolve live via GetItemIcon from bag-link entries; the four kirei scrolls carry their known entries (500203/500204/500205/500207) as icon fallbacks. Sends still use only live bag-link entries.
- /sr count now lists all six types.
- /sr reset resets all three movables (minimap, on-screen button, bar).
- Live-test note folded into the manual: rejection is not silence on this realm — non-whitelisted entries get SCRDONE used=0 plus a server explanation line, so the 6s watchdog is a never-fires edge case here.

v1.1.0 — 2026-09-07

Rework: server-verb bulk consume. v1.0.0's UseContainerItem sweep was taint-blocked in-game ("blocked from an action only available to the Blizzard UI") — these scrolls cast a spell on use, and protected calls can't be looped from addon code. v1.1.0 adopts the server's own mass-consume mechanism, as used by the Dashboard's "Use in bulk" buttons.

- **True one-press burst:** sends SCROLL:<itemEntry> (transport REAGENTBANK) per scroll type; the server consumes every bag copy in one call. Requests are spaced 1.2s apart.
- **Confirmation dialog** before anything is sent, quoting exact counts and names — the scrolls are destroyed with no undo (suite consent rule).
- SCRDONE:<entry>:<used>:<held> **reply handling** — three fields, matching what the server actually sends (the historical two-field pattern in UncappedScrolls was a known dead branch; not repeated here). Chat summary of spent/remaining; suppressed when the Uncapped Dashboard is loaded, since its [Scrolls] handler already prints one.
- **6s reply watchdog:** silence means the server's SCROLL whitelist likely doesn't cover the entry — the addon says so and prints the entry ID for a one-line admin ask.
- **Live count badges** on both buttons (total matching scrolls held; hidden at zero; refreshed on BAG_UPDATE).
- **Item entries resolved from bag links** by exact title at click time — no hardcoded IDs.
- New /sr count — per-type counts plus entry IDs.
- Removed: the v1.0.0 client-side UseContainerItem sweep and its per-click leftover semantics (obsolete — the server call is exhaustive).

v1.0.0 — 2026-09-07

Initial release.

- Burst reader for exact titles **Wildcard Transmog Scroll** and **Sealed Traveler's Map**: one click sweeps bags 0–4 and uses every matching, unlocked item. (*Superseded in v1.1.0 — this approach is taint-blocked for spell-casting items.*)
- Chat report per sweep with total and per-title counts; "no matching scrolls" when bags are clean.
- **Minimap button** with free-form drag (exact x/y from minimap center, no ring snapping; canonical LibDBIcon texture layout) — safe with scaled minimaps.
- **On-screen button** (36×36, draggable, clamped to screen, position persisted).
- Slash commands: /sr (/scrollread), /sr button, /sr minimap, /sr reset.
- Combat gating: both buttons desaturate and ignore clicks in combat; state also detected correctly when logging in mid-combat.
- SavedVariables: ScrollReaderDB (button positions + visibility only).
- 3.3.5a-safe: no C_Timer, no SetShown, all UI built after ADDON_LOADED.