

ScrollReader Guide

Version 1.2.3 · WotLK 3.3.5a · Uncapped server · by Mhortai

What it does

ScrollReader bulk-reads (consumes) scrolls from your bags — every copy of a type in one press — via the Uncapped server's mass-consume verb (SCRALL), the same mechanism behind the Dashboard's "Use in bulk" buttons. Six scroll types are covered:

- 1. Wildcard Transmog Scroll
- 2. Sealed Traveler's Map
- 3. Scroll of Mastery
- 4. Scroll of the Delver
- 5. Scroll of Reach
- 6. Scroll of Bounty

Client addons cannot loop item uses — each use of a spell-casting item requires its own hardware event — so the addon names the item and the server eats the whole stack in one call per type.

The bar

A draggable horizontal bar of six buttons, one per scroll type, each showing the item's icon and a live count badge of how many you hold. Press a button — or its keybind — to bulk-read that type. Empty types render greyed. Drag anywhere on the bar (or its buttons) to move it; the position is remembered. Toggle it with /sr bar.

Keybinds

Each of the six buttons can be bound to a key: ESC → Key Bindings → scroll to the "ScrollReader" section ("Read all: Scroll of Mastery" and so on). A button's tooltip shows its current binding. Keybinds act exactly like clicks — immediately.

Flow (every trigger)

- Press a bar button or its keybind (one type), or the minimap button / /sr (all six types at once).
- The request goes out immediately — no confirmation dialog (removed in 1.2.3 by owner choice). The scrolls are destroyed with no undo, so treat keybinds with respect.
- One SCRALL request per type goes out (spaced ~1.2s when several are queued).
- The server's SCRDONE reply reports spent/remaining; a chat line summarizes it. When the Uncapped Dashboard is loaded, its [Scrolls] line appears instead (ScrollReader stays quiet to avoid duplicates).

Item entries are resolved live from your bag links by exact title — you can only bulk what you hold, so bags are always a sufficient source of the ID.

Minimap button

Reads ALL six types at once under a single confirmation. Free-form left-drag placement (exact position, no ring snapping; safe with scaled minimaps), with a badge showing the grand total held. The separate on-screen master button was removed in 1.2.2.

Slash commands

<code>/sr, /scrollread</code>	Read ALL six types at once (asks first)
<code>/sr count</code>	Held counts per type, with item entry IDs
<code>/sr bar</code>	Show/hide the six-button bar
<code>/sr minimap</code>	Show/hide the minimap button
<code>/sr reset</code>	Reset all positions to defaults and show everything

Behavior notes

- **Combat:** everything greys out; presses do nothing and queued requests (including auto-repeat calls) hold until combat ends.
- **Server whitelist:** all six types are bulk-whitelisted server-side as of 2026-09-14 (Wildcard Transmog Scroll = entry 500201, Sealed Traveler's Map = 500200). The server accepts or rejects each entry independently.
- **Maps:** consumed at most 500 per server call; they require every eligible flight path known first; each keeps its normal socket-scroll chance; and they are consumed even when they award nothing. Holding more than 500 makes ScrollReader auto-repeat the call until your bags are empty of them, then print one summary line ("read 1398 ... over 3 calls"). The repeat loop watches your bags, not the server's remaining count, so bank copies can't spin it.
- **Counts are descriptions, not instructions:** the server consumes what is actually in your bags at execution time; SCRDONE reports what really happened.
- **Matching is exact and case-sensitive** — variant titles are ignored by design.
- A 6-second reply watchdog covers the edge case of a server build with no SCRALL handler at all (this realm answers rejections properly, so you should never see it).

Saved variables

ScrollReaderDB stores only positions and visibility (minimap button, bar). Delete it (or `/sr reset`) to restore defaults.

Changelog

v1.2.3 — 2026-09-14

- **Confirmation dialog removed** for all six types, by owner decision: every trigger (bar click, keybind, minimap, `/sr`) sends SCRALL immediately. The SCRDONE chat line is the receipt. Map auto-chain unchanged. Note this deliberately trades away the accidental-keypress safety net.

v1.2.2 — 2026-09-14

- **Removed the on-screen master button** (the standalone floating scroll icon). The bar covers per-type reading and the minimap button (or `/sr`) covers read-everything; the extra button was redundant. Its stale saved-variables entry is cleaned on load, and `/sr` button is gone from the slash commands.

v1.2.1 — 2026-09-14

Server landed bulk support for both custom scrolls (Wildcard Transmog Scroll = 500201, Sealed Traveler's Map = 500200, per Dashboard [#1350]/[#1360]); this patch adapts to the maps' server rules.

- **Auto-chain for the 500-per-call map cap:** one confirmation covers the full stack, and ScrollReader re-sends SCRALL until your **bags** are empty of that type (bag scan as the loop condition, deliberately — SCRDONE's held counts bank copies SCRALL can't touch, and chaining on it would loop forever). A used=0 reply ends a chain; a 40-send budget caps it outright. One summary line replaces per-call chatter ("read 1398 ... over 3 calls").
- **Map-aware confirmation:** confirming >500 maps notes the 500-per-call rule and the auto-repeat.
- **Combat holds the send queue** (new sends and chained re-sends) and resumes after; previously only button presses were gated.
- Manual updated: whitelist now fully live; map rules (flight-path requirement, no-award consumption, socket-scroll chance) documented.

v1.2.0 — 2026-09-14

Six-type keybindable bulk bar.

- **New: the bar** — a draggable horizontal bar of six buttons (Wildcard Transmog Scroll, Sealed Traveler's Map, Scroll of Mastery, Scroll of the Delver, Scroll of Reach, Scroll of Bounty), each with the item's live icon, a held-count badge, and a tooltip showing its current keybind. Press = bulk-read that type via SCRALL. Empty types grey out. Dragging any part moves the bar; position persisted (/sr bar toggles it).
- **New: keybindings** — Bindings.xml exposes one binding per type under ESC → Key Bindings → ScrollReader ("Read all: "). Keybinds behave exactly like clicks, confirmation dialog included (dialog-every-press was the chosen policy).
- **Master buttons widened:** the minimap and on-screen buttons (and /sr) now sweep **all six types** in one confirmation; their badges show the grand total held.
- Icons resolve live via GetItemIcon from bag-link entries; the four kirei scrolls carry their known entries (500203/500204/500205/500207) as icon fallbacks. Sends still use only live bag-link entries.
- /sr count now lists all six types.
- /sr reset resets all three movables (minimap, on-screen button, bar).
- Live-test note folded into the manual: rejection is not silence on this realm — non-whitelisted entries get SCRDONE used=0 plus a server explanation line, so the 6s watchdog is a never-fires edge case here.

v1.1.0 — 2026-09-07

Rework: server-verb bulk consume. v1.0.0's UseContainerItem sweep was taint-blocked in-game ("blocked from an action only available to the Blizzard UI") — these scrolls cast a spell on use, and protected calls can't be looped from addon code. v1.1.0 adopts the server's own mass-consume mechanism, as used by the Dashboard's "Use in bulk" buttons.

- **True one-press burst:** sends SCRALL: (transport REAGENTBANK) per scroll type; the server consumes every bag copy in one call. Requests are spaced 1.2s apart.
- **Confirmation dialog** before anything is sent, quoting exact counts and names — the scrolls are destroyed with no undo (suite consent rule).
- **SCRDONE::: reply handling** — three fields, matching what the server actually sends (the historical two-field pattern in UncappedScrolls was a known dead branch; not repeated here). Chat summary of spent/remaining; suppressed when the Uncapped Dashboard is loaded, since its [Scrolls] handler already prints one.
- **6s reply watchdog:** silence means the server's SCRALL whitelist likely doesn't cover the entry — the addon says so and prints the entry ID for a one-line admin ask.

- **Live count badges** on both buttons (total matching scrolls held; hidden at zero; refreshed on BAG_UPDATE).
- **Item entries resolved from bag links** by exact title at click time — no hardcoded IDs.
- New /sr count — per-type counts plus entry IDs.
- Removed: the v1.0.0 client-side UseContainerItem sweep and its per-click leftover semantics (obsolete — the server call is exhaustive).

v1.0.0 — 2026-09-07

Initial release.

- Burst reader for exact titles **Wildcard Transmog Scroll** and **Sealed Traveler's Map**: one click sweeps bags 0–4 and uses every matching, unlocked item. *(Superseded in v1.1.0 — this approach is taint-blocked for spell-casting items.)*
- Chat report per sweep with total and per-title counts; "no matching scrolls" when bags are clean.
- **Minimap button** with free-form drag (exact x/y from minimap center, no ring snapping; canonical LibDBIcon texture layout) — safe with scaled minimaps.
- **On-screen button** (36×36, draggable, clamped to screen, position persisted).
- Slash commands: /sr (/scrollread), /sr button, /sr minimap, /sr reset.
- Combat gating: both buttons desaturate and ignore clicks in combat; state also detected correctly when logging in mid-combat.
- SavedVariables: ScrollReaderDB (button positions + visibility only).
- 3.3.5a-safe: no C_Timer, no SetShown, all UI built after ADDON_LOADED.