# Teach BridgePoint to Speak the Local Lingo

1. Set up BridgePoint

2. Make Sure the OS supports the Language you want to run BridgePoint in,
   (i.e. for Windows XP OS to support Arabic)

**3.** Install the Language Packs corresponding to your Eclipse Version

   **3.1.** Open BridgePoint  Help->Software Updates-> Find and Install



   **3.2.**       Select Search for new Features to install then Next

**3.3.** Click the "New Remote Site" button and add the name "Language Packs" and in the URL field
for eclipse 3.3 http://download.eclipse.org/technology/babel/update-site/europa/
for eclipse 3.4 http://download.eclipse.org/technology/babel/update-site/ganymede/

Then Click OK Then Finish

**3.4.** Select the required language to be installed (in this case Arabic is chosen) then click Next



**3.5.** Select I accept the terms in the license agreement then Next

### 3.6.　　　Click Finish



### 3.7　Then Click install all Then restart BridgePoint

**4.** Then the language packs required are installed to Run BridgePoint in your local Language if the required language is the same as the OS default language then it will work properly if the required language is not the same as the OS default language then we need to adjust the eclipse.exe command according to the new language required

    **4.1** Open the file "BridgePoint_Launcher.bat"in the directory
       C:\MentorGraphics\BridgePoint\eclipse or where ever you installed BridgePoint

    **4.2** adjust the last line that has the eclipse.exe command and add to it
       - nl (language locale)
       i.e. For french it becomes  eclipse.exe -nl fr

      for bidirectional languages like Arabic and Hebrew add another directive -dir rtl
      to adjust the direction right to left

      i.e. For Arabic it becomes eclipse.exe -nl ar -dir rtl

```
@echo off


if not "%MGLS_LICENSE_FILE%"=="" goto LicenseConfigured
  ::
  :: Since the license path is not already set, use the standard location.  BridgePoint users may
  :: choose to set the value in the environment, or modify the following line to point to the correct
  :: location (either local or remote).
  ::
  :: example configuration for a remote license server
  ::    set MGLS_LICENSE_FILE=1717@svr-taz-eng-05
  ::
  set MGLS_LICENSE_FILE=C:\MentorGraphics\BridgePoint\license\license.dat
:LicenseConfigured
echo Using MGLS_LICENSE_FILE=%MGLS_LICENSE_FILE%


::
:: DO NOT MODIFY ANY OF THE FOLLOWING LINES.
::
set PATH=%PATH%;C:\MentorGraphics\BridgePoint\tools\docgen\docbook
set MGC_EMBEDDED_HOME=C:\MentorGraphics\BridgePoint
set MGLS_DLL=
set MGLS_PKGINFO_FILE=
set MGLS_HOME=
set MGC_HOME=

start eclipse.exe %1 %2 %3 %4 %5 %6 %7 %8 %9 -nl ar -dir rtl
```

**5.** Here we are, now BridePint is running in your local lingo :)

**This is Arabic:**



**This is Japanese:**