LVLHFrameModel

5.0

Generated by Doxygen 1.8.14

Contents

1	Mod	ule Index	1
	1.1	Modules	1
2	Nam	espace Index	3
	2.1	Namespace List	3
3	Data	Structure Index	5
	3.1	Data Structures	5
4	File	Index	7
	4.1	File List	7
5	Mod	ule Documentation	9
	5.1	Models	9
		5.1.1 Detailed Description	9
	5.2	Utils	0
		5.2.1 Detailed Description	0
	5.3	LvlhFrame	1
		5.3.1 Detailed Description	11
		5.3.2 Macro Definition Documentation	1
		5.3.2.1 PATH	1
6	Nam	espace Documentation	13
	6.1	jeod Namespace Reference	13
		6.1.1 Detailed Description	13

ii CONTENTS

7	Data	Struct	ure Docur	mentation	15
	7.1	jeod::L	vlhFrame	Class Reference	15
		7.1.1	Detailed	Description	16
		7.1.2	Construc	ctor & Destructor Documentation	16
			7.1.2.1	LvlhFrame() [1/2]	16
			7.1.2.2	~LvIhFrame()	17
			7.1.2.3	LvlhFrame() [2/2]	17
		7.1.3	Member	Function Documentation	17
			7.1.3.1	compute_lvlh_frame()	17
			7.1.3.2	initialize()	17
			7.1.3.3	operator=()	18
			7.1.3.4	set_planet()	18
			7.1.3.5	set_planet_name()	18
			7.1.3.6	set_subject_frame()	19
			7.1.3.7	set_subject_name()	19
			7.1.3.8	update()	19
		7.1.4	Friends A	And Related Function Documentation	19
			7.1.4.1	init_attrjeodLvlhFrame	20
			7.1.4.2	InputProcessor	20
		7.1.5	Field Do	cumentation	20
			7.1.5.1	frame	20
			7.1.5.2	local_dm	20
			7.1.5.3	planet_centered_inertial	21
			7.1.5.4	planet_name	21
			7.1.5.5	subject_frame	21
			7.1.5.6	subject_name	21
	7.2	jeod::L	.vlhFramel	Messages Class Reference	22
		7.2.1	Detailed	Description	22
		7.2.2	Construc	ctor & Destructor Documentation	22
			7.2.2.1	LvlhFrameMessages() [1/2]	23

CONTENTS

			7.2.2.2 LvlhFrameMessages() [2/2]	23
		7.2.3	Member Function Documentation	23
			7.2.3.1 operator=()	23
		7.2.4	Friends And Related Function Documentation	23
			7.2.4.1 init_attrjeodLvlhFrameMessages	23
			7.2.4.2 InputProcessor	23
		7.2.5	Field Documentation	23
			7.2.5.1 divide_by_zero	24
			7.2.5.2 fatal_error	24
			7.2.5.3 illegal_value	24
			7.2.5.4 invalid_configuration	25
			7.2.5.5 invalid_name	25
			7.2.5.6 invalid_object	25
			7.2.5.7 null_pointer	26
			7.2.5.8 trace	26
	7.3	jeod::L	vlhType Class Reference	26
		7.3.1	Detailed Description	27
		7.3.2	Member Enumeration Documentation	27
			7.3.2.1 Type	27
		7.3.3	Constructor & Destructor Documentation	27
			7.3.3.1 LvlhType()	28
		7.3.4	Friends And Related Function Documentation	28
			7.3.4.1 init_attrjeodLvlhType	28
			7.3.4.2 InputProcessor	28
		7.3.5	Field Documentation	28
			7.3.5.1 value	28
	Tile I	D		00
8			entation	29
	8.1	_	me.cc File Reference	29
	0.0	8.1.1	Detailed Description	29
	8.2		me.hh File Reference	29
	0.0	8.2.1	Detailed Description	30
	8.3		Ime_messages.cc File Reference	30
		8.3.1	Detailed Description	30
	8.4		Ime_messages.hh File Reference	30
	<u> </u>	8.4.1	Detailed Description	31
	8.5		pe.hh File Reference	31
		8.5.1	Detailed Description	31
Inc	lex			33

Module Index

1.1 Modules

Here is a list of all modules:

Models	 																9
Utils	 							 									 10
LylhFrame																	11

2 Module Index

Namespace Index

	2.1	Namespace	List
--	-----	-----------	------

Here is a list of all Harriespaces w	itii bilei descriptions.	

jeod																						
	Namespace jeod															 						13

4 Namespace Index

Data Structure Index

3.1 Data Structures

Here are the data structures with brief descriptions:

jeod::LvlhFrame	
The class used to represent an LVLH reference frame associated with a subject DynBody	15
jeod::LvlhFrameMessages	
The class that specifies the message IDs used in the LvlhFrame model	22
jeod::LvlhType	
The class used to identify the type of LVLH desired	26

6 Data Structure Index

File Index

4.1 File List

Here is a list of all files with brief descriptions:

lvlh_frame.cc	
Define methods for the LVLH reference frame class	29
lvlh_frame.hh	
Define the class LvlhFrame, the class used to represent a local-vertical, local-horizontal refer-	
ence frame associated with a subject DynBody	29
lvlh_frame_messages.cc	
Implement the class LvlhFrameMessages	30
lvlh_frame_messages.hh	
Define the class LvIhFrameMessages, the class that specifies the message IDs used in the	
LvlhFrame model	30
lvlh_type.hh	
Define the class LylhType, which identifies the type of LVLH desired to be calculated	31

8 File Index

Module Documentation

5.1 Models

Modules

• Utils

5.1.1 Detailed Description

10 Module Documentation

5.2 Utils

Modules

• LvlhFrame

5.2.1 Detailed Description

5.3 LvlhFrame 11

5.3 LvlhFrame

Files

· file lvlh_frame.hh

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

· file lvlh_frame_messages.hh

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model.

· file lvlh_type.hh

Define the class LvIhType, which identifies the type of LVLH desired to be calculated.

• file lvlh_frame.cc

Define methods for the LVLH reference frame class.

• file lvlh_frame_messages.cc

Implement the class LvlhFrameMessages.

Namespaces

• jeod

Namespace jeod.

Macros

• #define PATH "utils/lvlh_frame/"

5.3.1 Detailed Description

5.3.2 Macro Definition Documentation

5.3.2.1 PATH

```
#define PATH "utils/lvlh_frame/"
```

Definition at line 31 of file lvlh_frame_messages.cc.

12 Module Documentation

Namespace Documentation

6.1 jeod Namespace Reference

Namespace jeod.

Data Structures

· class LvlhFrame

The class used to represent an LVLH reference frame associated with a subject DynBody.

class LvlhFrameMessages

The class that specifies the message IDs used in the LvlhFrame model.

class LvlhType

The class used to identify the type of LVLH desired.

6.1.1 Detailed Description

Namespace jeod.

Data Structure Documentation

7.1 jeod::LvlhFrame Class Reference

The class used to represent an LVLH reference frame associated with a subject DynBody.

```
#include <lvlh_frame.hh>
```

Public Member Functions

• LvlhFrame ()

Construct an LvlhFrame object.

• ∼LvlhFrame ()

Destruct an LvlhFrame object.

void initialize (DynManager &dyn_manager)

Begin initialization of an LvlhFrame.

• void update ()

Update the state.

void set subject name (const std::string new name)

Set the subject_name to the supplied value.

void set_planet_name (const std::string new_name)

Set the planet_name to the supplied value.

void set_subject_frame (RefFrame &new_frame)

Set the subject_frame to the supplied value.

void set_planet (BasePlanet &new_planet)

Set the planet whose PCI frame will be the reference for LVLH.

Data Fields

· RefFrame frame

The LVLH frame defined by the subject frame's motion with respect to the reference planet.

• std::string subject_name

The frame whose motion defines LVLH.

• std::string planet_name

The planet used as reference for the LVLH frame.

Protected Member Functions

void compute_lvlh_frame (const RefFrameTrans &rel_trans)
 Update the state of the LVLH frame wrt its parent.

Protected Attributes

RefFrame * subject_frame
 The (moving) frame specified with subject_name.

• RefFrame * planet_centered_inertial

The inertial frame with origin at the center of the specified planet.

Private Member Functions

- LvlhFrame (const LvlhFrame &)
- LvlhFrame & operator= (const LvlhFrame &)

Private Attributes

DynManager * local_dm
 A local pointer to the dynamics manager needed for clean-up.

Friends

- · class InputProcessor
- void init_attrjeod__LvlhFrame ()

7.1.1 Detailed Description

The class used to represent an LVLH reference frame associated with a subject DynBody.

Definition at line 84 of file lvlh_frame.hh.

7.1.2 Constructor & Destructor Documentation

Construct an LvlhFrame object.

Definition at line 51 of file lvlh_frame.cc.

7.1.2.2 \sim LvlhFrame()

```
\label{eq:condition} \mbox{jeod::LvlhFrame::$\sim$LvlhFrame} \mbox{ (} \\ \mbox{void )}
```

Destruct an LvIhFrame object.

Definition at line 69 of file lvlh_frame.cc.

References frame, local_dm, planet_centered_inertial, and subject_frame.

7.1.2.3 LvlhFrame() [2/2]

7.1.3 Member Function Documentation

7.1.3.1 compute_lvlh_frame()

Update the state of the LVLH frame wrt its parent.

Parameters

in	rel_trans	Planet relative state

Definition at line 267 of file lvlh_frame.cc.

References frame.

Referenced by update().

7.1.3.2 initialize()

Begin initialization of an LvlhFrame.

Parameters

in,out	dyn_manager	Dynamics manager
--------	-------------	------------------

Definition at line 96 of file lvlh_frame.cc.

References frame, jeod::LvlhFrameMessages::invalid_configuration, jeod::LvlhFrameMessages::invalid_name, local_dm, planet_centered_inertial, planet_name, subject_frame, and subject_name.

7.1.3.3 operator=()

7.1.3.4 set_planet()

Set the planet whose PCI frame will be the reference for LVLH.

Parameters

```
in new_planet new planet.
```

Definition at line 255 of file lvlh_frame.cc.

References planet_centered_inertial.

7.1.3.5 set_planet_name()

Set the planet_name to the supplied value.

Parameters

in	new_name	new name.
----	----------	-----------

Definition at line 243 of file lvlh_frame.cc.

References planet_name.

7.1.3.6 set_subject_frame()

Set the subject_frame to the supplied value.

Parameters

in new_fra	me new frame.
------------	---------------

Definition at line 231 of file lvlh_frame.cc.

References subject_frame.

7.1.3.7 set_subject_name()

Set the subject_name to the supplied value.

Parameters

```
in new_name new name.
```

Definition at line 220 of file lvlh_frame.cc.

References subject_name.

7.1.3.8 update()

Update the state.

Definition at line 190 of file lvlh_frame.cc.

References compute_lvlh_frame(), frame, planet_centered_inertial, and subject_frame.

7.1.4 Friends And Related Function Documentation

7.1.4.1 init_attrjeod__LvlhFrame

```
void init_attrjeod__LvlhFrame ( ) [friend]
```

7.1.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 86 of file lvlh_frame.hh.

7.1.5 Field Documentation

7.1.5.1 frame

```
RefFrame jeod::LvlhFrame::frame
```

The LVLH frame defined by the subject frame's motion with respect to the reference planet.

trick_units(-)

Definition at line 95 of file lvlh_frame.hh.

Referenced by compute_lvlh_frame(), initialize(), update(), and $\sim\!$ LvlhFrame().

7.1.5.2 local_dm

```
DynManager* jeod::LvlhFrame::local_dm [private]
```

A local pointer to the dynamics manager needed for clean-up.

trick_units(-)

Definition at line 124 of file lvlh_frame.hh.

Referenced by initialize(), and ~LvlhFrame().

7.1.5.3 planet_centered_inertial

```
RefFrame* jeod::LvlhFrame::planet_centered_inertial [protected]
```

The inertial frame with origin at the center of the specified planet.

trick units(-)

Definition at line 117 of file lvlh frame.hh.

Referenced by initialize(), set_planet(), update(), and ~LvlhFrame().

7.1.5.4 planet_name

```
std::string jeod::LvlhFrame::planet_name
```

The planet used as reference for the LVLH frame.

trick_units(-)

Definition at line 105 of file lvlh_frame.hh.

Referenced by initialize(), and set_planet_name().

7.1.5.5 subject_frame

```
RefFrame* jeod::LvlhFrame::subject_frame [protected]
```

The (moving) frame specified with subject_name.

trick_units(-)

Definition at line 112 of file lvlh_frame.hh.

Referenced by initialize(), set_subject_frame(), update(), and \sim LvIhFrame().

7.1.5.6 subject_name

```
std::string jeod::LvlhFrame::subject_name
```

The frame whose motion defines LVLH.

Can be on a vehicle or not.trick_units(-)

Definition at line 100 of file lvlh frame.hh.

Referenced by initialize(), and set_subject_name().

The documentation for this class was generated from the following files:

- · Ivlh frame.hh
- lvlh_frame.cc

7.2 jeod::LvlhFrameMessages Class Reference

The class that specifies the message IDs used in the LvlhFrame model.

```
#include <lvlh_frame_messages.hh>
```

Static Public Attributes

static char const * fatal_error

Issued when performing an action results in an error return from the method performing the action.

• static char const * illegal_value

Issued when a simple type (e.g.

static char const * invalid_name

Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).

• static char const * invalid_configuration

Issued when insufficient information has been specified prior to initialization.

static char const * invalid_object

Issued when a pointer points to an object of the wrong type.

• static char const * null_pointer

Error issued when a pointer is required but was not provided.

static char const * trace

Debug message issued to trace LvlhFrame actions.

static char const * divide_by_zero

Fatal message when a divide by zero is encountered.

Private Member Functions

- LvlhFrameMessages (void)
- LvIhFrameMessages (const LvIhFrameMessages &)
- LvlhFrameMessages & operator= (const LvlhFrameMessages &)

Friends

- · class InputProcessor
- void init_attrjeod__LvlhFrameMessages ()

7.2.1 Detailed Description

The class that specifies the message IDs used in the LvlhFrame model.

Definition at line 82 of file lvlh_frame_messages.hh.

7.2.2 Constructor & Destructor Documentation

7.2.2.1 LvlhFrameMessages() [1/2]

7.2.2.2 LvlhFrameMessages() [2/2]

7.2.3 Member Function Documentation

7.2.3.1 operator=()

7.2.4 Friends And Related Function Documentation

7.2.4.1 init_attrjeod__LvlhFrameMessages

```
void init_attrjeod__LvlhFrameMessages ( ) [friend]
```

7.2.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 85 of file lvlh_frame_messages.hh.

7.2.5 Field Documentation

7.2.5.1 divide_by_zero

```
char const * jeod::LvlhFrameMessages::divide_by_zero [static]
```

Initial value:

```
"utils/lvlh_frame/" "divide_by_zero"
```

Fatal message when a divide by zero is encountered.

```
trick_units(-)
```

Definition at line 131 of file lvlh_frame_messages.hh.

7.2.5.2 fatal_error

```
char const * jeod::LvlhFrameMessages::fatal_error [static]
```

Initial value:

```
"utils/lvlh_frame/" "fatal_error"
```

Issued when performing an action results in an error return from the method performing the action.

```
trick_units(-)
```

Definition at line 94 of file lvlh_frame_messages.hh.

7.2.5.3 illegal_value

```
char const * jeod::LvlhFrameMessages::illegal_value [static]
```

Initial value:

```
=
"utils/lvlh_frame/" "illegal_value"
```

Issued when a simple type (e.g.

an enum) has an illegal value.trick_units(-)

Definition at line 99 of file lvlh_frame_messages.hh.

7.2.5.4 invalid_configuration

```
char const * jeod::LvlhFrameMessages::invalid_configuration [static]
```

Initial value:

```
"utils/lvlh_frame/" "invalid_configuration"
```

Issued when insufficient information has been specified prior to initialization.

```
trick_units(-)
```

Definition at line 111 of file lvlh_frame_messages.hh.

Referenced by jeod::LvlhFrame::initialize().

7.2.5.5 invalid_name

```
char const * jeod::LvlhFrameMessages::invalid_name [static]
```

Initial value:

```
"utils/lvlh_frame/" "invalid_name"
```

Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).

```
trick_units(-)
```

Definition at line 105 of file lvlh_frame_messages.hh.

Referenced by jeod::LvlhFrame::initialize().

7.2.5.6 invalid_object

```
char const * jeod::LvlhFrameMessages::invalid_object [static]
```

Initial value:

```
=
"utils/lvlh_frame/" "invalid_object"
```

Issued when a pointer points to an object of the wrong type.

```
trick_units(-)
```

Definition at line 116 of file lvlh_frame_messages.hh.

7.2.5.7 null_pointer

```
char const * jeod::LvlhFrameMessages::null_pointer [static]
```

Initial value:

```
"utils/lvlh_frame/" "null_pointer"
```

Error issued when a pointer is required but was not provided.

```
trick_units(-)
```

Definition at line 121 of file lvlh_frame_messages.hh.

7.2.5.8 trace

```
char const * jeod::LvlhFrameMessages::trace [static]
```

Initial value:

```
"utils/lvlh_frame/" "trace"
```

Debug message issued to trace LvlhFrame actions.

```
trick_units(-)
```

Definition at line 126 of file lvlh_frame_messages.hh.

The documentation for this class was generated from the following files:

- lvlh_frame_messages.hh
- lvlh_frame_messages.cc

7.3 jeod::LvIhType Class Reference

The class used to identify the type of LVLH desired.

```
#include <lvlh_type.hh>
```

Public Types

• enum Type { Rectilinear = 0, CircularCurvilinear = 1, EllipticalCurvilinear = 2 }

An enumeration to specify the type of LVLH coordinates to use, whether rectilinear, circular curvilinear, or elliptical curvilinear.

Public Member Functions

• LvlhType (void)

Default constructor.

Data Fields

· Type value

Indicates type of LVLH coordinates desired.

Friends

- · class InputProcessor
- void init_attrjeod__LvlhType ()

7.3.1 Detailed Description

The class used to identify the type of LVLH desired.

Definition at line 79 of file lvlh_type.hh.

7.3.2 Member Enumeration Documentation

7.3.2.1 Type

enum jeod::LvlhType::Type

An enumeration to specify the type of LVLH coordinates to use, whether rectilinear, circular curvilinear, or elliptical curvilinear.

As of March 2015, elliptical is not implemented.

Enumerator

Rectilinear	
CircularCurvilinear	
EllipticalCurvilinear	

Definition at line 92 of file lvlh_type.hh.

7.3.3 Constructor & Destructor Documentation

7.3.3.1 LvlhType()

Default constructor.

Definition at line 120 of file lvlh_type.hh.

References Rectilinear, and value.

7.3.4 Friends And Related Function Documentation

7.3.4.1 init_attrjeod__LvlhType

```
void init_attrjeod__LvlhType ( ) [friend]
```

7.3.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 81 of file lvlh_type.hh.

7.3.5 Field Documentation

7.3.5.1 value

```
Type jeod::LvlhType::value
```

Indicates type of LVLH coordinates desired.

Default is rectilinear.trick_units(-)

Definition at line 111 of file lvlh_type.hh.

Referenced by LvlhType().

The documentation for this class was generated from the following file:

• lvlh_type.hh

File Documentation

8.1 lvlh_frame.cc File Reference

Define methods for the LVLH reference frame class.

```
#include <cstddef>
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "environment/planet/include/base_planet.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/named_item/include/named_item.hh"
#include "../include/lvlh_frame.hh"
#include "../include/lvlh_frame_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

8.1.1 Detailed Description

Define methods for the LVLH reference frame class.

8.2 lvlh_frame.hh File Reference

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

```
#include <string>
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/planet/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame.hh"
#include "utils/sim_interface/include/jeod_class.hh"
```

30 File Documentation

Data Structures

· class jeod::LvlhFrame

The class used to represent an LVLH reference frame associated with a subject DynBody.

Namespaces

· jeod

Namespace jeod.

8.2.1 Detailed Description

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

8.3 lvlh_frame_messages.cc File Reference

Implement the class LvlhFrameMessages.

```
#include "../include/lvlh_frame_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

Macros

• #define PATH "utils/lvlh_frame/"

8.3.1 Detailed Description

Implement the class LvlhFrameMessages.

8.4 lvlh_frame_messages.hh File Reference

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::LvlhFrameMessages

The class that specifies the message IDs used in the LvlhFrame model.

Namespaces

• jeod

Namespace jeod.

8.4.1 Detailed Description

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model.

8.5 lvlh_type.hh File Reference

Define the class LvlhType, which identifies the type of LVLH desired to be calculated.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

· class jeod::LvIhType

The class used to identify the type of LVLH desired.

Namespaces

• jeod

Namespace jeod.

8.5.1 Detailed Description

Define the class LvIhType, which identifies the type of LVLH desired to be calculated.

32 File Documentation

Index

\sim LvlhFrame	set_subject_name, 19
jeod::LvlhFrame, 16	subject_frame, 21
•	subject_name, 21
compute_lvlh_frame	update, 19
jeod::LvIhFrame, 17	jeod::LvlhFrameMessages, 22
	divide_by_zero, 23
divide_by_zero	fatal_error, 24
jeod::LvlhFrameMessages, 23	illegal_value, 24
fatal error	init_attrjeodLvlhFrameMessages, 2
jeod::LvlhFrameMessages, 24	InputProcessor, 23
frame	invalid_configuration, 24
jeod::LvlhFrame, 20	invalid_name, 25
JeouEviliFrame, 20	invalid_object, 25
illegal_value	LvlhFrameMessages, 22, 23
jeod::LvlhFrameMessages, 24	null_pointer, 25
init_attrjeodLvlhFrame	operator=, 23
jeod::LvlhFrame, 19	trace, 26
init_attrjeodLvlhFrameMessages	jeod::LvlhType, 26
jeod::LvlhFrameMessages, 23	init_attrjeodLvlhType, 28
init attrjeod LvlhType	InputProcessor, 28
jeod::LvlhType, 28	LvlhType, 27
initialize	Type, 27
jeod::LvlhFrame, 17	value, 28
InputProcessor	
jeod::LvlhFrame, 20	local_dm
jeod::LvlhFrameMessages, 23	jeod::LvIhFrame, 20
jeod::LvlhType, 28	lvlh_frame.cc, 29
invalid_configuration	lvlh_frame.hh, 29
jeod::LvlhFrameMessages, 24	lvlh_frame_messages.cc, 30
invalid_name	lvlh_frame_messages.hh, 30
jeod::LvlhFrameMessages, 25	lvlh_type.hh, 31
invalid_object	LvlhFrame, 11
jeod::LvlhFrameMessages, 25	jeod::LvlhFrame, 16, 17
jeodEviili rameiviessages, 25	PATH, 11
jeod, 13	LvlhFrameMessages
jeod::LvlhFrame, 15	jeod::LvlhFrameMessages, 22, 23
∼LvlhFrame, 16	LvlhType
compute_lvlh_frame, 17	jeod::LvlhType, 27
frame, 20	
init attrjeod LvlhFrame, 19	Models, 9
initialize, 17	
InputProcessor, 20	null_pointer
local_dm, 20	jeod::LvlhFrameMessages, 25
LvlhFrame, 16, 17	onorator
operator=, 18	operator=
planet_centered_inertial, 20	jeod::LvlhFrame, 18
planet_name, 21	jeod::LvIhFrameMessages, 23
set planet, 18	PATH
set_planet_name, 18	LvlhFrame, 11
set_subject_frame, 19	planet centered inertial
ser_subject_frame, 13	pianet_centered_inertial

34 INDEX

```
jeod::LvlhFrame, 20
planet_name
    jeod::LvlhFrame, 21
set_planet
    jeod::LvlhFrame, 18
set_planet_name
    jeod::LvlhFrame, 18
set_subject_frame
    jeod::LvlhFrame, 19
set_subject_name
    jeod::LvlhFrame, 19
subject_frame
    jeod::LvlhFrame, 21
subject_name
    jeod::LvlhFrame, 21
trace
    jeod::LvlhFrameMessages, 26
Type
    jeod::LvlhType, 27
update
    jeod::LvlhFrame, 19
Utils, 10
value
    jeod::LvlhType, 28
```