LVLHFrameModel 5.0

Generated by Doxygen 1.8.5

Wed Jun 1 2022 12:09:56

Contents

| 1 | Mod | lule Index | 1 |
|---|------|--|----|
| | 1.1 | Modules | 1 |
| 2 | Nam | nespace Index | 3 |
| | 2.1 | Namespace List | 3 |
| 3 | Data | a Structure Index | 5 |
| | 3.1 | Data Structures | 5 |
| 4 | File | Index | 7 |
| | 4.1 | File List | 7 |
| 5 | Mod | dule Documentation | 9 |
| | 5.1 | Models | 9 |
| | | 5.1.1 Detailed Description | 9 |
| | 5.2 | Utils | 10 |
| | | 5.2.1 Detailed Description | 10 |
| | 5.3 | LvlhFrame | 11 |
| | | 5.3.1 Detailed Description | 11 |
| | | 5.3.2 Macro Definition Documentation | 11 |
| | | 5.3.2.1 PATH | 11 |
| 6 | Nam | nespace Documentation | 13 |
| | 6.1 | jeod Namespace Reference | 13 |
| | | 6.1.1 Detailed Description | 13 |
| 7 | Data | a Structure Documentation | 15 |
| | 7.1 | jeod::LvlhFrame Class Reference | 15 |
| | | 7.1.1 Detailed Description | 16 |
| | | 7.1.2 Constructor & Destructor Documentation | 16 |
| | | 7.1.2.1 LvlhFrame | 16 |
| | | 7.1.2.2 ~LvlhFrame | 16 |
| | | 7.1.2.3 LvlhFrame | 17 |
| | | 7.1.3 Member Function Documentation | 17 |

iv CONTENTS

| | | 7.1.3.1 | compute_lvlh_frame | 17 |
|-----|---------|-------------|-----------------------------------|----|
| | | 7.1.3.2 | initialize | 18 |
| | | 7.1.3.3 | operator= | 18 |
| | | 7.1.3.4 | set_planet | 18 |
| | | 7.1.3.5 | set_planet_name | 18 |
| | | 7.1.3.6 | set_subject_frame | 18 |
| | | 7.1.3.7 | set_subject_name | 19 |
| | | 7.1.3.8 | update | 20 |
| | 7.1.4 | Friends A | nd Related Function Documentation | 20 |
| | | 7.1.4.1 | init_attrjeodLvlhFrame | 20 |
| | | 7.1.4.2 | InputProcessor | 20 |
| | 7.1.5 | Field Doc | umentation | 20 |
| | | 7.1.5.1 | frame | 20 |
| | | 7.1.5.2 | local_dm | 20 |
| | | 7.1.5.3 | planet_centered_inertial | 20 |
| | | 7.1.5.4 | planet_name | 20 |
| | | 7.1.5.5 | subject_frame | 21 |
| | | 7.1.5.6 | subject_name | 21 |
| 7.2 | jeod::L | vlhFrameM | lessages Class Reference | 21 |
| | 7.2.1 | Detailed [| Description | 22 |
| | 7.2.2 | Construct | tor & Destructor Documentation | 22 |
| | | 7.2.2.1 | LvlhFrameMessages | 22 |
| | | 7.2.2.2 | LvlhFrameMessages | 22 |
| | 7.2.3 | Member F | Function Documentation | 22 |
| | | 7.2.3.1 | operator= | 22 |
| | 7.2.4 | Friends A | nd Related Function Documentation | 22 |
| | | 7.2.4.1 | init_attrjeodLvIhFrameMessages | 22 |
| | | 7.2.4.2 | InputProcessor | 22 |
| | 7.2.5 | Field Doc | umentation | 22 |
| | | 7.2.5.1 | divide_by_zero | 22 |
| | | 7.2.5.2 | fatal_error | 22 |
| | | 7.2.5.3 | illegal_value | 23 |
| | | 7.2.5.4 | invalid_configuration | 23 |
| | | 7.2.5.5 | invalid_name | 23 |
| | | 7.2.5.6 | invalid_object | 23 |
| | | 7.2.5.7 | null_pointer | 24 |
| | | 7.2.5.8 | trace | 24 |
| 7.3 | jeod::L | vlhType Cla | ass Reference | 24 |
| | 7.3.1 | Detailed [| Description | 25 |
| | 7.3.2 | Member E | Enumeration Documentation | 25 |

CONTENTS

| | | | 7.3.2.1 Type | 25 |
|----|------|----------|--|----|
| | | 7.3.3 | Constructor & Destructor Documentation | 25 |
| | | | 7.3.3.1 LvlhType | 25 |
| | | 7.3.4 | Friends And Related Function Documentation | 25 |
| | | | 7.3.4.1 init_attrjeodLvlhType | 25 |
| | | | 7.3.4.2 InputProcessor | 25 |
| | | 7.3.5 | Field Documentation | 25 |
| | | | 7.3.5.1 value | 25 |
| | | _ | | |
| 8 | File | Docume | entation | 27 |
| | 8.1 | lvlh_fra | ame.cc File Reference | 27 |
| | | 8.1.1 | Detailed Description | 27 |
| | 8.2 | lvlh_fra | ame.hh File Reference | 27 |
| | | 8.2.1 | Detailed Description | 28 |
| | 8.3 | lvlh_fra | ame_messages.cc File Reference | 28 |
| | | 8.3.1 | Detailed Description | 28 |
| | 8.4 | lvlh_fra | ame_messages.hh File Reference | 28 |
| | | 8.4.1 | Detailed Description | 29 |
| | 8.5 | lvlh_ty | pe.hh File Reference | 29 |
| | | 8.5.1 | Detailed Description | 29 |
| | | | | |
| In | dex | | | 30 |
| | | | | |

Module Index

1.1 Modules

| Horo | ie | 2 | liet | ٥f | الد | modu | ٠عما |
|------|----|---|------|----|-----|------|------|
| пеге | 15 | а | IISt | ΟI | all | modu | ies. |

| Models | | | | | | | | | | | | | | | | | | | | | , |
|-----------|------|--|--|------|--|--|------|--|--|------|--|--|--|------|--|--|------|--|--|--|----|
| Utils | | | | | | | | | | | | | | | | | | | | | 1(|
| LvlhFrame | | | | | | | | | | | | | | | | | | | | | 1 |

2 **Module Index**

Namespace Index

| 2.1 | Namespace List | |
|------|--|--|
| Here | e is a list of all namespaces with brief descriptions: | |

| eod | | | | | |
|-----|----------------|------|------|------|----|
| | Namespace jeod | | | | 13 |

Namespace Index

Data Structure Index

3.1 Data Structures

Here are the data structures with brief descriptions:

| jeod::LvlhFrame | |
|---|----|
| The class used to represent an LVLH reference frame associated with a subject DynBody | 15 |
| jeod::LvlhFrameMessages | |
| The class that specifies the message IDs used in the LvlhFrame model | 21 |
| jeod::LvlhType | |
| The class used to identify the type of LVLH desired | 24 |

6 Data Structure Index

File Index

4.1 File List

Here is a list of all files with brief descriptions:

| lvlh_frame.cc | |
|---|----|
| Define methods for the LVLH reference frame class | 27 |
| lvlh_frame.hh | |
| Define the class LvlhFrame, the class used to represent a local-vertical, local-horizontal refer- | |
| ence frame associated with a subject DynBody | 27 |
| lvlh_frame_messages.cc | |
| Implement the class LvIhFrameMessages | 28 |
| lvlh_frame_messages.hh | |
| Define the class LvIhFrameMessages, the class that specifies the message IDs used in the LvIh- | |
| Frame model | 28 |
| lvlh_type.hh | |
| Define the class LvlhType, which identifies the type of LVLH desired to be calculated | 29 |

8 File Index

Module Documentation

5.1 Models

Modules

• Utils

5.1.1 Detailed Description

10 Module Documentation

5.2 Utils

Modules

• LvlhFrame

5.2.1 Detailed Description

5.3 LvlhFrame 11

5.3 LvlhFrame

Files

· file lvlh_frame.hh

Define the class LvlhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

• file lvlh_frame_messages.hh

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model.

• file lvlh_type.hh

Define the class LvIhType, which identifies the type of LVLH desired to be calculated.

• file lvlh_frame.cc

Define methods for the LVLH reference frame class.

• file lvlh_frame_messages.cc

Implement the class LvlhFrameMessages.

Namespaces

• jeod

Namespace jeod.

Macros

• #define PATH "utils/lvlh_frame/"

5.3.1 Detailed Description

5.3.2 Macro Definition Documentation

5.3.2.1 #define PATH "utils/lvlh_frame/"

Definition at line 32 of file lvlh frame messages.cc.

12 **Module Documentation**

Namespace Documentation

6.1 jeod Namespace Reference

Namespace jeod.

Data Structures

class LvlhFrame

The class used to represent an LVLH reference frame associated with a subject DynBody.

• class LvlhFrameMessages

The class that specifies the message IDs used in the LvlhFrame model.

class LvlhType

The class used to identify the type of LVLH desired.

6.1.1 Detailed Description

Namespace jeod.

| Names | pace | Docur | mentatior |
|-------|------|-------|-----------|
| | | | |

Data Structure Documentation

7.1 jeod::LvIhFrame Class Reference

The class used to represent an LVLH reference frame associated with a subject DynBody.

```
#include <lvlh_frame.hh>
```

Public Member Functions

• LvlhFrame ()

Construct an LvlhFrame object.

∼LvlhFrame ()

Destruct an LvlhFrame object.

void initialize (DynManager &dyn_manager)

Begin initialization of an LvlhFrame.

• void update ()

Update the state.

void set_subject_name (const std::string new_name)

Set the subject_name to the supplied value.

void set_planet_name (const std::string new_name)

Set the planet_name to the supplied value.

• void set_subject_frame (RefFrame &new_frame)

Set the subject_frame to the supplied value.

• void set_planet (BasePlanet &new_planet)

Set the planet whose PCI frame will be the reference for LVLH.

Data Fields

RefFrame frame

The LVLH frame defined by the subject frame's motion with respect to the reference planet.

• std::string subject_name

The frame whose motion defines LVLH.

• std::string planet_name

The planet used as reference for the LVLH frame.

Protected Member Functions

void compute_lvlh_frame (const RefFrameTrans &rel_trans)
 Update the state of the LVLH frame wrt its parent.

Protected Attributes

• RefFrame * subject_frame

The (moving) frame specified with subject_name.

• RefFrame * planet_centered_inertial

The inertial frame with origin at the center of the specified planet.

Private Member Functions

- LvlhFrame (const LvlhFrame &)
- LvlhFrame & operator= (const LvlhFrame &)

Private Attributes

• DynManager * local_dm

A local pointer to the dynamics manager needed for clean-up.

Friends

- class InputProcessor
- void init_attrjeod__LvlhFrame ()

7.1.1 Detailed Description

The class used to represent an LVLH reference frame associated with a subject DynBody.

Definition at line 49 of file lvlh_frame.hh.

7.1.2 Constructor & Destructor Documentation

7.1.2.1 jeod::LvlhFrame::LvlhFrame (void)

Construct an LvlhFrame object.

Definition at line 52 of file lvlh_frame.cc.

7.1.2.2 jeod::LvlhFrame::~LvlhFrame (void)

Destruct an LvlhFrame object.

Definition at line 70 of file lvlh_frame.cc.

References frame, local_dm, planet_centered_inertial, and subject_frame.

- **7.1.2.3** jeod::LvlhFrame::LvlhFrame(const LvlhFrame &) [private]
- 7.1.3 Member Function Documentation
- 7.1.3.1 void jeod::LvlhFrame::compute_lvlh_frame (const RefFrameTrans & rel_trans) [protected]

Update the state of the LVLH frame wrt its parent.

Parameters

| in | rel_trans | Planet relative state |
|----|-----------|-----------------------|
|----|-----------|-----------------------|

Definition at line 268 of file lvlh_frame.cc.

References frame.

Referenced by update().

7.1.3.2 void jeod::LvlhFrame::initialize (DynManager & dyn_manager)

Begin initialization of an LvlhFrame.

Parameters

| in,out | dyn_manager | Dynamics manager | |
|--------|-------------|------------------|--|

Definition at line 97 of file lvlh_frame.cc.

References frame, jeod::LvlhFrameMessages::invalid_configuration, jeod::LvlhFrameMessages::invalid_name, local_dm, planet_centered_inertial, planet_name, subject_frame, and subject_name.

7.1.3.3 LvlhFrame& jeod::LvlhFrame::operator=(const LvlhFrame &) [private]

7.1.3.4 void jeod::LvlhFrame::set_planet (BasePlanet & new_planet)

Set the planet whose PCI frame will be the reference for LVLH.

Parameters

| ſ | in | new_planet | new planet. |
|---|----|------------|-------------|

Definition at line 256 of file lvlh_frame.cc.

References planet_centered_inertial.

7.1.3.5 void jeod::LvlhFrame::set_planet_name (const std::string new_name)

Set the planet_name to the supplied value.

Parameters

| in new_name new name. | |
|-----------------------|--|
|-----------------------|--|

Definition at line 244 of file lvlh_frame.cc.

References planet_name.

7.1.3.6 void jeod::LvlhFrame::set_subject_frame (RefFrame & new_frame)

Set the subject_frame to the supplied value.

Parameters

| in | new_frame | new frame. |
|----|-----------|------------|

Definition at line 232 of file lvlh_frame.cc.

References subject_frame.

7.1.3.7 void jeod::LvIhFrame::set_subject_name (const std::string new_name)

Set the subject_name to the supplied value.

Parameters

| in | new_name | new name. |
|----|----------|-----------|
|----|----------|-----------|

Definition at line 221 of file lvlh_frame.cc.

References subject_name.

7.1.3.8 void jeod::LvlhFrame::update (void)

Update the state.

Definition at line 191 of file lvlh_frame.cc.

References compute_lvlh_frame(), frame, planet_centered_inertial, and subject_frame.

7.1.4 Friends And Related Function Documentation

```
7.1.4.1 void init_attrjeod__LvlhFrame( ) [friend]
```

7.1.4.2 friend class InputProcessor [friend]

Definition at line 51 of file lvlh_frame.hh.

7.1.5 Field Documentation

7.1.5.1 RefFrame jeod::LvlhFrame::frame

The LVLH frame defined by the subject frame's motion with respect to the reference planet.

trick units(-)

Definition at line 60 of file lvlh frame.hh.

Referenced by compute_lvlh_frame(), initialize(), update(), and ~LvlhFrame().

```
7.1.5.2 DynManager* jeod::LvlhFrame::local_dm [private]
```

A local pointer to the dynamics manager needed for clean-up.

trick_units(-)

Definition at line 89 of file lvlh_frame.hh.

Referenced by initialize(), and ~LvlhFrame().

7.1.5.3 RefFrame* jeod::LvlhFrame::planet_centered_inertial [protected]

The inertial frame with origin at the center of the specified planet.

trick_units(-)

Definition at line 82 of file lvlh_frame.hh.

Referenced by initialize(), set_planet(), update(), and \sim LvlhFrame().

7.1.5.4 std::string jeod::LvlhFrame::planet_name

The planet used as reference for the LVLH frame.

trick_units(-)

Definition at line 70 of file lvlh_frame.hh.

Referenced by initialize(), and set planet name().

7.1.5.5 RefFrame* jeod::LvlhFrame::subject_frame [protected]

The (moving) frame specified with subject_name.

trick units(-)

Definition at line 77 of file lvlh_frame.hh.

Referenced by initialize(), set_subject_frame(), update(), and ~LvlhFrame().

7.1.5.6 std::string jeod::LvlhFrame::subject_name

The frame whose motion defines LVLH.

Can be on a vehicle or not.trick_units(-)

Definition at line 65 of file lvlh frame.hh.

Referenced by initialize(), and set_subject_name().

The documentation for this class was generated from the following files:

- · Ivlh frame.hh
- lvlh_frame.cc

7.2 jeod::LvlhFrameMessages Class Reference

The class that specifies the message IDs used in the LvlhFrame model.

#include <lvlh_frame_messages.hh>

Static Public Attributes

static char const * fatal_error

Issued when performing an action results in an error return from the method performing the action.

• static char const * illegal value

Issued when a simple type (e.g.

static char const * invalid_name

Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).

• static char const * invalid_configuration

Issued when insufficient information has been specified prior to initialization.

static char const * invalid_object

Issued when a pointer points to an object of the wrong type.

• static char const * null_pointer

Error issued when a pointer is required but was not provided.

• static char const * trace

Debug message issued to trace LvlhFrame actions.

• static char const * divide_by_zero

Fatal message when a divide by zero is encountered.

Private Member Functions

- LvlhFrameMessages (void)
- LvlhFrameMessages (const LvlhFrameMessages &)
- LvlhFrameMessages & operator= (const LvlhFrameMessages &)

Friends

- · class InputProcessor
- · void init attrjeod LvlhFrameMessages ()

7.2.1 Detailed Description

The class that specifies the message IDs used in the LvlhFrame model.

Definition at line 47 of file lvlh frame messages.hh.

7.2.2 Constructor & Destructor Documentation

```
7.2.2.1 jeod::LvlhFrameMessages::LvlhFrameMessages(void) [private]
```

- 7.2.2.2 jeod::LvlhFrameMessages::LvlhFrameMessages (const LvlhFrameMessages &) [private]
- 7.2.3 Member Function Documentation
- 7.2.3.1 LvlhFrameMessages&jeod::LvlhFrameMessages::operator=(const LvlhFrameMessages&) [private]
- 7.2.4 Friends And Related Function Documentation

```
7.2.4.1 void init_attrjeod__LvlhFrameMessages() [friend]
```

7.2.4.2 friend class InputProcessor [friend]

Definition at line 50 of file lvlh_frame_messages.hh.

7.2.5 Field Documentation

7.2.5.1 char const * jeod::LvlhFrameMessages::divide_by_zero [static]

Initial value:

```
=
"utils/lvlh_frame/" "divide_by_zero"
```

Fatal message when a divide by zero is encountered.

```
trick_units(-)
```

Definition at line 96 of file lvlh_frame_messages.hh.

7.2.5.2 char const * **jeod::LvlhFrameMessages::fatal_error** [static]

Initial value:

```
7.2 jeod::LvIhFrameMessages Class Reference
     "utils/lvlh_frame/" "fatal_error"
Issued when performing an action results in an error return from the method performing the action.
trick units(-)
Definition at line 59 of file lvlh_frame_messages.hh.
7.2.5.3 char const * jeod::LvlhFrameMessages::illegal_value [static]
Initial value:
     "utils/lvlh_frame/" "illegal_value"
Issued when a simple type (e.g.
an enum) has an illegal value.trick_units(-)
Definition at line 64 of file lvlh_frame_messages.hh.
7.2.5.4 char const * jeod::LvlhFrameMessages::invalid_configuration [static]
Initial value:
     "utils/lvlh_frame/" "invalid_configuration"
Issued when insufficient information has been specified prior to initialization.
trick units(-)
Definition at line 76 of file lvlh_frame_messages.hh.
Referenced by jeod::LvlhFrame::initialize().
7.2.5.5 char const * jeod::LvlhFrameMessages::invalid_name [static]
Initial value:
     "utils/lvlh_frame/" "invalid_name"
Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).
trick units(-)
Definition at line 70 of file lvlh_frame_messages.hh.
Referenced by jeod::LvlhFrame::initialize().
```

Initial value:

```
"utils/lvlh_frame/" "invalid_object"
```

Issued when a pointer points to an object of the wrong type.

7.2.5.6 char const * jeod::LvlhFrameMessages::invalid_object [static]

trick_units(-)

Definition at line 81 of file lvlh_frame_messages.hh.

7.2.5.7 char const * jeod::LvlhFrameMessages::null_pointer [static]

Initial value:

```
"utils/lvlh_frame/" "null_pointer"
```

Error issued when a pointer is required but was not provided.

trick units(-)

Definition at line 86 of file lvlh_frame_messages.hh.

7.2.5.8 char const * jeod::LvlhFrameMessages::trace [static]

Initial value:

```
= "utils/lvlh_frame/" "trace"
```

Debug message issued to trace LvlhFrame actions.

trick_units(-)

Definition at line 91 of file lvlh_frame_messages.hh.

The documentation for this class was generated from the following files:

- · Ivlh frame messages.hh
- lvlh_frame_messages.cc

7.3 jeod::LvIhType Class Reference

The class used to identify the type of LVLH desired.

```
#include <lvlh_type.hh>
```

Public Types

• enum Type { Rectilinear = 0, CircularCurvilinear = 1, EllipticalCurvilinear = 2 }

An enumeration to specify the type of LVLH coordinates to use, whether rectilinear, circular curvilinear, or elliptical curvilinear.

Public Member Functions

LvlhType (void)

Default constructor.

Data Fields

• Type value

Indicates type of LVLH coordinates desired.

Friends

- · class InputProcessor
- void init_attrjeod__LvlhType ()

7.3.1 Detailed Description

The class used to identify the type of LVLH desired.

Definition at line 44 of file lvlh_type.hh.

7.3.2 Member Enumeration Documentation

7.3.2.1 enum jeod::LvIhType::Type

An enumeration to specify the type of LVLH coordinates to use, whether rectilinear, circular curvilinear, or elliptical curvilinear

As of March 2015, elliptical is not implemented.

Enumerator

Rectilinear

CircularCurvilinear

EllipticalCurvilinear

Definition at line 57 of file lvlh_type.hh.

7.3.3 Constructor & Destructor Documentation

```
7.3.3.1 jeod::LvlhType::LvlhType( void ) [inline]
```

Default constructor.

Definition at line 85 of file lvlh_type.hh.

References Rectilinear, and value.

7.3.4 Friends And Related Function Documentation

```
7.3.4.1 void init_attrjeod__LvlhType( ) [friend]
```

7.3.4.2 friend class InputProcessor [friend]

Definition at line 46 of file lvlh_type.hh.

7.3.5 Field Documentation

7.3.5.1 Type jeod::LvlhType::value

Indicates type of LVLH coordinates desired.

Default is rectilinear.trick units(-)

Definition at line 76 of file lvlh_type.hh.

Referenced by LvlhType().

The documentation for this class was generated from the following file:

• lvlh_type.hh



File Documentation

8.1 lvlh_frame.cc File Reference

Define methods for the LVLH reference frame class.

```
#include <cstddef>
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "environment/planet/include/base_planet.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/named_item/include/named_item.hh"
#include "../include/lvlh_frame.hh"
#include "../include/lvlh_frame_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

8.1.1 Detailed Description

Define methods for the LVLH reference frame class.

Definition in file lvlh_frame.cc.

8.2 lvlh_frame.hh File Reference

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

```
#include <string>
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/planet/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame.hh"
#include "utils/sim_interface/include/jeod_class.hh"
```

28 File Documentation

Data Structures

· class jeod::LvlhFrame

The class used to represent an LVLH reference frame associated with a subject DynBody.

Namespaces

jeod

Namespace jeod.

8.2.1 Detailed Description

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

Definition in file lvlh_frame.hh.

8.3 lvlh_frame_messages.cc File Reference

Implement the class LvIhFrameMessages.

```
#include "../include/lvlh_frame_messages.hh"
```

Namespaces

jeod

Namespace jeod.

Macros

• #define PATH "utils/lvlh_frame/"

8.3.1 Detailed Description

Implement the class LvIhFrameMessages.

Definition in file lvlh_frame_messages.cc.

8.4 lvlh_frame_messages.hh File Reference

Define the class LvIhFrameMessages, the class that specifies the message IDs used in the LvIhFrame model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::LvlhFrameMessages

The class that specifies the message IDs used in the LvlhFrame model.

Namespaces

jeod

Namespace jeod.

8.4.1 Detailed Description

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model. Definition in file lvlh frame messages.hh.

8.5 lvlh_type.hh File Reference

Define the class LvlhType, which identifies the type of LVLH desired to be calculated.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

class jeod::LvlhType

The class used to identify the type of LVLH desired.

Namespaces

• jeod

Namespace jeod.

8.5.1 Detailed Description

Define the class LvIhType, which identifies the type of LVLH desired to be calculated.

Definition in file lvlh_type.hh.

Index

| \sim LvIhFrame | InputProcessor, 20 |
|---------------------------------|------------------------------------|
| jeod::LvlhFrame, 16 | local dm, 20 |
| • | LvlhFrame, 16 |
| CircularCurvilinear | operator=, 18 |
| jeod::LvIhType, 25 | planet_centered_inertial, 20 |
| compute_lvlh_frame | planet name, 20 |
| jeod::LvlhFrame, 17 | set_planet, 18 |
| | set_planet_name, 18 |
| divide_by_zero | set subject frame, 18 |
| jeod::LvIhFrameMessages, 22 | set_subject_name, 18 |
| FIF 11 10 11 | subject_frame, 21 |
| EllipticalCurvilinear | subject_name, 21 |
| jeod::LvlhType, 25 | update, 20 |
| fatal array | jeod::LvlhFrameMessages, 21 |
| fatal_error | |
| jeod::LvlhFrameMessages, 22 | divide_by_zero, 22 |
| frame | fatal_error, 22 |
| jeod::LvlhFrame, 20 | illegal_value, 23 |
| illegal_value | init_attrjeodLvlhFrameMessages, 22 |
| jeod::LvlhFrameMessages, 23 | InputProcessor, 22 |
| init_attrjeod_LvlhFrame | invalid_configuration, 23 |
| jeod::LvlhFrame, 20 | invalid_name, 23 |
| init_attrjeod_LvlhFrameMessages | invalid_object, 23 |
| | LvIhFrameMessages, 22 |
| jeod::LvlhFrameMessages, 22 | null_pointer, 23 |
| init_attrjeodLvlhType | operator=, 22 |
| jeod::LvlhType, 25 | trace, 24 |
| initialize | jeod::LvlhType, 24 |
| jeod::LvlhFrame, 18 | init_attrjeodLvIhType, 25 |
| InputProcessor | InputProcessor, 25 |
| jeod::LvlhFrame, 20 | LvlhType, 25 |
| jeod::LvlhFrameMessages, 22 | Type, 25 |
| jeod::LvlhType, 25 | value, 25 |
| invalid_configuration | |
| jeod::LvlhFrameMessages, 23 | local dm |
| invalid_name | jeod::LvIhFrame, 20 |
| jeod::LvlhFrameMessages, 23 | lvlh frame.cc, 27 |
| invalid_object | lvlh frame.hh, 27 |
| jeod::LvlhFrameMessages, 23 | lvlh_frame_messages.cc, 28 |
| 1.1.0 | lvlh frame messages.hh, 28 |
| jeod, 13 | lvlh_type.hh, 29 |
| jeod::LvlhType | — · · |
| CircularCurvilinear, 25 | LvlhFrame, 11 |
| EllipticalCurvilinear, 25 | jeod::LvlhFrame, 16 |
| Rectilinear, 25 | PATH, 11 |
| jeod::LvlhFrame, 15 | LvlhFrameMessages |
| ∼LvlhFrame, 16 | jeod::LvlhFrameMessages, 22 |
| compute_lvlh_frame, 17 | LvIhType |
| frame, 20 | jeod::LvlhType, 25 |
| init_attrjeodLvlhFrame, 20 | |
| initialize, 18 | Models, 9 |

INDEX 31

```
null_pointer
    jeod::LvlhFrameMessages, 23
operator=
    jeod::LvlhFrame, 18
    jeod::LvlhFrameMessages, 22
PATH
    LvIhFrame, 11
planet_centered_inertial
    jeod::LvlhFrame, 20
planet_name
    jeod::LvlhFrame, 20
Rectilinear
    jeod::LvlhType, 25
set_planet
    jeod::LvlhFrame, 18
set_planet_name
    jeod::LvlhFrame, 18
set_subject_frame
    jeod::LvlhFrame, 18
set_subject_name
    jeod::LvlhFrame, 18
subject_frame
    jeod::LvlhFrame, 21
subject_name
    jeod::LvlhFrame, 21
    jeod::LvlhFrameMessages, 24
Type
    jeod::LvlhType, 25
update
    jeod::LvlhFrame, 20
Utils, 10
value
    jeod::LvlhType, 25
```