RadiationPressureModel 5.0

Generated by Doxygen 1.8.5

Wed Jun 1 2022 12:07:44

Contents

1	Mod	lule Inde	ex	1
	1.1	Module	es	1
2	Nam	nespace	Index	3
	2.1	Names	space List	3
3	Hier	archica	l Index	5
	3.1	Class I	Hierarchy	5
4	Data	Struct	ure Index	7
	4.1	Data S	tructures	7
5	File	Index		9
	5.1	File Lis	st	9
6	Mod	lule Doc	eumentation	11
	6.1	Models	3	11
		6.1.1	Detailed Description	11
	6.2	Interac	tions	12
		6.2.1	Detailed Description	12
	6.3	Radiat	ionPressure	13
		6.3.1	Detailed Description	14
		6.3.2	Macro Definition Documentation	14
			6.3.2.1 PATH	14
7	Nam	nespace	Documentation	15
	7.1	jeod N	amespace Reference	15
		7.1.1	Detailed Description	15
8	Data	Struct	ure Documentation	17
	8.1	jeod::F	latPlateRadiationFacet Class Reference	17
		8.1.1	Detailed Description	18
		8.1.2	Constructor & Destructor Documentation	18
			8.1.2.1 FlatPlateRadiationFacet	18

iv CONTENTS

		8.1.2.2	~FlatPlateRadiationFacet	18
		8.1.2.3	FlatPlateRadiationFacet	18
	8.1.3	Member	Function Documentation	18
		8.1.3.1	define_facet	18
		8.1.3.2	incident_radiation	19
		8.1.3.3	initialize_geom	19
		8.1.3.4	operator=	19
		8.1.3.5	radiation_pressure	19
	8.1.4	Friends A	And Related Function Documentation	19
		8.1.4.1	init_attrjeodFlatPlateRadiationFacet	19
		8.1.4.2	InputProcessor	20
	8.1.5	Field Doo	cumentation	20
		8.1.5.1	incident_flux_hat	20
		8.1.5.2	normal	20
		8.1.5.3	sin_theta	20
8.2	jeod::F	latPlateRa	adiationFactory Class Reference	20
	8.2.1	Detailed	Description	21
	8.2.2	Construc	tor & Destructor Documentation	21
		8.2.2.1	FlatPlateRadiationFactory	21
		8.2.2.2	$\sim \! FlatPlateRadiationFactory \ \ldots \ \ldots$	21
		8.2.2.3	FlatPlateRadiationFactory	21
	8.2.3	Member	Function Documentation	21
		8.2.3.1	create_facet	21
		8.2.3.2	is_correct_factory	22
		8.2.3.3	operator=	22
	8.2.4	Friends A	And Related Function Documentation	22
		8.2.4.1	init_attrjeodFlatPlateRadiationFactory	22
		8.2.4.2	InputProcessor	22
8.3	jeod::R	adiationBa	aseFacet Class Reference	22
	8.3.1	Detailed	Description	24
	8.3.2	Construc	tor & Destructor Documentation	24
		8.3.2.1	RadiationBaseFacet	24
		8.3.2.2	~RadiationBaseFacet	24
		8.3.2.3	RadiationBaseFacet	24
	8.3.3	Member	Function Documentation	24
		8.3.3.1	incident_radiation	24
		8.3.3.2	initialize	24
		8.3.3.3	initialize_runtime_values	24
		8.3.3.4	interact_with_third_body	25
		8.3.3.5	operator=	25

CONTENTS

	8.3.4	Friends A	And Related Function Documentation	25
		8.3.4.1	init_attrjeodRadiationBaseFacet	25
		8.3.4.2	InputProcessor	25
	8.3.5	Field Doo	cumentation	25
		8.3.5.1	albedo	25
		8.3.5.2	albedo_IR	25
		8.3.5.3	albedo_vis	26
		8.3.5.4	areaxflux	26
		8.3.5.5	areaxflux_e	26
		8.3.5.6	cx_area	26
		8.3.5.7	diffuse	26
		8.3.5.8	F_absorption	26
		8.3.5.9	F_diffuse	27
		8.3.5.10	F_emission	27
		8.3.5.11	F_specular	27
		8.3.5.12	speed_of_light	27
		8.3.5.13	thermal	27
8.4	jeod::R	adiationDe	efaultSurface Class Reference	28
	8.4.1	Detailed	Description	29
	8.4.2	Construc	tor & Destructor Documentation	29
		8.4.2.1	RadiationDefaultSurface	29
		8.4.2.2	~RadiationDefaultSurface	29
		8.4.2.3	RadiationDefaultSurface	29
	8.4.3	Member	Function Documentation	29
		8.4.3.1	add_thermal_integrator_to	29
		8.4.3.2	incident_radiation	29
		8.4.3.3	initialize	30
		8.4.3.4	operator=	30
		8.4.3.5	set_name	30
		8.4.3.6	thermal_update	30
	8.4.4	Friends A	And Related Function Documentation	30
		8.4.4.1	init_attrjeodRadiationDefaultSurface	30
		8.4.4.2	InputProcessor	31
	8.4.5	Field Doo	cumentation	31
		8.4.5.1	name	31
		8.4.5.2	rad_coeff	31
		8.4.5.3	surface_area	31
		8.4.5.4	temperature	31
8.5	jeod::R		acet Class Reference	31
	8.5.1	Detailed	Description	33

vi CONTENTS

	8.5.2	Construc	ctor & Destructor Documentation	33
		8.5.2.1	RadiationFacet	33
		8.5.2.2	\sim RadiationFacet	33
		8.5.2.3	RadiationFacet	33
	8.5.3	Member	Function Documentation	33
		8.5.3.1	define_facet_core	33
		8.5.3.2	get_thermal_integrator	33
		8.5.3.3	initialize	33
		8.5.3.4	initialize_geom	34
		8.5.3.5	operator=	34
		8.5.3.6	radiation_pressure	34
	8.5.4	Friends A	And Related Function Documentation	34
		8.5.4.1	init_attrjeodRadiationFacet	34
		8.5.4.2	InputProcessor	34
	8.5.5	Field Doo	cumentation	34
		8.5.5.1	center_pressure	34
		8.5.5.2	crot_to_cp	34
		8.5.5.3	two_thirds	35
8.6	jeod::R	adiationM	lessages Class Reference	35
	8.6.1	Detailed	Description	35
	8.6.2	Construc	ctor & Destructor Documentation	36
		8.6.2.1	RadiationMessages	36
		8.6.2.2	RadiationMessages	36
	8.6.3	Member	Function Documentation	36
		8.6.3.1	operator=	36
	8.6.4	Friends A	And Related Function Documentation	36
		8.6.4.1	init_attrjeodRadiationMessages	36
		8.6.4.2	InputProcessor	36
	8.6.5	Field Doo	cumentation	36
		8.6.5.1	incomplete_setup_error	36
		8.6.5.2	invalid_function_call	36
		8.6.5.3	invalid_setup_error	36
		8.6.5.4	operational_setup_error	37
		8.6.5.5	unknown_numerical_error	37
8.7	jeod::R	adiationPa	arams Class Reference	37
	8.7.1	Detailed	Description	38
	8.7.2	Construc	ctor & Destructor Documentation	38
		8.7.2.1	RadiationParams	38
		8.7.2.2	\sim RadiationParams	38
		8.7.2.3	RadiationParams	39

CONTENTS vii

	8.7.3	Member	Function Documentation	39
		8.7.3.1	operator=	39
	8.7.4	Friends A	And Related Function Documentation	39
		8.7.4.1	init_attrjeodRadiationParams	39
		8.7.4.2	InputProcessor	39
	8.7.5	Field Doo	cumentation	39
		8.7.5.1	albedo	39
		8.7.5.2	diffuse	39
		8.7.5.3	thermal	39
8.8	jeod::R	adiationPr	ressure Class Reference	39
	8.8.1	Detailed	Description	41
	8.8.2	Construc	tor & Destructor Documentation	41
		8.8.2.1	RadiationPressure	41
		8.8.2.2	~RadiationPressure	41
		8.8.2.3	RadiationPressure	42
	8.8.3	Member	Function Documentation	42
		8.8.3.1	add_third_body	42
		8.8.3.2	find_third_body	42
		8.8.3.3	initialize	42
		8.8.3.4	initialize	42
		8.8.3.5	initialize_environment	44
		8.8.3.6	operator=	44
		8.8.3.7	set_calculate_forces	44
		8.8.3.8	set_third_body_active	44
		8.8.3.9	set_third_body_inactive	44
		8.8.3.10	third_body_adjustments	45
		8.8.3.11	update	45
		8.8.3.12	update_default_surface	45
		8.8.3.13	update_facet_surface	45
	8.8.4	Friends A	And Related Function Documentation	46
		8.8.4.1	init_attrjeodRadiationPressure	46
		8.8.4.2	InputProcessor	46
	8.8.5	Field Doo	cumentation	46
		8.8.5.1	active	46
		8.8.5.2	calculate_forces	46
		8.8.5.3	default_surface_ptr	46
		8.8.5.4	dyn_manager_ptr	46
		8.8.5.5	force	47
		8.8.5.6	illum_factor	47
		8.8.5.7	initialized	47

viii CONTENTS

		8.8.5.8	num_third_bodies	47
		8.8.5.9	source	47
		8.8.5.10	surface_ptr	47
		8.8.5.11	thermal	48
		8.8.5.12	third_bodies	48
		8.8.5.13	third_bodies_active	48
		8.8.5.14	torque	48
8.9	jeod::R	adiationSo	ource Class Reference	48
	8.9.1	Detailed	Description	50
	8.9.2	Member	Enumeration Documentation	50
		8.9.2.1	OldShadowGeometry	50
	8.9.3	Construc	tor & Destructor Documentation	50
		8.9.3.1	RadiationSource	50
		8.9.3.2	~RadiationSource	50
		8.9.3.3	RadiationSource	51
	8.9.4	Member	Function Documentation	51
		8.9.4.1	calculate_flux	51
		8.9.4.2	initialize	51
		8.9.4.3	operator=	51
		8.9.4.4	set_name	51
	8.9.5	Friends A	And Related Function Documentation	51
		8.9.5.1	init_attrjeodRadiationSource	51
		8.9.5.2	InputProcessor	51
	8.9.6	Field Doo	cumentation	51
		8.9.6.1	bodies_active	51
		8.9.6.2	d_source_to_cg	52
		8.9.6.3	flux_hat	52
		8.9.6.4	flux_inertial	52
		8.9.6.5	flux_mag	52
		8.9.6.6	flux_struc	52
		8.9.6.7	flux_struc_hat	52
		8.9.6.8	inertial_cg	53
		8.9.6.9	inertial_frame_ptr	53
		8.9.6.10	luminosity	53
		8.9.6.11	multiple_shadow_bodies	53
		8.9.6.12	name	53
		8.9.6.13	num_bodies	53
		8.9.6.14	radius	54
		8.9.6.15	shadow_geometry	54
		8.9.6.16	solar_luminosity	54

CONTENTS

		8.9.6.17 sola	ar_radius		 	 	 	54
		8.9.6.18 sou	rce_to_cg		 	 	 	54
		8.9.6.19 sou	rce_to_struc_origin		 	 	 	54
		8.9.6.20 third	d_body		 	 	 	55
8.10	jeod::R	adiationSurfac	e Class Reference		 	 	 	55
	8.10.1	Detailed Desc	ription		 	 	 	56
	8.10.2	Constructor &	Destructor Documenta	ation	 	 	 	56
		8.10.2.1 Rad	liationSurface		 	 	 	56
		8.10.2.2 ∼R	adiationSurface		 	 	 	56
		8.10.2.3 Rad	liationSurface		 	 	 	57
	8.10.3	Member Fund	tion Documentation .		 	 	 	57
		8.10.3.1 acc	umulate_thermal_sour	ces	 	 	 	57
		8.10.3.2 add	_thermal_integrators_	to	 	 	 	57
		8.10.3.3 allo	cate_array		 	 	 	57
		8.10.3.4 allo	cate_interaction_facet		 	 	 	57
		8.10.3.5 equ	alize_absorption_emis	sion	 	 	 	57
		8.10.3.6 inci	dent_radiation		 	 	 	58
		8.10.3.7 initi	alize		 	 	 	59
		8.10.3.8 initi	alize_runtime_values .		 	 	 	59
		8.10.3.9 inte	ract_with_third_body .		 	 	 	59
		8.10.3.10 ope	rator=		 	 	 	59
		8.10.3.11 rad	ation_pressure		 	 	 	59
		8.10.3.12 the	mal_integrator		 	 	 	60
	8.10.4	Friends And F	delated Function Docur	mentation	 	 	 	60
		8.10.4.1 init_	_attrjeodRadiationSu	urface	 	 	 	60
		8.10.4.2 Inpo	utProcessor		 	 	 	60
	8.10.5	Field Docume	ntation		 	 	 	60
		8.10.5.1 face	ets		 	 	 	60
		8.10.5.2 force	e		 	 	 	60
		8.10.5.3 ii_fa	icet		 	 	 	60
		8.10.5.4 incl	ude_conduction		 	 	 	60
		8.10.5.5 nun	n_facets		 	 	 	61
		8.10.5.6 the	mal_conduction		 	 	 	61
		8.10.5.7 tord	ue		 	 	 	61
8.11	jeod::R	adiationSurfac	eFactory Class Refere	nce	 	 	 	61
	8.11.1	Detailed Desc	ription		 	 	 	62
	8.11.2	Constructor &	Destructor Documenta	ation	 	 	 	62
		8.11.2.1 Rad	liationSurfaceFactory .		 	 	 	62
		8.11.2.2 ∼R	adiationSurfaceFactory	y	 	 	 	62
		8.11.2.3 Rad	liationSurfaceFactory .		 	 	 	62

X CONTENTS

	8.11.3	Member Function Documentation	62
		8.11.3.1 add_facet_params	62
		8.11.3.2 operator=	63
	8.11.4	Friends And Related Function Documentation	63
		8.11.4.1 init_attrjeodRadiationSurfaceFactory	63
		8.11.4.2 InputProcessor	63
	8.11.5	Field Documentation	63
		8.11.5.1 flat_plate_radiation_factory	63
8.12	jeod::R	adiationThirdBody Class Reference	63
	8.12.1	Detailed Description	65
	8.12.2	Member Enumeration Documentation	66
		8.12.2.1 ShadowGeometry	66
	8.12.3	Constructor & Destructor Documentation	66
		8.12.3.1 RadiationThirdBody	66
		8.12.3.2 \sim RadiationThirdBody	66
		8.12.3.3 RadiationThirdBody	66
	8.12.4	Member Function Documentation	66
		8.12.4.1 accumulate_rad_flux	66
		8.12.4.2 accumulate_refl_flux	66
		8.12.4.3 calculate_shadow	67
		8.12.4.4 convert_shadow_from_int	67
		8.12.4.5 generate_alpha	67
		8.12.4.6 get_added_to_model	67
		8.12.4.7 initialize	68
		8.12.4.8 is_interactive	68
		8.12.4.9 operator=	68
		8.12.4.10 process_third_body	68
		8.12.4.11 set_added_to_model	68
		8.12.4.12 set_name	69
		8.12.4.13 test_for_state_update	69
		8.12.4.14 update_third_body_state	69
	8.12.5	Friends And Related Function Documentation	69
		8.12.5.1 init_attrjeodRadiationThirdBody	69
		8.12.5.2 InputProcessor	69
	8.12.6	Field Documentation	69
		8.12.6.1 active	69
		8.12.6.2 added_to_model	70
		8.12.6.3 d_source_to_third	70
		8.12.6.4 force_state_update	70
		8.12.6.5 illum_factor	70

CONTENTS xi

		8.12.6.6 initialized	70
		8.12.6.7 last_update_time	70
		8.12.6.8 local_frame_ptr	71
		8.12.6.9 name	71
		8.12.6.10 output_flux	71
		8.12.6.11 planet_link	71
		8.12.6.12 primary_source_ptr	71
		8.12.6.13 r_minus	71
		8.12.6.14 r_par	72
		8.12.6.15 r_perp	72
		8.12.6.16 r_plus	72
		8.12.6.17 r_ratio	72
		8.12.6.18 radius	72
		8.12.6.19 shadow_geometry	72
		8.12.6.20 source_to_third_hat_inrtl	73
		8.12.6.21 source_to_third_inrtl	73
		8.12.6.22 third_to_cg_inrtl	73
		8.12.6.23 update_interval	73
9	File I	Documentation	75
•	9.1	flat_plate_radiation_facet.cc File Reference	75
	0.1	9.1.1 Detailed Description	75
	9.2	flat_plate_radiation_facet.hh File Reference	75
	0.2	9.2.1 Detailed Description	76
	9.3	flat_plate_radiation_factory.cc File Reference	76
	0.0	9.3.1 Detailed Description	76
	9.4	flat_plate_radiation_factory.hh File Reference	76
	0.4	9.4.1 Detailed Description	77
	9.5	radiation_base_facet.cc File Reference	77
	0.0	9.5.1 Detailed Description	77
	9.6	radiation_base_facet.hh File Reference	77
	0.0	9.6.1 Detailed Description	78
	9.7	radiation_default_surface.cc File Reference	78
	•	9.7.1 Detailed Description	78
	9.8	radiation_default_surface.hh File Reference	78
	5.5	9.8.1 Detailed Description	79
	9.9	radiation_facet.cc File Reference	79
	2.0	9.9.1 Detailed Description	79
	9.10	radiation_facet.hh File Reference	79
	5.10	9.10.1 Detailed Description	80

xii CONTENTS

9.11	radiation_messages.cc File Reference	80
	9.11.1 Detailed Description	80
9.12	radiation_messages.hh File Reference	80
	9.12.1 Detailed Description	80
9.13	radiation_params.cc File Reference	81
	9.13.1 Detailed Description	81
9.14	radiation_params.hh File Reference	81
	9.14.1 Detailed Description	81
9.15	radiation_pressure.cc File Reference	81
	9.15.1 Detailed Description	82
9.16	radiation_pressure.hh File Reference	82
	9.16.1 Detailed Description	82
9.17	radiation_pressuredefault_surface.cc File Reference	83
	9.17.1 Detailed Description	83
9.18	radiation_pressuresurface_model.cc File Reference	83
	9.18.1 Detailed Description	83
9.19	radiation_source.cc File Reference	83
	9.19.1 Detailed Description	84
9.20	radiation_source.hh File Reference	84
	9.20.1 Detailed Description	84
9.21	radiation_surface.cc File Reference	84
	9.21.1 Detailed Description	85
9.22	radiation_surface.hh File Reference	85
	9.22.1 Detailed Description	85
9.23	radiation_surface_factory.cc File Reference	86
	9.23.1 Detailed Description	86
9.24	radiation_surface_factory.hh File Reference	86
	9.24.1 Detailed Description	86
9.25	radiation_third_body.cc File Reference	86
	9.25.1 Detailed Description	87
9.26	radiation_third_body.hh File Reference	87
	9.26.1 Detailed Description	87

Module Index

1.1 Modules

11	:_	_	1: _4		-11	modules:
пеге	15	a	IISt	OI	all	modules.

Models	 	 11
Interactions	 	 12
RadiationPressu	 	 13

2 **Module Index**

Namespace Index

2.1	Namespace List
Here	is a list of all namespaces with brief descriptions:
je	od

Namespace Index

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

FacetParams	
jeod::RadiationParams	37
nteractionFacet	
jeod::RadiationFacet	31
jeod::FlatPlateRadiationFacet	17
nteractionFacetFactory	
jeod::FlatPlateRadiationFactory	20
nteractionSurface	
jeod::RadiationSurface	55
nteractionSurfaceFactory	
jeod::RadiationSurfaceFactory	
eod::RadiationBaseFacet	22
jeod::RadiationDefaultSurface	28
jeod::RadiationFacet	31
eod::RadiationMessages	35
eod::RadiationPressure	39
eod::RadiationSource	48
eod::RadiationThirdBody	63

6 **Hierarchical Index**

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

jeod::FlatPlateRadiationFacet	
A flat plate facet to be used for radiation interaction	17
jeod::FlatPlateRadiationFactory	
The factory for building flat plate radiation facets	20
jeod::RadiationBaseFacet	
Generic type of facet for radiation pressure	22
jeod::RadiationDefaultSurface	
The default spherical surface for radiation pressure	28
jeod::RadiationFacet	
Generic type of facet for radiation pressure	31
jeod::RadiationMessages	
Provides error messages	35
jeod::RadiationParams	
Provides a parameter list to each facet, based on the facet material properties	37
jeod::RadiationPressure	
Radiation pressure top-level definition	39
jeod::RadiationSource	
Provides information on the source of the incident radiation	48
jeod::RadiationSurface	
The surface of the vehicle that interacts with the incident flux	55
jeod::RadiationSurfaceFactory	
The factory for creating Radiation Surfaces	61
jeod::RadiationThirdBody	
Provide information on bodies that may cause shadowing or reflected illumination	63
Provide information on bodies that may cause shadowing or reflected illumination	63

8 Data Structure Index

File Index

5.1 File List

Here is a list of all files with brief descriptions:

flat plate	_radiation_facet.cc	
	Define member functions for class FlatPlateRadiationFacet	75
flat_plate	_radiation_facet.hh	
	Individual facets for use with rad environment interaction models	75
flat_plate	_radiation_factory.cc	
	Factory that creates a FlatPlateRadiationFacet, from a facet model	76
flat_plate	_radiation_factory.hh	
	Factory that creates an interaction facet, for a specific environment interaction model, from a	
	facet model	76
radiation_	_base_facet.cc	
	Define member functions for class RadiationBaseFacet	77
radiation_	_base_facet.hh	
	Individual facets for use with radiation environment interaction models	77
radiation_	_default_surface.cc	
	Default surface for use with Radiation Pressure interaction model	78
radiation_	_default_surface.hh	
	Individual facets for use with radiation environment interaction models	78
radiation_	_facet.cc	
	Individual facets for use with Radiation Pressure interaction models	79
$radiation_{_}$	_	
	Individual facets for use with radiation environment interaction models	79
$radiation_{_}$	_messages.cc	
	Implement the class RadiationMessages	80
radiation_	_messages.hh	
	Define the class RadiationMessages, the class that specifies the message IDs used in the Radi-	
	ation model	80
radiation_	_params.cc	
	A virtual base class for radiation facet parameters, used to create interaction facets for radiation	
	in the InteractionSurfaceFactorys	81
radiation_	_params.hh	
	A virtual base class for radiation facet parameters, used to create interaction facets for radiation	
	in the InteractionSurfaceFactorys	81
radiation_	_pressure.cc	
	Calculation of force and torque due to radiation pressure	81
radiation_	_pressure.hh	
	Radiation pressure top-level definition	82
radiation_	_pressuredefault_surface.cc	
	Calculation of force and torque due to radiation pressure	83

10 File Index

radiation_pressuresurface_model.cc	
Calculation of force and torque due to radiation pressure	83
radiation_source.cc	
Definition of methods associated with Primary Sources	83
radiation_source.hh	
Radiation pressure parameter and variable definitions	84
radiation_surface.cc	
Vehicle surface model for Radiation Pressure model	84
radiation_surface.hh	
Vehicle surface model for general environment interaction models	85
radiation_surface_factory.cc	
Factory that creates an interaction surface, for a specific enviornment interaction model, from a	
surface model	86
radiation_surface_factory.hh	
Factory that creates an interaction surface, for a specific environment interaction model, from a	
surface model	86
radiation_third_body.cc	
Provides the functionality associated with RadiationThirdBodys	86
radiation_third_body.hh	
Define the class RadiationThirdBody	87

Module Documentation

6.1 Models

Modules

- Interactions
- 6.1.1 Detailed Description

12 Module Documentation

6.2 Interactions

Modules

RadiationPressure

6.2.1 Detailed Description

6.3 RadiationPressure 13

6.3 RadiationPressure

Files

· file flat_plate_radiation_facet.hh

Individual facets for use with rad environment interaction models.

· file flat plate radiation factory.hh

Factory that creates an interaction facet, for a specific environment interaction model, from a facet model.

· file radiation base facet.hh

Individual facets for use with radiation environment interaction models.

· file radiation default surface.hh

Individual facets for use with radiation environment interaction models.

file radiation_facet.hh

Individual facets for use with radiation environment interaction models.

file radiation_messages.hh

Define the class RadiationMessages, the class that specifies the message IDs used in the Radiation model.

· file radiation_params.hh

A virtual base class for radiation facet parameters, used to create interaction facets for radiation in the Interaction-SurfaceFactorys.

file radiation_pressure.hh

Radiation pressure top-level definition.

· file radiation_source.hh

Radiation pressure parameter and variable definitions.

· file radiation_surface.hh

Vehicle surface model for general environment interaction models.

· file radiation surface factory.hh

Factory that creates an interaction surface, for a specific environment interaction model, from a surface model.

• file radiation_third_body.hh

 ${\it Define the class Radiation Third Body.}$

file flat_plate_radiation_facet.cc

Define member functions for class FlatPlateRadiationFacet.

file flat_plate_radiation_factory.cc

Factory that creates a FlatPlateRadiationFacet, from a facet model.

· file radiation base facet.cc

Define member functions for class RadiationBaseFacet.

• file radiation_default_surface.cc

Default surface for use with Radiation Pressure interaction model.

· file radiation facet.cc

Individual facets for use with Radiation Pressure interaction models.

file radiation_messages.cc

Implement the class RadiationMessages.

· file radiation params.cc

A virtual base class for radiation facet parameters, used to create interaction facets for radiation in the Interaction-SurfaceFactorys.

· file radiation pressure.cc

Calculation of force and torque due to radiation pressure.

file radiation_pressure__default_surface.cc

Calculation of force and torque due to radiation pressure.

• file radiation_pressure__surface_model.cc

Calculation of force and torque due to radiation pressure.

• file radiation_source.cc

14 Module Documentation

Definition of methods associated with Primary Sources.

• file radiation_surface.cc

Vehicle surface model for Radiation Pressure model.

• file radiation_surface_factory.cc

Factory that creates an interaction surface, for a specific environment interaction model, from a surface model.

• file radiation_third_body.cc

Provides the functionality associated with RadiationThirdBodys.

Namespaces

jeod

Namespace jeod.

Macros

- #define PATH "interactions/radiation pressure/"
- 6.3.1 Detailed Description
- 6.3.2 Macro Definition Documentation
- 6.3.2.1 #define PATH "interactions/radiation_pressure/"

Definition at line 39 of file radiation_messages.cc.

Namespace Documentation

7.1 jeod Namespace Reference

Namespace jeod.

Data Structures

· class FlatPlateRadiationFacet

A flat plate facet to be used for radiation interaction.

· class FlatPlateRadiationFactory

The factory for building flat plate radiation facets.

· class RadiationBaseFacet

Generic type of facet for radiation pressure.

· class RadiationDefaultSurface

The default spherical surface for radiation pressure.

class RadiationFacet

Generic type of facet for radiation pressure.

class RadiationMessages

Provides error messages.

• class RadiationParams

Provides a parameter list to each facet, based on the facet material properties.

• class RadiationPressure

Radiation pressure top-level definition.

· class RadiationSource

Provides information on the source of the incident radiation.

class RadiationSurface

The surface of the vehicle that interacts with the incident flux.

class RadiationSurfaceFactory

The factory for creating Radiation Surfaces.

class RadiationThirdBody

Provide information on bodies that may cause shadowing or reflected illumination.

7.1.1 Detailed Description

Namespace jeod.

Names	pace	Docur	mentatior


Data Structure Documentation

8.1 jeod::FlatPlateRadiationFacet Class Reference

A flat plate facet to be used for radiation interaction.

```
#include <flat_plate_radiation_facet.hh>
```

Inheritance diagram for jeod::FlatPlateRadiationFacet:



Public Member Functions

• FlatPlateRadiationFacet ()

Construct a FlatPlateRadiationFacet.

virtual ∼FlatPlateRadiationFacet ()

Destructor for FlatPlateRadiationFacet.

- void incident_radiation (const double flux_mag, const double flux_struct_hat[3], const bool calculate_forces)

 Calculation of force and torque due to radiation pressure.
- void initialize_geom (double center_grav[3])

Initializes the Facet for use in the model.

void define_facet (FlatPlate *flat_plate)

Defines the facet data values.

void radiation_pressure (void)

Calculates the radiative emission force, accumulated force, and torque acting on a facet.

Data Fields

double * normal

Unit vector normal to the plate surface, pointing outward (structural frame).

• double incident_flux_hat [3]

Temporary value.

Private Member Functions

- FlatPlateRadiationFacet & operator= (const FlatPlateRadiationFacet &rhs)
- FlatPlateRadiationFacet (const FlatPlateRadiationFacet &rhs)

Private Attributes

· double sin_theta

Theta is the angle between the plate and the radiation vector.

Friends

- · class InputProcessor
- void init attrjeod FlatPlateRadiationFacet ()

Additional Inherited Members

8.1.1 Detailed Description

A flat plate facet to be used for radiation interaction.

Definition at line 52 of file flat_plate_radiation_facet.hh.

8.1.2 Constructor & Destructor Documentation

8.1.2.1 jeod::FlatPlateRadiationFacet::FlatPlateRadiationFacet (void)

Construct a FlatPlateRadiationFacet.

Definition at line 61 of file flat_plate_radiation_facet.cc.

```
8.1.2.2 jeod::FlatPlateRadiationFacet::~FlatPlateRadiationFacet(void) [virtual]
```

Destructor for FlatPlateRadiationFacet.

Definition at line 224 of file flat_plate_radiation_facet.cc.

```
8.1.2.3 jeod::FlatPlateRadiationFacet::FlatPlateRadiationFacet ( const FlatPlateRadiationFacet & rhs ) [private]
```

8.1.3 Member Function Documentation

8.1.3.1 void jeod::FlatPlateRadiationFacet::define_facet (FlatPlate * flat_plate)

Defines the facet data values.

Parameters

	in	flat_plate	pointer to the flat plate object
--	----	------------	----------------------------------

Definition at line 76 of file flat_plate_radiation_facet.cc.

References jeod::RadiationFacet::center_pressure, and normal.

 $Referenced\ by\ jeod::FlatPlateRadiationFactory::create_facet().$

8.1.3.2 void jeod::FlatPlateRadiationFacet::incident_radiation (const double flux_mag, const double flux_struct_hat[3], const bool calculate_forces) [virtual]

Calculation of force and torque due to radiation pressure.

Assumptions and Limitations

Only called when flux_mag > 0

Parameters

	in	flux_mag	incident flux (per unit area)
			Units: N/m
Ī	in	flux_struct_hat	the flux unit vector in structural frame
	in	calculate_forces	on/off flag for whether to calculate forces.

Implements jeod::RadiationBaseFacet.

Definition at line 120 of file flat_plate_radiation_facet.cc.

References jeod::RadiationBaseFacet::albedo, jeod::RadiationBaseFacet::areaxflux, jeod::RadiationBaseFacet::areaxflux_e, jeod::RadiationBaseFacet::cx_area, jeod::RadiationBaseFacet::diffuse, jeod::RadiationBaseFacet::F_absorption, jeod::RadiationBaseFacet::F_diffuse, jeod::RadiationBaseFacet::F_specular, normal, sin_theta, jeod::RadiationBaseFacet::speed_of_light, jeod::RadiationBaseFacet::thermal, and jeod::RadiationFacet::two_thirds.

8.1.3.3 void jeod::FlatPlateRadiationFacet::initialize_geom (double center_grav[3]) [virtual]

Initializes the Facet for use in the model.

Parameters

in	center_grav	center of gravity position
		Units: M

Implements jeod::RadiationFacet.

Definition at line 98 of file flat_plate_radiation_facet.cc.

References jeod::RadiationFacet::center_pressure, jeod::RadiationFacet::crot_to_cp, jeod::RadiationFacet::initialize(), and jeod::RadiationBaseFacet::thermal.

- 8.1.3.4 FlatPlateRadiationFacet& jeod::FlatPlateRadiationFacet::operator=(const FlatPlateRadiationFacet & rhs)
 [private]
- **8.1.3.5 void jeod::FlatPlateRadiationFacet::radiation_pressure(void)** [virtual]

Calculates the radiative emission force, accumulated force, and torque acting on a facet.

Implements jeod::RadiationFacet.

Definition at line 183 of file flat_plate_radiation_facet.cc.

References jeod::RadiationFacet::crot_to_cp, jeod::RadiationBaseFacet::F_absorption, jeod::RadiationBaseFacet::F_diffuse, jeod::RadiationBaseFacet::F_emission, jeod::RadiationBaseFacet::F_specular, normal, jeod::RadiationBaseFacet::speed_of_light, jeod::RadiationBaseFacet::thermal, jeod::RadiationFacet::two_thirds, and jeod::RadiationMessages::unknown_numerical_error.

8.1.4 Friends And Related Function Documentation

8.1.4.1 void init_attrjeod__FlatPlateRadiationFacet() [friend]

8.1.4.2 friend class InputProcessor [friend]

Definition at line 54 of file flat_plate_radiation_facet.hh.

8.1.5 Field Documentation

8.1.5.1 double jeod::FlatPlateRadiationFacet::incident_flux_hat[3]

Temporary value.

trick units(-)

Definition at line 70 of file flat_plate_radiation_facet.hh.

8.1.5.2 double* jeod::FlatPlateRadiationFacet::normal

Unit vector normal to the plate surface, pointing outward (structural frame).

once the radiation surface is initialized, it points to the normal found in FlatPlatetrick_units(-)

Definition at line 65 of file flat plate radiation facet.hh.

Referenced by define_facet(), incident_radiation(), and radiation_pressure().

8.1.5.3 double jeod::FlatPlateRadiationFacet::sin_theta [private]

Theta is the angle between the plate and the radiation vector.

trick_units(-)

Definition at line 76 of file flat_plate_radiation_facet.hh.

Referenced by incident_radiation().

The documentation for this class was generated from the following files:


- flat_plate_radiation_facet.hh
- flat_plate_radiation_facet.cc

8.2 jeod::FlatPlateRadiationFactory Class Reference

The factory for building flat plate radiation facets.

```
#include <flat_plate_radiation_factory.hh>
```

Inheritance diagram for jeod::FlatPlateRadiationFactory:



Public Member Functions

- FlatPlateRadiationFactory ()
 - Constructor for FlatPlateRadiationFactory.
- ∼FlatPlateRadiationFactory ()

Destructor for FlatPlateRadiationFactory.

virtual InteractionFacet * create_facet (Facet *facet, FacetParams *params)

Records the data for the Flat Plate Radiation Facet.

virtual bool is_correct_factory (Facet *facet)

Tests to ensure that the factory can function on the facet as intended.

Private Member Functions

- FlatPlateRadiationFactory & operator= (const FlatPlateRadiationFactory &rhs)
- FlatPlateRadiationFactory (const FlatPlateRadiationFactory &rhs)

Friends

- · class InputProcessor
- void init_attrjeod__FlatPlateRadiationFactory ()

8.2.1 Detailed Description

The factory for building flat plate radiation facets.

Definition at line 51 of file flat_plate_radiation_factory.hh.

8.2.2 Constructor & Destructor Documentation

8.2.2.1 jeod::FlatPlateRadiationFactory::FlatPlateRadiationFactory (void)

Constructor for FlatPlateRadiationFactory.

Definition at line 65 of file flat_plate_radiation_factory.cc.

8.2.2.2 jeod::FlatPlateRadiationFactory::~FlatPlateRadiationFactory (void)

Destructor for FlatPlateRadiationFactory.

Definition at line 156 of file flat_plate_radiation_factory.cc.

```
8.2.2.3 jeod::FlatPlateRadiationFactory::FlatPlateRadiationFactory ( const FlatPlateRadiationFactory & rhs ) [private]
```

8.2.3 Member Function Documentation

```
8.2.3.1 InteractionFacet * jeod::FlatPlateRadiationFactory::create_facet ( Facet * facet, FacetParams * params )

[virtual]
```

Records the data for the Flat Plate Radiation Facet.

Returns

pointer to the interaction facet that this function creates.

Parameters

in	facet	pointer to the facet
in	params	pointer to the set of parameters for the facet.

Definition at line 79 of file flat plate radiation factory.cc.

References jeod::FlatPlateRadiationFacet::define_facet(), and jeod::RadiationMessages::invalid_setup_error.

8.2.3.2 bool jeod::FlatPlateRadiationFactory::is_correct_factory (Facet * facet) [virtual]

Tests to ensure that the factory can function on the facet as intended.

Returns

Boolean, is this the correct factory?

Parameters

in	facet	pointer to the facet being manipulated by the factory
----	-------	---

Definition at line 138 of file flat_plate_radiation_factory.cc.

8.2.3.3 FlatPlateRadiationFactory& jeod::FlatPlateRadiationFactory::operator= (const FlatPlateRadiationFactory & rhs) [private]

8.2.4 Friends And Related Function Documentation

- **8.2.4.1** void init_attrjeod__FlatPlateRadiationFactory() [friend]
- **8.2.4.2 friend class InputProcessor** [friend]

Definition at line 53 of file flat_plate_radiation_factory.hh.

The documentation for this class was generated from the following files:


- · flat_plate_radiation_factory.hh
- flat_plate_radiation_factory.cc

8.3 jeod::RadiationBaseFacet Class Reference

Generic type of facet for radiation pressure.

#include <radiation_base_facet.hh>

Inheritance diagram for jeod::RadiationBaseFacet:



Public Member Functions

RadiationBaseFacet ()

Construct a RadiationBaseFacet.

virtual ∼RadiationBaseFacet ()

Destructor for RadiationBaseFacet.

virtual void initialize (void)

initializes the base surface

virtual void interact_with_third_body (RadiationThirdBody *third_body, const bool calc_forces)

Calculation of force, torques and irradiance due to ThirdBody flux.

virtual void initialize_runtime_values (void)

To initialize the values during each update run.

• virtual void incident_radiation (const double flux_mag, const double flux_hat[3], const bool calc_forc)=0

Calculates the effect on the facet of the incident radiation.

Data Fields

· double albedo

Usable value of albedo, set to either albedo_IR or albedo_vis, depending on situation.

· double albedo vis

Fraction of incident visible radiation that is immediately reflected.

· double albedo_IR

Fraction of incident IR radiation that is immediately reflected.

· double diffuse

Fraction of reflected radiation that is reflected diffusely (balance reflected specularly)

ThermalFacetRider thermal

thermal characteristics of the facet.

• double cx area

cross-sectional area projected perpendicular to the radiation vector.

double areaxflux

product of momentum flux and cross-sectional area (cx_area).

· double areaxflux e

product of energy flux and cross-sectional area

• double F_absorption [3]

Force due to photon absorption from ONLY ONE source.

double F_specular [3]

Force due to photon specular reflection from ONLY ONE source.

double F_diffuse [3]

Force due to photon diffuse reflection from ONLY ONE source.

• double F_emission [3]

Force due to photon (thermal) emission.

Static Protected Attributes

static const double speed_of_light = 299792458.0
 Speed of light in vacuum.

Private Member Functions

- RadiationBaseFacet & operator= (const RadiationBaseFacet &rhs)
- RadiationBaseFacet (const RadiationBaseFacet &rhs)

Friends

- · class InputProcessor
- void init_attrjeod__RadiationBaseFacet ()

8.3.1 Detailed Description

Generic type of facet for radiation pressure.

Definition at line 51 of file radiation_base_facet.hh.

8.3.2 Constructor & Destructor Documentation

8.3.2.1 jeod::RadiationBaseFacet::RadiationBaseFacet (void)

Construct a RadiationBaseFacet.

Definition at line 59 of file radiation base facet.cc.

8.3.2.2 jeod::RadiationBaseFacet::~RadiationBaseFacet(void) [virtual]

Destructor for RadiationBaseFacet.

Definition at line 160 of file radiation_base_facet.cc.

8.3.2.3 jeod::RadiationBaseFacet::RadiationBaseFacet (const RadiationBaseFacet & rhs) [private]

8.3.3 Member Function Documentation

8.3.3.1 virtual void jeod::RadiationBaseFacet::incident_radiation (const double flux_mag, const double flux_hat[3], const bool calc_forc) [pure virtual]

Calculates the effect on the facet of the incident radiation.

Parameters

in	flux_mag	Magnitude of the incident flux
in	flux_hat	unit vector associated with the incident flux vector
in	calc_forc	true/false, do forces get calculated

 $Implemented\ in\ jeod:: Radiation Default Surface,\ and\ jeod:: Flat Plate Radiation Facet.$

 $Referenced\ by\ jeod:: Radiation Surface:: incident_radiation().$

8.3.3.2 void jeod::RadiationBaseFacet::initialize (void) [virtual]

initializes the base surface

Reimplemented in jeod::RadiationDefaultSurface, and jeod::RadiationFacet.

Definition at line 79 of file radiation_base_facet.cc.

References albedo, albedo_IR, albedo_vis, and jeod::RadiationMessages::invalid_setup_error.

Referenced by jeod::RadiationFacet::initialize(), and jeod::RadiationDefaultSurface::initialize().

8.3.3.3 void jeod::RadiationBaseFacet::initialize_runtime_values(void) [virtual]

To initialize the values during each update run.

Definition at line 147 of file radiation_base_facet.cc.

References F absorption, F diffuse, F specular, and thermal.

Referenced by jeod::RadiationSurface::initialize_runtime_values(), and jeod::RadiationPressure::update_default_surface().

8.3.3.4 void jeod::RadiationBaseFacet::interact_with_third_body (RadiationThirdBody * third_body_ptr, const bool calculate_forces) [virtual]

Calculation of force, torques and irradiance due to ThirdBody flux.

Parameters

in,out	third_body_ptr	Third body that emits radiation
in	calculate_forces	Calculate forces on this facet if true.

Definition at line 125 of file radiation base facet.cc.

References jeod::RadiationThirdBody::accumulate_rad_flux(), jeod::RadiationThirdBody::accumulate_refl_flux(), albedo, albedo_IR, and albedo_vis.

Referenced by jeod::RadiationSurface::interact_with_third_body(), and jeod::RadiationPressure::update_default_surface().

8.3.3.5 RadiationBaseFacet& jeod::RadiationBaseFacet::operator= (const RadiationBaseFacet & rhs)
[private]

8.3.4 Friends And Related Function Documentation

8.3.4.1 void init_attrjeod__RadiationBaseFacet() [friend]

8.3.4.2 friend class InputProcessor [friend]

Definition at line 53 of file radiation_base_facet.hh.

8.3.5 Field Documentation

8.3.5.1 double jeod::RadiationBaseFacet::albedo

Usable value of albedo, set to either albedo_IR or albedo_vis, depending on situation.

trick units(-)

Definition at line 63 of file radiation_base_facet.hh.

 $Referenced \ by jeod::RadiationFacet::define_facet_core(), jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), jeod::RadiationFacet::initialize(), jeod::RadiationDefaultSurface::RadiationDefaultSurface::RadiationDefaultSurface().$

8.3.5.2 double jeod::RadiationBaseFacet::albedo_IR

Fraction of incident IR radiation that is immediately reflected.

trick_units(-)

Definition at line 73 of file radiation_base_facet.hh.

Referenced by jeod::RadiationFacet::initialize(), initialize(), and interact_with_third_body().

8.3.5.3 double jeod::RadiationBaseFacet::albedo_vis

Fraction of incident visible radiation that is immediately reflected.

trick units(-)

Definition at line 68 of file radiation base facet.hh.

Referenced by jeod::RadiationFacet::initialize(), initialize(), and interact_with_third_body().

8.3.5.4 double jeod::RadiationBaseFacet::areaxflux

product of momentum flux and cross-sectional area (cx area).

Highly variable.trick_units(-)

Definition at line 103 of file radiation base facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), and jeod::RadiationDefaultSurface::RadiationDefaultSurface().

8.3.5.5 double jeod::RadiationBaseFacet::areaxflux_e

product of energy flux and cross-sectional area

trick units(-)

Definition at line 108 of file radiation_base_facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), and jeod::RadiationDefaultSurface::RadiationDefaultSurface().

8.3.5.6 double jeod::RadiationBaseFacet::cx_area

cross-sectional area projected perpendicular to the radiation vector.

For facets that have an orientation, this is intended to be a variable value, dependent upon the orientation. For spherical surfaces, this can be set at initialization.trick_units(m2)

Definition at line 94 of file radiation_base_facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), jeod::RadiationDefaultSurface::initialize(), and jeod::RadiationDefaultSurface::RadiationDefaultSurface().

8.3.5.7 double jeod::RadiationBaseFacet::diffuse

Fraction of reflected radiation that is reflected diffusely (balance reflected specularly)

trick_units(-)

Definition at line 79 of file radiation_base_facet.hh.

Referenced by jeod::RadiationFacet::define_facet_core(), jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), jeod::RadiationFacet::initialize(), jeod::RadiationDefaultSurface::RadiationDefaultSurface().

8.3.5.8 double jeod::RadiationBaseFacet::F_absorption[3]

Force due to photon absorption from ONLY ONE source.

trick_units(-)

Definition at line 113 of file radiation_base_facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), initialize_runtime_values(), jeod::FlatPlateRadiationFacet::radiation_pressure(), jeod::RadiationDefaultSurface(), and jeod::RadiationPressure::update_default_surface().

8.3.5.9 double jeod::RadiationBaseFacet::F_diffuse[3]

Force due to photon diffuse reflection from ONLY ONE source.

trick units(-)

Definition at line 123 of file radiation_base_facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), initialize_runtime_values(), jeod::FlatPlateRadiationFacet::radiation_pressure(), jeod::RadiationDefaultSurface::RadiationDefaultSurface(), and jeod::RadiationPressure::update_default_surface().

8.3.5.10 double jeod::RadiationBaseFacet::F_emission[3]

Force due to photon (thermal) emission.

trick_units(-)

Definition at line 128 of file radiation base facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::radiation_pressure(), and jeod::RadiationDefaultSurface::RadiationDefaultSurface().

8.3.5.11 double jeod::RadiationBaseFacet::F_specular[3]

Force due to photon specular reflection from ONLY ONE source.

trick units(-)

Definition at line 118 of file radiation base facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), initialize_runtime_values(), jeod::FlatPlateRadiationFacet::radiation_pressure(), jeod::RadiationDefaultSurface(), and jeod::RadiationPressure::update_default_surface().

8.3.5.12 const double jeod::RadiationBaseFacet::speed_of_light = 299792458.0 [static], [protected]

Speed of light in vacuum.

trick io(*o) trick units(m/s)

Definition at line 136 of file radiation base facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), jeod::RadiationDefaultSurface::incident_radiation(), and jeod::FlatPlateRadiationFacet::radiation_pressure().

8.3.5.13 ThermalFacetRider jeod::RadiationBaseFacet::thermal

thermal characteristics of the facet.

trick_units(-)

Definition at line 84 of file radiation_base_facet.hh.

Referenced by jeod::RadiationSurface::accumulate_thermal_sources(), jeod::RadiationDefaultSurface::add_thermal_integrator_to(), jeod::RadiationFacet::define_facet_core(), jeod::RadiationSurface::equalize_absorption_emission(), jeod::RadiationFacet::get_thermal_integrator(), jeod::FlatPlateRadiationFacet::incident_radiation(),

jeod::RadiationDefaultSurface::incident_radiation(), jeod::RadiationFacet::initialize(), jeod::RadiationSurface::initialize(), jeod::RadiationDefaultSurface::initialize(), jeod::FlatPlateRadiationFacet::initialize_geom(), initialize_runtime_values(), jeod::FlatPlateRadiationFacet::radiation_pressure(), jeod::RadiationSurface::thermal_integrator(), and jeod::RadiationDefaultSurface::thermal_update().

The documentation for this class was generated from the following files:


- · radiation base facet.hh
- · radiation_base_facet.cc

8.4 jeod::RadiationDefaultSurface Class Reference

The default spherical surface for radiation pressure.

```
#include <radiation_default_surface.hh>
```

Inheritance diagram for jeod::RadiationDefaultSurface:



Public Member Functions

· RadiationDefaultSurface ()

Constructor for RadiationDefaultSurface.

virtual ∼RadiationDefaultSurface ()

Destructor for RadiationDefaultSurface.

• virtual void initialize (void)

initializes the default surface

virtual void incident_radiation (const double flux_mag, const double flux_struc_hat[3], const bool calculate_forces)

Calculation of force and torque due to radiation pressure.

void thermal_update (void)

Test for necessity of maintaining thermal updates, and performs them as necessary.

void add_thermal_integrator_to (DynBody *dyn_body)

Adds the thermal integrator of this surface to the integration group of the DynBody.

void set_name (std::string name_in)

Setter for the name.

Data Fields

· double rad_coeff

The radiation-equivalent of a drag coefficient.

· double temperature

The value of the surface kinetic temperature.

std::string name

The name of the surface.

· double surface area

surface area of the default sphere.

Private Member Functions

- RadiationDefaultSurface & operator= (const RadiationDefaultSurface &rhs)
- RadiationDefaultSurface (const RadiationDefaultSurface &rhs)

Friends

- · class InputProcessor
- · void init attrieod RadiationDefaultSurface ()

Additional Inherited Members

8.4.1 Detailed Description

The default spherical surface for radiation pressure.

Definition at line 55 of file radiation_default_surface.hh.

8.4.2 Constructor & Destructor Documentation

8.4.2.1 jeod::RadiationDefaultSurface::RadiationDefaultSurface (void)

Constructor for RadiationDefaultSurface.

Definition at line 69 of file radiation default surface.cc.

References jeod::RadiationBaseFacet::albedo, jeod::RadiationBaseFacet::areaxflux, jeod::RadiationBaseFacet::areaxflux_e, jeod::RadiationBaseFacet::cx_area, jeod::RadiationBaseFacet::diffuse, jeod::RadiationBaseFacet::F_absorption, jeod::RadiationBaseFacet::F_emission, jeod::RadiationBaseFacet::F_e

8.4.2.2 jeod::RadiationDefaultSurface::~RadiationDefaultSurface(void) [virtual]

Destructor for RadiationDefaultSurface.

Definition at line 303 of file radiation_default_surface.cc.

 $\textbf{8.4.2.3} \quad \textbf{jeod::RadiationDefaultSurface::RadiationDefaultSurface (\ const \ RadiationDefaultSurface \& \textit{rhs} \) \quad \texttt{[private]}$

8.4.3 Member Function Documentation

8.4.3.1 void jeod::RadiationDefaultSurface::add_thermal_integrator_to ($DynBody*dyn_body$)

Adds the thermal integrator of this surface to the integration group of the DynBody.

Parameters

	in,out	dyn_body	Body associated with this thermal object.
- 4			·

Definition at line 293 of file radiation_default_surface.cc.

References jeod::RadiationBaseFacet::thermal.

8.4.3.2 void jeod::RadiationDefaultSurface::incident_radiation (const double flux_mag, const double flux_struc_hat[3], const bool calculate_forces) [virtual]

Calculation of force and torque due to radiation pressure.

Assumptions and Limitations

- · Assumes that flux magnitude is positive.
- · Will only be called if flux magnitude is positive.
- · Assumes spherical surface.

Parameters

in	flux_mag	the magnitude of the incident flux
in	flux_struc_hat	the unit vector in structural frame for the flux vector.
in	calculate_forces	boolean indicating whether to calculate forces.

Implements jeod::RadiationBaseFacet.

Definition at line 222 of file radiation_default_surface.cc.

References jeod::RadiationBaseFacet::albedo, jeod::RadiationBaseFacet::areaxflux, jeod::RadiationBaseFacet::areaxflux_e, jeod::RadiationBaseFacet::cx_area, jeod::RadiationBaseFacet::diffuse, jeod::RadiationBaseFacet::F_absorption, jeod::RadiationBaseFacet::F_geod::RadiationBaseFacet::F_specular, jeod::RadiationBaseFacet::speed of light, and jeod::RadiationBaseFacet::thermal.

Referenced by jeod::RadiationPressure::update_default_surface().

8.4.3.3 void jeod::RadiationDefaultSurface::initialize (void) [virtual]

initializes the default surface

Reimplemented from jeod::RadiationBaseFacet.

Definition at line 93 of file radiation default surface.cc.

References jeod::RadiationBaseFacet::albedo, jeod::RadiationBaseFacet::cx_area, jeod::RadiationBaseFacet::diffuse, jeod::RadiationBaseFacet::initialize(), jeod::RadiationMessages::invalid_setup_error, jeod::RadiationMessages::operational_setup_error, rad_coeff, surface_area, temperature, and jeod::RadiationBaseFacet::thermal.

Referenced by jeod::RadiationPressure::initialize().

8.4.3.4 RadiationDefaultSurface& jeod::RadiationDefaultSurface::operator=(const RadiationDefaultSurface & rhs)
[private]

8.4.3.5 void jeod::RadiationDefaultSurface::set_name(std::string name_in) [inline]

Setter for the name.

Definition at line 126 of file radiation_default_surface.hh.

8.4.3.6 void jeod::RadiationDefaultSurface::thermal_update (void)

Test for necessity of maintaining thermal updates, and performs them as necessary.

Definition at line 274 of file radiation_default_surface.cc.

References temperature, and jeod::RadiationBaseFacet::thermal.

Referenced by jeod::RadiationPressure::update_default_surface().

8.4.4 Friends And Related Function Documentation

8.4.4.1 void init_attrjeod__RadiationDefaultSurface() [friend]

8.4.4.2 friend class InputProcessor [friend]

Definition at line 57 of file radiation_default_surface.hh.

8.4.5 Field Documentation

8.4.5.1 std::string jeod::RadiationDefaultSurface::name

The name of the surface.

This is optional.trick units(-)

Definition at line 85 of file radiation_default_surface.hh.

8.4.5.2 double jeod::RadiationDefaultSurface::rad_coeff

The radiation-equivalent of a drag coefficient.

It is the value by which the area must be multiplied in order to generate the same force if the reflecting surface were considered a perfectly absorbing surface. For a sphere, this has a value between 1.0 (perfectly absorbing, or perfect specular reflection) to 1.4444 (all diffuse reflection). Specify either: rad_coeff OR (albedo AND diffuse). NOTE 1 - this value is used at initialization only; changes to its value mid-simulation cannot be effected. NOTE 2 - the values albedo and diffuse are inherited from RadiationBaseFacet.trick_units(-)

Definition at line 75 of file radiation_default_surface.hh.

Referenced by initialize(), and RadiationDefaultSurface().

8.4.5.3 double jeod::RadiationDefaultSurface::surface_area

surface area of the default sphere.

trick_units(m2)

Definition at line 95 of file radiation_default_surface.hh.

Referenced by initialize(), and RadiationDefaultSurface().

8.4.5.4 double jeod::RadiationDefaultSurface::temperature

The value of the surface kinetic temperature.

trick units(K)

Definition at line 80 of file radiation_default_surface.hh.

Referenced by initialize(), RadiationDefaultSurface(), and thermal_update().

The documentation for this class was generated from the following files:


- radiation_default_surface.hh
- radiation_default_surface.cc

8.5 jeod::RadiationFacet Class Reference

Generic type of facet for radiation pressure.

#include <radiation_facet.hh>

Inheritance diagram for jeod::RadiationFacet:



Public Member Functions

• RadiationFacet ()

Constructor for Radiationfacet.

virtual ∼RadiationFacet ()

Destructor for RadiationFacet.

virtual void radiation_pressure ()=0

Calculates the effect of radiation pressure on the facet.

virtual void initialize_geom (double cg[3])=0

Initialize the facet geometry.

• virtual void initialize ()

Run sanity checks on input variables.

• void define_facet_core (Facet *facet, ThermalFacetRider &facet_thermal, RadiationParams *params)

Defines the inherent facet values.

ThermalIntegrableObject & get_thermal_integrator ()

Get the integrator for thermal characteristics.

Data Fields

• double crot_to_cp [3]

position of center of pressure w.r.t.

• double * center_pressure

Center of pressure (in structural frame).

Static Protected Attributes

static const double two_thirds = 2.0 / 3.0
 quite literally, 2/3.

Private Member Functions

- RadiationFacet & operator= (const RadiationFacet &rhs)
- RadiationFacet (const RadiationFacet &rhs)

Friends

- class InputProcessor
- void init_attrjeod__RadiationFacet ()

8.5.1 Detailed Description

Generic type of facet for radiation pressure.

Definition at line 53 of file radiation_facet.hh.

8.5.2 Constructor & Destructor Documentation

8.5.2.1 jeod::RadiationFacet::RadiationFacet (void)

Constructor for Radiationfacet.

Definition at line 61 of file radiation_facet.cc.

References center_pressure, and crot_to_cp.

8.5.2.2 jeod::RadiationFacet::~RadiationFacet(void) [virtual]

Destructor for RadiationFacet.

Definition at line 123 of file radiation_facet.cc.

8.5.2.3 jeod::RadiationFacet::RadiationFacet (const RadiationFacet & rhs) [private]

8.5.3 Member Function Documentation

8.5.3.1 void jeod::RadiationFacet::define_facet_core (Facet * facet, ThermalFacetRider & facet_thermal, RadiationParams * params)

Defines the inherent facet values.

Parameters

in	facet	pointer to the facet
in	facet_thermal	reference to the thermal components of the facet.
in	params	pointer to the list of material parameters for the facet.

Definition at line 102 of file radiation_facet.cc.

References jeod::RadiationParams::albedo, jeod::RadiationBaseFacet::albedo, jeod::RadiationParams::diffuse, jeod::RadiationBaseFacet::diffuse, jeod::RadiationParams::thermal, and jeod::RadiationBaseFacet::thermal.

8.5.3.2 ThermalIntegrableObject& jeod::RadiationFacet::get_thermal_integrator() [inline]

Get the integrator for thermal characteristics.

Returns

Integrable object that integrates temperature.

Definition at line 120 of file radiation facet.hh.

References jeod::RadiationBaseFacet::thermal.

8.5.3.3 void jeod::RadiationFacet::initialize (void) [virtual]

Run sanity checks on input variables.

Reimplemented from jeod::RadiationBaseFacet.

Definition at line 72 of file radiation_facet.cc.

References jeod::RadiationBaseFacet::albedo, jeod::RadiationBaseFacet::albedo_IR, jeod::RadiationBaseFacet::albedo_vis, jeod::RadiationBaseFacet::diffuse, jeod::RadiationBaseFacet::initialize(), jeod::RadiationMessages::invalid_setup_error, and jeod::RadiationBaseFacet::thermal.

Referenced by jeod::FlatPlateRadiationFacet::initialize_geom().

8.5.3.4 virtual void jeod::RadiationFacet::initialize_geom (double cg[3]) [pure virtual]

Initialize the facet geometry.

Parameters

```
cg Center of mass.
```

Implemented in jeod::FlatPlateRadiationFacet.

Referenced by jeod::RadiationSurface::initialize().

```
8.5.3.5 RadiationFacet&jeod::RadiationFacet::operator=(const RadiationFacet&rhs) [private]
```

```
8.5.3.6 virtual void jeod::RadiationFacet::radiation_pressure() [pure virtual]
```

Calculates the effect of radiation pressure on the facet.

Implemented in jeod::FlatPlateRadiationFacet.

Referenced by jeod::RadiationSurface::radiation_pressure().

8.5.4 Friends And Related Function Documentation

```
8.5.4.1 void init_attrjeod__RadiationFacet() [friend]
```

 $\textbf{8.5.4.2} \quad \textbf{friend class InputProcessor} \quad [\, \texttt{friend} \,]$

Definition at line 55 of file radiation facet.hh.

8.5.5 Field Documentation

8.5.5.1 double* jeod::RadiationFacet::center_pressure

Center of pressure (in structural frame).

Potentially variable, depending on the topology of the facet. For a flat plate facet, this just points to the position found in FlatPlatetrick units(m)

Definition at line 74 of file radiation facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::define_facet(), jeod::FlatPlateRadiationFacet::initialize_geom(), and RadiationFacet().

8.5.5.2 double jeod::RadiationFacet::crot to cp[3]

position of center of pressure w.r.t.

center of rotation (usually center of mass, or center of gravity), expressed in structural reference frame. Potentially variable, depending on the topology of the facet and the configuration of the vehicle.trick_units(m)

Definition at line 67 of file radiation_facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::initialize_geom(), jeod::FlatPlateRadiationFacet::radiation_pressure(), and RadiationFacet().

8.5.5.3 const double jeod::RadiationFacet::two_thirds = 2.0/3.0 [static], [protected]

quite literally, 2/3.

Occurs frequently with diffuse reflection and emission, so it is calculated once.trick_io(*o) trick_units(-)

Definition at line 84 of file radiation facet.hh.

Referenced by jeod::FlatPlateRadiationFacet::incident_radiation(), and jeod::FlatPlateRadiationFacet::radiation_pressure().

The documentation for this class was generated from the following files:

- · radiation_facet.hh
- · radiation_facet.cc

8.6 jeod::RadiationMessages Class Reference

Provides error messages.

```
#include <radiation_messages.hh>
```

Static Public Attributes

• static char const * incomplete setup error

The setup was not fully defined.

• static char const * invalid_setup_error

The setup is invalid.

static char const * operational_setup_error

Something internal went wrong in the setup methods without obvious user error.

• static char const * invalid_function_call

A function was called before it was fully implemented.

• static char const * unknown_numerical_error

Something went horribly wrong.

Private Member Functions

- RadiationMessages (void)
- RadiationMessages (const RadiationMessages &)
- RadiationMessages & operator= (const RadiationMessages &)

Friends

- · class InputProcessor
- void init_attrjeod__RadiationMessages ()

8.6.1 Detailed Description

Provides error messages.

Definition at line 52 of file radiation_messages.hh.

```
8.6.2 Constructor & Destructor Documentation
```

```
8.6.2.1 jeod::RadiationMessages::RadiationMessages ( void ) [private]
```

- **8.6.2.2** jeod::RadiationMessages::RadiationMessages (const RadiationMessages &) [private]
- 8.6.3 Member Function Documentation
- **8.6.3.1** RadiationMessages& jeod::RadiationMessages::operator=(const RadiationMessages &) [private]
- 8.6.4 Friends And Related Function Documentation

```
8.6.4.1 void init_attrjeod__RadiationMessages() [friend]
```

8.6.4.2 friend class InputProcessor [friend]

Definition at line 55 of file radiation messages.hh.

8.6.5 Field Documentation

```
8.6.5.1 char const * jeod::RadiationMessages::incomplete_setup_error [static]
```

Initial value:

```
"interactions/radiation_pressure/" "incomplete_setup_error"
```

The setup was not fully defined.

trick_units(-)

Definition at line 64 of file radiation_messages.hh.

 $Referenced\ by\ jeod:: Radiation Pressure:: add_third_body(),\ and\ jeod:: Radiation Source:: initialize().$

```
\textbf{8.6.5.2} \quad \textbf{char const} * \textbf{jeod::RadiationMessages::invalid\_function\_call} \quad \texttt{[static]}
```

Initial value:

```
"interactions/radiation_pressure/" "invalid_function_call"
```

A function was called before it was fully implemented.

trick_units(-)

Definition at line 77 of file radiation_messages.hh.

Referenced by jeod::RadiationPressure::find_third_body(), jeod::RadiationPressure::set_third_body_active(), and jeod::RadiationPressure::set_third_body_inactive().

8.6.5.3 char const * jeod::RadiationMessages::invalid_setup_error [static]

Initial value:

```
"interactions/radiation_pressure/" "invalid_setup_error"
```

The setup is invalid.

trick_units(-)

Definition at line 68 of file radiation_messages.hh.

Referenced by jeod::RadiationSurfaceFactory::add_facet_params(), jeod::RadiationPressure::add_third_body(), jeod::RadiationSurface::allocate_interaction_facet(), jeod::RadiationThirdBody::calculate_shadow(), jeod::RadiationThirdBody::calculate_shadow(), jeod::RadiationThirdBody::create_facet(), jeod::RadiationFactory::create_facet(), jeod::RadiationFacet::initialize(), jeod::RadiationDefaultSurface::initialize(), jeod::RadiationThirdBody::process_third_body(), and jeod::RadiationThirdBody::update_third_body_state().

8.6.5.4 char const * jeod::RadiationMessages::operational_setup_error [static]

Initial value:

```
"interactions/radiation_pressure/" "operational_setup_error"
```

Something internal went wrong in the setup methods without obvious user error.

trick units(-)

Definition at line 73 of file radiation_messages.hh.

Referenced by jeod::RadiationSurface::allocate_array(), jeod::RadiationSurface::allocate_interaction_facet(), jeod::RadiationSurface::initialize(), jeod::RadiationDefaultSurface::initialize(), and jeod::RadiationThirdBody::process_third_body().

8.6.5.5 char const * jeod::RadiationMessages::unknown_numerical_error [static]

Initial value:

```
"interactions/radiation_pressure/" "unknown_numerical_error"
```

Something went horribly wrong.

trick units(-)

Definition at line 82 of file radiation_messages.hh.

Referenced by jeod::FlatPlateRadiationFacet::radiation pressure().

The documentation for this class was generated from the following files:


- · radiation_messages.hh
- · radiation_messages.cc

8.7 jeod::RadiationParams Class Reference

Provides a parameter list to each facet, based on the facet material properties.

```
#include <radiation_params.hh>
```

Inheritance diagram for jeod::RadiationParams:



Public Member Functions

· RadiationParams ()

Constructor for RadiationParams.

virtual ∼RadiationParams ()

Destructor for RadiationParams.

Data Fields

· double albedo

Fraction of incident radiation that is immediately reflected.

· double diffuse

Fraction of reflected radiation that is reflected diffusely (balance reflected specularly)

· ThermalParams thermal

Additional thermal parameters.

Private Member Functions

- RadiationParams & operator= (const RadiationParams &rhs)
- · RadiationParams (const RadiationParams &rhs)

Friends

- · class InputProcessor
- void init_attrjeod__RadiationParams ()

8.7.1 Detailed Description

Provides a parameter list to each facet, based on the facet material properties.

Definition at line 48 of file radiation_params.hh.

8.7.2 Constructor & Destructor Documentation

8.7.2.1 jeod::RadiationParams::RadiationParams (void)

Constructor for RadiationParams.

Definition at line 44 of file radiation_params.cc.

References albedo, and diffuse.

8.7.2.2 jeod::RadiationParams::~RadiationParams(void) [virtual]

Destructor for RadiationParams.

Definition at line 54 of file radiation_params.cc.

```
8.7.2.3 jeod::RadiationParams::RadiationParams ( const RadiationParams & rhs ) [private]
```

8.7.3 Member Function Documentation

8.7.3.1 RadiationParams& jeod::RadiationParams::operator=(const RadiationParams & rhs) [private]

8.7.4 Friends And Related Function Documentation

```
8.7.4.1 void init_attrjeod__RadiationParams() [friend]
```

8.7.4.2 friend class InputProcessor [friend]

Definition at line 50 of file radiation_params.hh.

8.7.5 Field Documentation

8.7.5.1 double jeod::RadiationParams::albedo

Fraction of incident radiation that is immediately reflected.

trick units(-)

Definition at line 58 of file radiation_params.hh.

Referenced by jeod::RadiationFacet::define_facet_core(), and RadiationParams().

8.7.5.2 double jeod::RadiationParams::diffuse

Fraction of reflected radiation that is reflected diffusely (balance reflected specularly)

trick_units(-)

Definition at line 64 of file radiation params.hh.

Referenced by jeod::RadiationFacet::define_facet_core(), and RadiationParams().

8.7.5.3 ThermalParams jeod::RadiationParams::thermal

Additional thermal parameters.

trick_units(-)

Definition at line 69 of file radiation params.hh.

Referenced by jeod::RadiationFacet::define_facet_core().

The documentation for this class was generated from the following files:

- radiation_params.hh
- · radiation_params.cc

8.8 jeod::RadiationPressure Class Reference

Radiation pressure top-level definition.

```
#include <radiation_pressure.hh>
```

Public Member Functions

• RadiationPressure ()

Constructor for RadiationPressure.

• virtual \sim RadiationPressure ()

Destructor for RadiationPressure.

void initialize (DynManager &dyn_manager, RadiationSurface *surf_ptr, double center_grav[3])

Initialize the radiation pressure model when using a RadiationSurface (i.e.

void initialize (DynManager &dyn_manager, RadiationDefaultSurface *surf_ptr)

Initialize the radiation pressure model when using a RadiationDefaultSurface (i.e.

• void update (RefFrame &vehicle_structural_frame, double center_grav[3], double scale_factor, double time)

Updates the model at each time step.

void add_third_body (RadiationThirdBody *third_body_ptr)

Adds a third body to the vector storage of third bodies.

void set_third_body_active (const char *third_body_name)

Sets a Third Body to be active when it previously was not.

void set_third_body_inactive (const char *third_body_name)

Sets a Third Body to be inactive when it previously was not.

• void set_calculate_forces (bool calc_forces)

Sets the value calculate_forces.

Data Fields

· bool active

Is radiation pressure desired?

• double force [3]

Net force due to radiation.

• double torque [3]

Net torque due to radiation.

· double illum_factor

fraction of primary flux that is not eclipsed

• RadiationSource source

Collection of data for radiation source.

• ThermalModelRider thermal

Rider to allow dynamic thermal variation on facets in this model.

Protected Member Functions

void update_default_surface (void)

Used to update the model when the surface is a default surface.

void update_facet_surface (void)

Used to update the model when the surface comprises facets.

void initialize_environment (DynManager *dyn_mgr_ptr)

Initializes the source and third bodies.

· void third body adjustments (double time, RefFrame &vehicle structural frame)

Used to modify the flux for shadowing.

• int find third body (const char *third body name)

Finds the index of a third body based on its name.

Protected Attributes

· bool initialized

Has model been initialized?

· bool calculate forces

Flag to indicate whether forces and torques should be calculated.

· bool third bodies active

Flag indicates whether there are any of the third bodies currently active.

· unsigned int num third bodies

Number of ThirdBodies available.

JeodPointerVector

< RadiationThirdBody >::type third_bodies

Planetary bodies that provide shadowing or indirect, reflected, illumination.

RadiationSurface * surface ptr

The surface over which the radiation pressure will be collected.

RadiationDefaultSurface * default surface ptr

If no surface is defined, use a DefaultSurface; this is the pointer to that default surface,.

DynManager * dyn_manager_ptr

Pointer to the Dynamics Manager.

Private Member Functions

- RadiationPressure (const RadiationPressure &)
- RadiationPressure & operator= (const RadiationPressure &)

Friends

- · class InputProcessor
- void init_attrjeod__RadiationPressure ()

8.8.1 Detailed Description

Radiation pressure top-level definition.

Definition at line 58 of file radiation_pressure.hh.

8.8.2 Constructor & Destructor Documentation

8.8.2.1 jeod::RadiationPressure::RadiationPressure (void)

Constructor for RadiationPressure.

Definition at line 72 of file radiation_pressure.cc.

References active, calculate_forces, default_surface_ptr, dyn_manager_ptr, force, illum_factor, initialized, num_third bodies, surface ptr, third bodies, third bodies active, and torque.

8.8.2.2 jeod::RadiationPressure::~RadiationPressure(void) [virtual]

Destructor for RadiationPressure.

Definition at line 396 of file radiation_pressure.cc.

References third_bodies.

8.8.2.3 jeod::RadiationPressure::RadiationPressure (const RadiationPressure &) [private]

8.8.3 Member Function Documentation

8.8.3.1 void jeod::RadiationPressure::add_third_body (RadiationThirdBody * third_body_ptr)

Adds a third body to the vector storage of third bodies.

Parameters

		maintainte ThindDade.
ın	third_body_ptr	pointer to ThirdBody

Definition at line 186 of file radiation_pressure.cc.

References jeod::RadiationThirdBody::active, dyn_manager_ptr, jeod::RadiationThirdBody::get_added_to_model(), jeod::RadiationMessages::incomplete_setup_error, jeod::RadiationThirdBody::initialize(), initialized, jeod::RadiationMessages::invalid_setup_error, jeod::RadiationThirdBody::name, num_third_bodies, jeod::RadiationThirdBody::set_added_to_model(), third_bodies, and third_bodies_active.

Referenced by initialize().

8.8.3.2 int jeod::RadiationPressure::find third body (const char * third body name) [protected]

Finds the index of a third body based on its name.

Returns

void

Parameters

in	third_body	Name of ThirdBody
	name	

Definition at line 360 of file radiation_pressure.cc.

References jeod::RadiationMessages::invalid function call, num third bodies, and third bodies.

Referenced by set third body active(), and set third body inactive().

8.8.3.3 void jeod::RadiationPressure::initialize (DynManager & dyn_mgr, RadiationSurface * surf_ptr, double center_grav[3])

Initialize the radiation pressure model when using a RadiationSurface (i.e.

with facets).

Parameters

in	dyn_mgr	The dynamics manager
in	surf_ptr	pointer to the radiation surface
in	center_grav	position of center of mass
		Units: M

Definition at line 79 of file radiation_pressure__surface_model.cc.

References add_third_body(), dyn_manager_ptr, jeod::RadiationSurface::initialize(), initialize_environment(), jeod::RadiationSource::num_bodies, jeod::RadiationSource::shadow_geometry, source, surface_ptr, thermal, third_bodies, and jeod::RadiationSource::third_body.

8.8.3.4 void jeod::RadiationPressure::initialize (DynManager & dyn_mgr, RadiationDefaultSurface * surf_ptr)

Initialize the radiation pressure model when using a RadiationDefaultSurface (i.e.

spherical, uniform properties.)

Parameters

in	dyn_mgr	The dynamics manager
in	surf_ptr	pointer to the radiation surface

Definition at line 75 of file radiation pressure default surface.cc.

References add_third_body(), default_surface_ptr, dyn_manager_ptr, jeod::RadiationDefaultSurface::initialize(), initialize_environment(), jeod::RadiationSource::num_bodies, jeod::RadiationSource::shadow_geometry, source, third bodies, and jeod::RadiationSource::third body.

8.8.3.5 void jeod::RadiationPressure::initialize_environment(DynManager * dyn_mgr_ptr) [protected]

Initializes the source and third bodies.

Parameters

in	dyn_mgr_ptr	The dynamics manager

Definition at line 97 of file radiation pressure.cc.

References jeod::RadiationSource::initialize(), initialized, num_third_bodies, source, and third_bodies.

Referenced by initialize().

- **8.8.3.6** RadiationPressure& jeod::RadiationPressure::operator=(const RadiationPressure &) [private]
- 8.8.3.7 void jeod::RadiationPressure::set_calculate_forces (bool value)

Sets the value calculate forces.

Parameters

in	value	whether forces are needed

Definition at line 381 of file radiation pressure.cc.

References calculate_forces, force, and torque.

8.8.3.8 void jeod::RadiationPressure::set_third_body_active (const char * third_body_name)

Sets a Third Body to be active when it previously was not.

Parameters

in	third_body	Name of ThirdBody
	name	

Definition at line 282 of file radiation pressure.cc.

References active, dyn_manager_ptr, find_third_body(), jeod::RadiationMessages::invalid_function_call, third_bodies, and third_bodies_active.

8.8.3.9 void jeod::RadiationPressure::set_third_body_inactive (const char * third_body_name)

Sets a Third Body to be inactive when it previously was not.

Parameters

Generated on Wed Jun 1 2022 12:07:44 for RadiationPressureModel by Doxygen

in	third_body	Name of ThirdBody
	name	

Definition at line 319 of file radiation pressure.cc.

References active, dyn_manager_ptr, find_third_body(), jeod::RadiationMessages::invalid_function_call, num_third_bodies, third_bodies, and third_bodies_active.

8.8.3.10 void jeod::RadiationPressure::third_body_adjustments (double *real_time*, RefFrame & *veh_struc_frame*)

[protected]

Used to modify the flux for shadowing.

Parameters

in	real_time	The current time, e.g. TAI or UT1.
		Units: s

Definition at line 162 of file radiation_pressure.cc.

References active, jeod::RadiationSource::flux_inertial, jeod::RadiationSource::flux_mag, jeod::RadiationSource::flux_struc, illum_factor, num_third_bodies, source, and third_bodies.

Referenced by update().

8.8.3.11 void jeod::RadiationPressure::update (RefFrame & veh_struc_frame, double center_grav[3], double scale_factor, double real_time)

Updates the model at each time step.

Parameters

in	veh_struc_frame	The vehicle structural reference frame.
in	center_grav	position of center of mass
		Units: M
in	scale_factor	the scale between the simulator time and the dynamic time.
in	real_time	The current time, e.g. TAI or UT1.
		Units: s

Definition at line 118 of file radiation_pressure.cc.

References active, jeod::RadiationSource::calculate_flux(), source, surface_ptr, third_bodies_active, third_body_adjustments(), update_default_surface(), and update_facet_surface().

8.8.3.12 void jeod::RadiationPressure::update_default_surface(void) [protected]

Used to update the model when the surface is a default surface.

Definition at line 100 of file radiation pressure default surface.cc.

References active, calculate_forces, default_surface_ptr, jeod::RadiationBaseFacet::F_absorption, jeod::RadiationBaseFacet::F_diffuse, jeod::RadiationBaseFacet::F_specular, jeod::RadiationSource::flux_mag, jeod::RadiationSource::flux_struc_hat, force, jeod::RadiationDefaultSurface::incident_radiation(), jeod::RadiationBaseFacet::initialize_runtime_values(), jeod::RadiationBaseFacet::interact_with_third_body(), num_third_bodies, source, jeod::RadiationDefaultSurface::thermal_update(), third_bodies, and torque.

Referenced by update().

8.8.3.13 void jeod::RadiationPressure::update_facet_surface(void) [protected]

Used to update the model when the surface comprises facets.

Definition at line 115 of file radiation_pressure__surface_model.cc.

References active, calculate_forces, jeod::RadiationSurface::equalize_absorption_emission(), jeod::RadiationSource::flux_mag, jeod::RadiationSource::flux_struc_hat, force, jeod::RadiationSurface::force, jeod::RadiationSurface::incident_radiation(), jeod::RadiationSurface::initialize_runtime_values(), jeod::RadiationSurface::interact_with_third_body(), num_third_bodies, jeod::RadiationSurface::radiation_pressure(), source, surface_ptr, thermal, third_bodies, torque, and jeod::RadiationSurface::torque.

Referenced by update().

8.8.4 Friends And Related Function Documentation

8.8.4.1 void init_attrjeod__RadiationPressure() [friend]

8.8.4.2 friend class InputProcessor [friend]

Definition at line 60 of file radiation pressure.hh.

8.8.5 Field Documentation

8.8.5.1 bool jeod::RadiationPressure::active

Is radiation pressure desired?

trick_units(-)

Definition at line 68 of file radiation pressure.hh.

Referenced by RadiationPressure(), set_third_body_active(), set_third_body_inactive(), third_body_adjustments(), update(), update_default_surface(), and update_facet_surface().

8.8.5.2 bool jeod::RadiationPressure::calculate_forces [protected]

Flag to indicate whether forces and torques should be calculated.

trick_units(-)

Definition at line 105 of file radiation_pressure.hh.

Referenced by RadiationPressure(), set calculate forces(), update default surface(), and update facet surface().

8.8.5.3 RadiationDefaultSurface* jeod::RadiationPressure::default_surface ptr [protected]

If no surface is defined, use a DefaultSurface; this is the pointer to that default surface,.

trick units(-)

Definition at line 135 of file radiation_pressure.hh.

Referenced by initialize(), RadiationPressure(), and update_default_surface().

8.8.5.4 DynManager* jeod::RadiationPressure::dyn_manager_ptr [protected]

Pointer to the Dynamics Manager.

trick_units(-)

Definition at line 140 of file radiation_pressure.hh.

Referenced by add_third_body(), initialize(), RadiationPressure(), set_third_body_active(), and set_third_body_inactive().

8.8.5.5 double jeod::RadiationPressure::force[3]

Net force due to radiation.

trick units(N)

Definition at line 73 of file radiation_pressure.hh.

Referenced by RadiationPressure(), set_calculate_forces(), update_default_surface(), and update_facet_surface().

8.8.5.6 double jeod::RadiationPressure::illum_factor

fraction of primary flux that is not eclipsed

trick units(-)

Definition at line 83 of file radiation_pressure.hh.

Referenced by RadiationPressure(), and third_body_adjustments().

8.8.5.7 bool jeod::RadiationPressure::initialized [protected]

Has model been initialized?

trick units(-)

Definition at line 100 of file radiation_pressure.hh.

Referenced by add_third_body(), initialize_environment(), and RadiationPressure().

8.8.5.8 unsigned int jeod::RadiationPressure::num_third_bodies [protected]

Number of ThirdBodies available.

trick_units(count)

Definition at line 116 of file radiation_pressure.hh.

Referenced by add_third_body(), find_third_body(), initialize_environment(), RadiationPressure(), set_third_body_inactive(), third_body_adjustments(), update_default_surface(), and update_facet_surface().

8.8.5.9 RadiationSource jeod::RadiationPressure::source

Collection of data for radiation source.

trick_units(-)

Definition at line 88 of file radiation_pressure.hh.

Referenced by initialize(), initialize_environment(), third_body_adjustments(), update(), update_default_surface(), and update_facet_surface().

8.8.5.10 RadiationSurface* jeod::RadiationPressure::surface_ptr [protected]

The surface over which the radiation pressure will be collected.

If this is NULL, use the default radiation surface (which is a whole separate entity from a RadiationSurface.trick_-units(-)

Definition at line 129 of file radiation_pressure.hh.

Referenced by initialize(), RadiationPressure(), update(), and update_facet_surface().

8.8.5.11 ThermalModelRider jeod::RadiationPressure::thermal

Rider to allow dynamic thermal variation on facets in this model.

trick units(-)

Definition at line 93 of file radiation pressure.hh.

Referenced by initialize(), and update_facet_surface().

8.8.5.12 JeodPointerVector < RadiationThirdBody >::type jeod::RadiationPressure::third_bodies [protected]

Planetary bodies that provide shadowing or indirect, reflected, illumination.

trick_io(**)

Definition at line 122 of file radiation pressure.hh.

Referenced by add_third_body(), find_third_body(), initialize(), initialize_environment(), RadiationPressure(), set_third_body_active(), set_third_body_inactive(), third_body_adjustments(), update_default_surface(), update_facet_surface(), and ~RadiationPressure().

8.8.5.13 bool jeod::RadiationPressure::third_bodies_active [protected]

Flag indicates whether there are any of the third bodies currently active.

trick_units(-)

Definition at line 111 of file radiation_pressure.hh.

Referenced by add_third_body(), RadiationPressure(), set_third_body_active(), set_third_body_inactive(), and update().

8.8.5.14 double jeod::RadiationPressure::torque[3]

Net torque due to radiation.

trick units(N*m)

Definition at line 78 of file radiation_pressure.hh.

Referenced by RadiationPressure(), set_calculate_forces(), update_default_surface(), and update_facet_surface().

The documentation for this class was generated from the following files:

- · radiation pressure.hh
- radiation_pressure.cc
- radiation_pressure__default_surface.cc
- radiation_pressure__surface_model.cc

8.9 jeod::RadiationSource Class Reference

Provides information on the source of the incident radiation.

```
#include <radiation_source.hh>
```

Public Types

 enum OldShadowGeometry { Cylindrical = 0, Cyl = 1, Conical = 2, Con = 3 } distinguishes between conical and cylindrical shadowing.

Public Member Functions

RadiationSource ()

Constructor for RadiationSource.

virtual ∼RadiationSource ()

destructor for RadiationSource

virtual void initialize (DynManager *dyn_manager_ptr)

Initializes the source object for use in the Radiation Pressure model.

• virtual void calculate_flux (RefFrame &veh_struc_frame, const double center_grav[3])

calculates the flux vector from the vehicle's position.

void set_name (std::string name_in)

Setter for the name.

Data Fields

· const double solar luminosity

Solar Luminosity.

· const double solar_radius

Mean solar radius.

std::string name

The name of the source of the illumination (usually Sun)

• double flux_hat [3]

(inertial) unit vector associated with primary radiative flux.

double flux_mag

magnitude of principle radiative flux vector

• double d_source_to_cg

distance from source to vehicle cg.

· double luminosity

Luminosity of primary source.

· double radius

Radius of primary source.

• double flux_inertial [3]

(N/M/s) Power per unit area in the inertial reference frame

• double flux_struc [3]

(N/M*s) Power per unit area in the vehicle structural reference frame

• double flux_struc_hat [3]

Unit vector representing flux vector in the vehicle structural reference frame.

• double inertial_cg [3]

vehicle cg position w.r.t vehicle strucural origin, expressed in inertial RF.

double source_to_cg [3]

vehicle cg position relative to the source

• double source_to_struc_origin [3]

vehicle struc frame origin position relative to source.

bool multiple_shadow_bodies

flags that more than one body are casting shadows on the vehicle.

• RefFrame * inertial_frame_ptr

the inertial reference frame associated with this source

· bool bodies_active

can there be 3rd-body interference, either shadowing or reflection.

unsigned int num_bodies

number of ThirdBodies available.

RadiationThirdBody ** third_body

Planetary bodies that provide shadowing or indirect, reflected, illumination.

OldShadowGeometry shadow geometry

Flag indicating cylindrical / conical shadow geometry.

Private Member Functions

- RadiationSource (const RadiationSource &)
- RadiationSource & operator= (const RadiationSource &)

Friends

- · class InputProcessor
- void init_attrjeod__RadiationSource ()

8.9.1 Detailed Description

Provides information on the source of the incident radiation.

Definition at line 57 of file radiation source.hh.

8.9.2 Member Enumeration Documentation

8.9.2.1 enum jeod::RadiationSource::OldShadowGeometry

distinguishes between conical and cylindrical shadowing.

NOTE this is provided for backward-compatibility and should not be used.

Enumerator

Cylindrical planet casts a cylindrical shadow

Cyl planet casts a cylindrical shadow

Conical planet casts a conical shadow

Con planet casts a conical shadow

Definition at line 174 of file radiation source.hh.

8.9.3 Constructor & Destructor Documentation

8.9.3.1 jeod::RadiationSource::RadiationSource (void)

Constructor for RadiationSource.

Definition at line 66 of file radiation_source.cc.

References d_source_to_cg, flux_hat, flux_inertial, flux_mag, flux_struc, flux_struc_hat, inertial_cg, inertial_frame_ptr, luminosity, multiple_shadow_bodies, name, radius, solar_luminosity, solar_radius, source_to_cg, and source_to_struc_origin.

8.9.3.2 jeod::RadiationSource:: \sim RadiationSource (void) [virtual]

destructor for RadiationSource

Definition at line 191 of file radiation_source.cc.

8.9.3.3 jeod::RadiationSource::RadiationSource (const RadiationSource &) [private]

8.9.4 Member Function Documentation

8.9.4.1 void jeod::RadiationSource::calculate_flux (RefFrame & veh_struc_frame, const double center_gravity[3])

[virtual]

calculates the flux vector from the vehicle's position.

Parameters

	in	veh_struc_frame	the vehicle structural reference frame
ſ	in	center_gravity	position of the center of mass
			Units: M

Definition at line 104 of file radiation_source.cc.

References d_source_to_cg, flux_hat, flux_inertial, flux_mag, flux_struc, flux_struc_hat, inertial_cg, inertial_frame_ptr, luminosity, source_to_cg, and source_to_struc_origin.

Referenced by jeod::RadiationPressure::update().

8.9.4.2 void jeod::RadiationSource::initialize (DynManager * dyn_mgr_ptr) [virtual]

Initializes the source object for use in the Radiation Pressure model.

Parameters

in	dyn_mgr_ptr	pointer to the dynamics manager

Definition at line 168 of file radiation source.cc.

References jeod::RadiationMessages::incomplete_setup_error, inertial_frame_ptr, and name.

Referenced by jeod::RadiationPressure::initialize environment().

8.9.4.3 RadiationSource& jeod::RadiationSource::operator=(const RadiationSource &) [private]

8.9.4.4 void jeod::RadiationSource::set_name(std::string name_in) [inline]

Setter for the name.

Definition at line 200 of file radiation_source.hh.

References name.

8.9.5 Friends And Related Function Documentation

8.9.5.1 void init_attrjeod__RadiationSource() [friend]

8.9.5.2 friend class InputProcessor [friend]

Definition at line 58 of file radiation_source.hh.

8.9.6 Field Documentation

8.9.6.1 bool jeod::RadiationSource::bodies_active

can there be 3rd-body interference, either shadowing or reflection.

trick_units(-)

Definition at line 156 of file radiation source.hh.

8.9.6.2 double jeod::RadiationSource::d_source_to_cg

distance from source to vehicle cg.

trick units(m)

Definition at line 92 of file radiation source.hh.

Referenced by calculate_flux(), jeod::RadiationThirdBody::calculate_shadow(), and RadiationSource().

8.9.6.3 double jeod::RadiationSource::flux_hat[3]

(inertial) unit vector associated with primary radiative flux.

trick units(-)

Definition at line 81 of file radiation source.hh.

Referenced by calculate_flux(), and RadiationSource().

8.9.6.4 double jeod::RadiationSource::flux_inertial[3]

(N/M/s) Power per unit area in the inertial reference frame

trick_units(-)

Definition at line 107 of file radiation_source.hh.

Referenced by calculate flux(), RadiationSource(), and jeod::RadiationPressure::third body adjustments().

8.9.6.5 double jeod::RadiationSource::flux_mag

magnitude of principle radiative flux vector

trick_units(N/m2)

Definition at line 86 of file radiation_source.hh.

 $Referenced \ by \ calculate_flux(), \ RadiationSource(), \ jeod::RadiationPressure::third_body_adjustments(), \ jeod::RadiationPressure::update_default_surface(), \ and jeod::RadiationPressure::update_facet_surface().$

8.9.6.6 double jeod::RadiationSource::flux_struc[3]

(N/M*s) Power per unit area in the vehicle structural reference frame

trick_units(-)

Definition at line 112 of file radiation source.hh.

Referenced by calculate_flux(), RadiationSource(), and jeod::RadiationPressure::third_body_adjustments().

 $8.9.6.7 \quad double\ jeod::RadiationSource::flux_struc_hat[3]$

Unit vector representing flux vector in the vehicle structural reference frame.

trick units(-)

Definition at line 118 of file radiation_source.hh.

Referenced by calculate_flux(), RadiationSource(), jeod::RadiationPressure::update_default_surface(), and jeod::RadiationPressure::update_facet_surface().

8.9.6.8 double jeod::RadiationSource::inertial_cg[3]

vehicle cg position w.r.t vehicle strucural origin, expressed in inertial RF.

trick_units(m)

Definition at line 124 of file radiation source.hh.

Referenced by calculate_flux(), and RadiationSource().

8.9.6.9 RefFrame* jeod::RadiationSource::inertial_frame_ptr

the inertial reference frame associated with this source

trick_units(-)

Definition at line 144 of file radiation source.hh.

Referenced by calculate_flux(), initialize(), jeod::RadiationThirdBody::initialize(), RadiationSource(), and jeod::RadiationThirdBody::update_third_body_state().

8.9.6.10 double jeod::RadiationSource::luminosity

Luminosity of primary source.

trick_units(-)

Definition at line 97 of file radiation_source.hh.

Referenced by calculate_flux(), and RadiationSource().

8.9.6.11 bool jeod::RadiationSource::multiple_shadow_bodies

flags that more than one body are casting shadows on the vehicle.

trick units(-)

Definition at line 139 of file radiation source.hh.

Referenced by RadiationSource().

8.9.6.12 std::string jeod::RadiationSource::name

The name of the source of the illumination (usually Sun)

trick units(-)

Definition at line 76 of file radiation_source.hh.

Referenced by initialize(), RadiationSource(), and set_name().

8.9.6.13 unsigned int jeod::RadiationSource::num_bodies

number of ThirdBodies available.

trick_units(count)

Definition at line 161 of file radiation_source.hh.

Referenced by jeod::RadiationPressure::initialize().

8.9.6.14 double jeod::RadiationSource::radius

Radius of primary source.

trick units(m)

Definition at line 102 of file radiation_source.hh.

Referenced by jeod::RadiationThirdBody::calculate_shadow(), jeod::RadiationThirdBody::initialize(), and Radiation-Source().

8.9.6.15 OldShadowGeometry jeod::RadiationSource::shadow_geometry

Flag indicating cylindrical / conical shadow geometry.

trick units(-)

Definition at line 184 of file radiation_source.hh.

Referenced by jeod::RadiationPressure::initialize().

8.9.6.16 const double jeod::RadiationSource::solar_luminosity

Solar Luminosity.

trick_units(-)

Definition at line 66 of file radiation source.hh.

Referenced by RadiationSource().

8.9.6.17 const double jeod::RadiationSource::solar_radius

Mean solar radius.

trick_units(m)

Definition at line 71 of file radiation_source.hh.

Referenced by RadiationSource().

8.9.6.18 double jeod::RadiationSource::source_to_cg[3]

vehicle cg position relative to the source

trick_units(m)

Definition at line 129 of file radiation_source.hh.

Referenced by calculate_flux(), jeod::RadiationThirdBody::calculate_shadow(), and RadiationSource().

8.9.6.19 double jeod::RadiationSource::source_to_struc_origin[3]

vehicle struc frame origin position relative to source.

trick_units(m)

Definition at line 134 of file radiation_source.hh.

Referenced by calculate_flux(), and RadiationSource().

8.9.6.20 RadiationThirdBody** jeod::RadiationSource::third_body

Planetary bodies that provide shadowing or indirect, reflected, illumination.

trick_units(-)

Definition at line 167 of file radiation source.hh.

Referenced by jeod::RadiationPressure::initialize().

The documentation for this class was generated from the following files:


- · radiation_source.hh
- radiation_source.cc

8.10 jeod::RadiationSurface Class Reference

The surface of the vehicle that interacts with the incident flux.

#include <radiation_surface.hh>

Inheritance diagram for jeod::RadiationSurface:



Public Member Functions

• RadiationSurface ()

Constructor for RadiationSurface.

virtual ∼RadiationSurface ()

Destructor for RadiationSurface.

• void initialize (double center grav[3])

Initializes the radiation surface.

void allocate_array (unsigned int size)

Allocates memory for an array of radiation facets.

void allocate_interaction_facet (Facet *facet, InteractionFacetFactory *factory, FacetParams *params, unsigned int index)

Turns facet memory into radiaiton facet memory.

· void initialize_runtime_values (void)

To initialize the values during each update run.

- void incident_radiation (double flux_mag, const double flux_struc_hat[3], bool calculate_forces)
 - systematically calls the method to calculate the interaction on each facet.
- void interact_with_third_body (RadiationThirdBody *third_body_ptr, const bool calculate_forces)

systematically calls the method to calculate the interaction of each facet with ThirdBody flux.

void accumulate_thermal_sources (void)

systematically calls the method to accumulate thermal sources on each facet.

void thermal_integrator (void)

systematically calls the method to integrate the temperature variation for each facet.

· void equalize absorption emission (void)

systematically calls the method to ensure that the same for each facet.

void radiation_pressure (void)

systematically calls the method to wrap up the radiation pressure calculation on each facet and accumulate forces and torques over all facets.

void add_thermal_integrators_to (DynBody *dyn_body)

To attach thermal integrators from each facet to the integration group of a DynBody.

Data Fields

RadiationFacet ** facets

Array of pointers to the Radiation Facets.

• unsigned int num_facets

number of facets in this surface.

bool include_conduction

Flag to instruct model to include conduction between plates in the thermal calculation.

double ** thermal_conduction

Conductivity values (Watts per Kelvin) between facets.

· double force [3]

Force resulting from all radiative interactions.

• double torque [3]

Torque resulting from all radiative interactions.

unsigned int ii_facet

Simple counter, used repeatedly.

Private Member Functions

- RadiationSurface & operator= (const RadiationSurface &rhs)
- RadiationSurface (const RadiationSurface &rhs)

Friends

- · class InputProcessor
- void init_attrjeod__RadiationSurface ()

8.10.1 Detailed Description

The surface of the vehicle that interacts with the incident flux.

Definition at line 55 of file radiation_surface.hh.

8.10.2 Constructor & Destructor Documentation

8.10.2.1 jeod::RadiationSurface::RadiationSurface (void)

Constructor for RadiationSurface.

Definition at line 67 of file radiation_surface.cc.

8.10.2.2 jeod::RadiationSurface::~RadiationSurface(void) [virtual]

Destructor for RadiationSurface.

Definition at line 376 of file radiation surface.cc.

References facets, ii_facet, and num_facets.

8.10.2.3 jeod::RadiationSurface::RadiationSurface (const RadiationSurface & rhs) [private]

8.10.3 Member Function Documentation

8.10.3.1 void jeod::RadiationSurface::accumulate_thermal_sources (void)

systematically calls the method to accumulate thermal sources on each facet.

Definition at line 278 of file radiation surface.cc.

References facets, ii_facet, num_facets, and jeod::RadiationBaseFacet::thermal.

8.10.3.2 void jeod::RadiationSurface::add_thermal_integrators_to (DynBody * dyn_body)

To attach thermal integrators from each facet to the integration group of a DynBody.

Parameters

in,out	dyn_body	Body to which integrators are to be added.
--------	----------	--

Definition at line 365 of file radiation_surface.cc.

8.10.3.3 void jeod::RadiationSurface::allocate_array (unsigned int size)

Allocates memory for an array of radiation facets.

Parameters

in	size	Size of array

Definition at line 142 of file radiation surface.cc.

References facets, ii_facet, num_facets, and jeod::RadiationMessages::operational_setup_error.

8.10.3.4 void jeod::RadiationSurface::allocate_interaction_facet (Facet * facet, InteractionFacetFactory * factory, FacetParams * params, unsigned int index)

Turns facet memory into radiaiton facet memory.

Parameters

in	facet	pointer to the facet
in	factory	pointer to the facet factory
in	params	pointer to the generic facet parameter.
in	index	index value in the facet list.

Definition at line 176 of file radiation_surface.cc.

 $References\ facets,\ jeod:: Radiation Messages:: invalid_setup_error,\ num_facets,\ and\ jeod:: Radiation Messages:: operational_setup_error.$

8.10.3.5 void jeod::RadiationSurface::equalize_absorption_emission (void)

systematically calls the method to ensure that the same for each facet.

Definition at line 313 of file radiation_surface.cc.

References facets, ii_facet, num_facets, and jeod::RadiationBaseFacet::thermal.

Referenced by jeod::RadiationPressure::update_facet_surface().

8.10.3.6 void jeod::RadiationSurface::incident_radiation (double flux_mag, const double flux_struc_hat[3], bool calculate_forces)

systematically calls the method to calculate the interaction on each facet.

Parameters

in	flux_mag	Magnitude of incident flux
in	flux_struc_hat	unit vector of incident flux
in	calculate_forces	boolean indicating whether to calculate forces.

Definition at line 241 of file radiation_surface.cc.

References facets, ii facet, jeod::RadiationBaseFacet::incident radiation(), and num facets.

Referenced by jeod::RadiationPressure::update_facet_surface().

8.10.3.7 void jeod::RadiationSurface::initialize (double center_grav[3])

Initializes the radiation surface.

Parameters

in	center_grav	position of center of mass
		Units: M

Definition at line 87 of file radiation surface.cc.

References facets, ii_facet, jeod::RadiationFacet::initialize_geom(), jeod::RadiationMessages::invalid_setup_error, num_facets, jeod::RadiationMessages::operational_setup_error, and jeod::RadiationBaseFacet::thermal.

Referenced by jeod::RadiationPressure::initialize().

8.10.3.8 void jeod::RadiationSurface::initialize_runtime_values (void)

To initialize the values during each update run.

Definition at line 349 of file radiation surface.cc.

References facets, ii facet, jeod::RadiationBaseFacet::initialize runtime values(), and num facets.

Referenced by jeod::RadiationPressure::update_facet_surface().

8.10.3.9 void jeod::RadiationSurface::interact_with_third_body (RadiationThirdBody * third_body_ptr, const bool calculate_forces)

systematically calls the method to calculate the interaction of each facet with ThirdBody flux.

Parameters

in,out	third_body_ptr	Third body that emits radiation.
in	calculate_forces	Calculate forces on the surface if true.

Definition at line 263 of file radiation_surface.cc.

References facets, ii_facet, jeod::RadiationBaseFacet::interact_with_third_body(), and num_facets.

Referenced by jeod::RadiationPressure::update_facet_surface().

8.10.3.10 RadiationSurface& jeod::RadiationSurface::operator=(const RadiationSurface & rhs) [private]

8.10.3.11 void jeod::RadiationSurface::radiation_pressure (void)

systematically calls the method to wrap up the radiation pressure calculation on each facet and accumulate forces and torques over all facets.

Definition at line 328 of file radiation surface.cc.

References facets, force, ii_facet, num_facets, jeod::RadiationFacet::radiation_pressure(), and torque.

Referenced by jeod::RadiationPressure::update_facet_surface().

8.10.3.12 void jeod::RadiationSurface::thermal_integrator (void)

systematically calls the method to integrate the temperature variation for each facet.

Definition at line 293 of file radiation surface.cc.

References facets, ii facet, num facets, and jeod::RadiationBaseFacet::thermal.

8.10.4 Friends And Related Function Documentation

```
8.10.4.1 void init_attrjeod__RadiationSurface() [friend]
```

8.10.4.2 friend class InputProcessor [friend]

Definition at line 57 of file radiation surface.hh.

8.10.5 Field Documentation

8.10.5.1 RadiationFacet** jeod::RadiationSurface::facets

Array of pointers to the Radiation Facets.

trick_units(-)

Definition at line 64 of file radiation surface.hh.

Referenced by accumulate_thermal_sources(), allocate_array(), allocate_interaction_facet(), equalize_absorption_emission(), incident_radiation(), initialize(), initialize_runtime_values(), interact_with_third_body(), radiation_pressure(), thermal_integrator(), and ~RadiationSurface().

8.10.5.2 double jeod::RadiationSurface::force[3]

Force resulting from all radiative interactions.

trick units(-)

Definition at line 88 of file radiation_surface.hh.

Referenced by radiation_pressure(), and jeod::RadiationPressure::update_facet_surface().

8.10.5.3 unsigned int jeod::RadiationSurface::ii_facet

Simple counter, used repeatedly.

trick units(-)

Definition at line 98 of file radiation_surface.hh.

Referenced by accumulate_thermal_sources(), allocate_array(), equalize_absorption_emission(), incident_radiation(), initialize_runtime_values(), interact_with_third_body(), radiation_pressure(), thermal_integrator(), and \sim RadiationSurface().

8.10.5.4 bool jeod::RadiationSurface::include_conduction

Flag to instruct model to include conduction between plates in the thermal calculation.

Requires a thermal_conduction matrix.trick_units(-)

Definition at line 75 of file radiation_surface.hh.

8.10.5.5 unsigned int jeod::RadiationSurface::num_facets

number of facets in this surface.

trick_units(-)

Definition at line 69 of file radiation surface.hh.

Referenced by accumulate_thermal_sources(), allocate_array(), allocate_interaction_facet(), equalize_absorption_emission(), incident_radiation(), initialize(), initialize_runtime_values(), interact_with_third_body(), radiation_pressure(), thermal_integrator(), and \sim RadiationSurface().

8.10.5.6 double** jeod::RadiationSurface::thermal_conduction

Conductivity values (Watts per Kelvin) between facets.

Assumed symmetric, only the values [small][large] will be considered (e.g. thermal_conduction[2][3] gives the conduction between facets 2 and 3, whereas thermal_conduction[3][2] will never be seen.trick_units(-)

Definition at line 83 of file radiation surface.hh.

8.10.5.7 double jeod::RadiationSurface::torque[3]

Torque resulting from all radiative interactions.

trick units(-)

Definition at line 93 of file radiation_surface.hh.

Referenced by radiation_pressure(), and jeod::RadiationPressure::update_facet_surface().

The documentation for this class was generated from the following files:


- · radiation_surface.hh
- · radiation_surface.cc

8.11 jeod::RadiationSurfaceFactory Class Reference

The factory for creating Radiation Surfaces.

#include <radiation_surface_factory.hh>

 $Inheritance\ diagram\ for\ jeod:: Radiation Surface Factory:$



Public Member Functions

· RadiationSurfaceFactory ()

Constructor.

virtual ∼RadiationSurfaceFactory ()

Destructor.

virtual void add_facet_params (FacetParams *to_add)
 Add a set of radiation parameters to those available to Radiation Surface.

Protected Attributes

• FlatPlateRadiationFactory flat_plate_radiation_factory

The factory to build flat plate thermal facets.

Private Member Functions

- RadiationSurfaceFactory & operator= (const RadiationSurfaceFactory &rhs)
- RadiationSurfaceFactory (const RadiationSurfaceFactory &rhs)

Friends

- · class InputProcessor
- void init_attrjeod__RadiationSurfaceFactory ()

8.11.1 Detailed Description

The factory for creating Radiation Surfaces.

Definition at line 50 of file radiation_surface_factory.hh.

8.11.2 Constructor & Destructor Documentation

```
8.11.2.1 jeod::RadiationSurfaceFactory::RadiationSurfaceFactory ( void )
```

Constructor.

Definition at line 56 of file radiation_surface_factory.cc.

References flat_plate_radiation_factory.

```
8.11.2.2 jeod::RadiationSurfaceFactory::~RadiationSurfaceFactory (void ) [virtual]
```

Destructor.

Definition at line 100 of file radiation_surface_factory.cc.

```
8.11.2.3 jeod::RadiationSurfaceFactory::RadiationSurfaceFactory ( const RadiationSurfaceFactory & rhs )
[private]
```

8.11.3 Member Function Documentation

8.11.3.1 void jeod::RadiationSurfaceFactory::add_facet_params (FacetParams * to_add) [virtual]

Add a set of radiation parameters to those available to Radiation Surface.

Parameters

in	to_add	pointer to the parameter list to add.

Definition at line 70 of file radiation_surface_factory.cc.

References jeod::RadiationMessages::invalid_setup_error.

8.11.3.2 RadiationSurfaceFactory& jeod::RadiationSurfaceFactory::operator=(const RadiationSurfaceFactory & rhs
) [private]

8.11.4 Friends And Related Function Documentation

```
8.11.4.1 void init_attrjeod__RadiationSurfaceFactory() [friend]
```

8.11.4.2 friend class InputProcessor [friend]

Definition at line 52 of file radiation_surface_factory.hh.

8.11.5 Field Documentation

8.11.5.1 FlatPlateRadiationFactory jeod::RadiationSurfaceFactory::flat_plate_radiation_factory [protected]

The factory to build flat plate thermal facets.

trick_units(-)

Definition at line 76 of file radiation_surface_factory.hh.

Referenced by RadiationSurfaceFactory().

The documentation for this class was generated from the following files:

- · radiation_surface_factory.hh
- radiation_surface_factory.cc

8.12 jeod::RadiationThirdBody Class Reference

Provide information on bodies that may cause shadowing or reflected illumination.

```
#include <radiation_third_body.hh>
```

Public Types

 enum ShadowGeometry { Cylindrical = 0, Cyl = 1, Conical = 2, Con = 3 } distinguishes between conical and cylindrical shadowing

Public Member Functions

• RadiationThirdBody ()

Constructor.

- virtual ∼RadiationThirdBody ()
- virtual void initialize (DynManager *dyn_mgr_ptr)

initializes the third body

· void calculate shadow (void)

Calculates the effect of shadowing by a third body.

void convert_shadow_from_int (int geometry)

convert from the old style framework in which the shadow geometry was owned by the RadiationSource (same for all third bodies) to the new style framework where the geometry is owned by each ThirdBody

• virtual double process_third_body (double time, RefFrame &vehicle_structural_frame)

Primary executable for handling the Third Body effects.

void set_name (std::string name_in)

Setter for the name.

virtual void accumulate refl flux (RadiationBaseFacet *veh surf elem, bool calculate forces)

To provide base class null implementation.

• virtual void accumulate rad flux (RadiationBaseFacet *veh surf elem, bool calculate forces)

To provide base class null implementation.

• virtual bool is_interactive ()

Identifies this class as one that does not produce a radiaiton field.

bool get added to model ()

Returns information on whether the body has already been used in one RadiationPressure model.

void set added to model (bool value)

Sets the added_to_model value.

Data Fields

• RadiationSource * primary_source_ptr

Pointer to the primary illumination source.

ShadowGeometry shadow_geometry

Flag indicating cylindrical / conical shadow geometry.

bool force_state_update

Flag to indicate whether to enforce an update to the third-body body-state.

· std::string name

Name of planet.

· bool active

Model on/off flag.

· double update interval

Time interval between third body state updates.

double radius

Radius of RadiationThirdBody.

double output_flux [3]

Calculated value.

RefFrame * local_frame_ptr

Pointer to the local reference frame, for determining position of this object.

Protected Member Functions

• double generate_alpha (double rho, double delta)

generate_alpha(rho_adj, delta: generates an approximate alpha-value given a relative disk size and fraction of maximum possible eclipse

bool test_for_state_update (double time)

Tests for necessity of updating third body state, and calls appropriate update method (polymorphic) if needed.

virtual bool update_third_body_state (void)

Updates the state of the Third Body.

Protected Attributes

bool added_to_model

Flag to indicate whether body has already been added to a model.

· bool initialized

Flag to indicate that initialization has been complete.

· double illum factor

Value between 0 and 1 representing the fraction of possible flux that is actually incident after shadowing effects.

· double last update time

Time at which the third body state was last updated.

Planet * planet_link

Pointer to the associated Planet object.

· double r_plus

The value (radius + R_source)

• double r_minus

The value (radius - R_source)

• double r ratio

The ratio (radius / R_source)

· double r_par

Component of vector from RadiationThirdBody to vehicle that is parallel to vector from primary source to Radiation-ThirdBody.

• double r_perp

Component of vector from RadiationThirdBody to vehicle that is perpendicular to vector from primary source to RadiationThirdBody.

• double third_to_cg_inrtl [3]

Vector from RadiationThirdBody to vehicle center of gravity, in inertial RF.

double source_to_third_inrtl [3]

Vector from the primary source to the RadiationThirdBody in inertial RF.

• double d_source_to_third

Magnitude of source_to_third.

• double source_to_third_hat_inrtl [3]

Unit vector of source_to_third.

Private Member Functions

- RadiationThirdBody (const RadiationThirdBody &)
- RadiationThirdBody & operator= (const RadiationThirdBody &)

Friends

- class InputProcessor
- void init_attrjeod__RadiationThirdBody ()

8.12.1 Detailed Description

Provide information on bodies that may cause shadowing or reflected illumination.

Definition at line 49 of file radiation_third_body.hh.

8.12.2 Member Enumeration Documentation

8.12.2.1 enum jeod::RadiationThirdBody::ShadowGeometry

distinguishes between conical and cylindrical shadowing

Enumerator

Cylindrical planet casts a cylindrical shadow

Cyl planet casts a cylindrical shadow

Conical planet casts a conical shadow

Con planet casts a conical shadow

Definition at line 57 of file radiation_third_body.hh.

8.12.3 Constructor & Destructor Documentation

8.12.3.1 jeod::RadiationThirdBody::RadiationThirdBody ()

Constructor.

Definition at line 58 of file radiation third body.cc.

References output_flux, source_to_third_hat_inrtl, source_to_third_inrtl, and third_to_cg_inrtl.

```
8.12.3.2 virtual jeod::RadiationThirdBody::~RadiationThirdBody( ) [inline], [virtual]
```

Definition at line 203 of file radiation third body.hh.

8.12.3.3 jeod::RadiationThirdBody::RadiationThirdBody (const RadiationThirdBody &) [private]

8.12.4 Member Function Documentation

8.12.4.1 virtual void jeod::RadiationThirdBody::accumulate_rad_flux (RadiationBaseFacet * veh_surf_elem, bool calculate_forces) [inline], [virtual]

To provide base class null implementation.

Parameters

veh_surf_elem	The facet of the vehicle.
calculate_forces	pass-through flag.

Definition at line 237 of file radiation_third_body.hh.

Referenced by jeod::RadiationBaseFacet::interact_with_third_body().

8.12.4.2 virtual void jeod::RadiationThirdBody::accumulate_refl_flux (RadiationBaseFacet * veh_surf_elem, bool calculate_forces) [inline], [virtual]

To provide base class null implementation.

Parameters

veh_sı	urf_elem	The facet of the vehicle.
calculate	e_forces	pass-through flag.

Definition at line 229 of file radiation third body.hh.

Referenced by jeod::RadiationBaseFacet::interact_with_third_body().

8.12.4.3 void jeod::RadiationThirdBody::calculate_shadow (void)

Calculates the effect of shadowing by a third body.

NOTE - This method is intended to be an internal call so should be protected However, doing so would be a change to the API. Delay for JEOD4.0.

Definition at line 206 of file radiation_third_body.cc.

References active, Con, Conical, Cyl, Cylindrical, jeod::RadiationSource::d_source_to_cg, d_source_to_third, generate_alpha(), illum_factor, initialized, jeod::RadiationMessages::invalid_setup_error, name, primary_source_ptr, r_minus, r_par, r_perp, r_plus, r_ratio, radius, jeod::RadiationSource::radius, shadow_geometry, jeod::RadiationSource::source_to_cg, source_to_third_hat_inrtl, source_to_third_inrtl, and third_to_cg_inrtl.

Referenced by process third body().

8.12.4.4 void jeod::RadiationThirdBody::convert_shadow_from_int (int old_shadow_geometry)

convert from the old style framework in which the shadow geometry was owned by the RadiationSource (same for all third bodies) to the new style framework where the geometry is owned by each ThirdBody

Parameters

in	old_shadow	integer representation of the shadow geometry enumeration.
	geometry	

Definition at line 409 of file radiation_third_body.cc.

References jeod::RadiationMessages::invalid setup error, and shadow geometry.

8.12.4.5 double jeod::RadiationThirdBody::generate_alpha (double *rho_adj*, double *delta*) [protected]

generate_alpha(rho_adj, delta: generates an approximate alpha-value given a relative disk size and fraction of maximum possible eclipse

Parameters

in	relative	disk size
in	fraction	of eclipse achieved.

Definition at line 376 of file radiation third body.cc.

Referenced by calculate_shadow().

8.12.4.6 bool jeod::RadiationThirdBody::get_added_to_model() [inline]

Returns information on whether the body has already been used in one RadiationPressure model.

Protects against multiple use of one ThirdBody instance.

Returns

added_to_model

Definition at line 252 of file radiation_third_body.hh.

References added_to_model.

Referenced by jeod::RadiationPressure::add third body().

8.12.4.7 void jeod::RadiationThirdBody::initialize (DynManager * dyn_mgr_ptr) [virtual]

initializes the third body

Parameters

in	dyn mgr ptr	pointer to the dynamics manager
	, _ 0 _	, ,

Definition at line 93 of file radiation third body.cc.

References active, jeod::RadiationSource::inertial_frame_ptr, initialized, jeod::RadiationMessages::invalid_setup_error, local_frame_ptr, name, planet_link, primary_source_ptr, r_minus, r_plus, r_ratio, radius, and jeod::Radiation-Source::radius.

Referenced by jeod::RadiationPressure::add third body().

8.12.4.8 virtual bool jeod::RadiationThirdBody::is_interactive() [inline], [virtual]

Identifies this class as one that does not produce a radiaiton field.

Returns

false

Definition at line 244 of file radiation_third_body.hh.

8.12.4.9 RadiationThirdBody&jeod::RadiationThirdBody::operator=(const RadiationThirdBody&) [private]

8.12.4.10 double jeod::RadiationThirdBody::process_third_body (double real_time, RefFrame & veh_struc_frame)

[virtual]

Primary executable for handling the Third Body effects.

Returns

shading fraction

Parameters

in	real_time	Current time. Units: s
in	veh_struc_frame	Unused.

Definition at line 431 of file radiation_third_body.cc.

References active, calculate_shadow(), illum_factor, initialized, jeod::RadiationMessages::invalid_setup_error, name, jeod::RadiationMessages::operational_setup_error, and test_for_state_update().

8.12.4.11 void jeod::RadiationThirdBody::set_added_to_model(bool value) [inline]

Sets the added_to_model value.

Parameters

value	New value
-------	-----------

Definition at line 258 of file radiation_third_body.hh.

References added to model.

Referenced by jeod::RadiationPressure::add_third_body().

8.12.4.12 void jeod::RadiationThirdBody::set_name (std::string name_in) [inline]

Setter for the name.

Definition at line 219 of file radiation third body.hh.

References name.

8.12.4.13 bool jeod::RadiationThirdBody::test_for_state_update (double real_time) [protected]

Tests for necessity of updating third body state, and calls appropriate update method (polymorphic) if needed.

Parameters

in	real_time	Current time
		Units: s

Definition at line 474 of file radiation_third_body.cc.

References force_state_update, last_update_time, update_interval, and update_third_body_state().

Referenced by process third body().

8.12.4.14 bool jeod::RadiationThirdBody::update_third_body_state (void) [protected], [virtual]

Updates the state of the Third Body.

Because the ThirdBody may be associated with multiple vehicles, and because its state typically changes much more slowly than the vehicle anyway, it is not always necessary to update the ThirdBodyState.

Definition at line 498 of file radiation third body.cc.

References active, d_source_to_third, jeod::RadiationSource::inertial_frame_ptr, jeod::RadiationMessages::invalid_setup_error, local_frame_ptr, name, primary_source_ptr, source_to_third_hat_inrtl, and source_to_third_inrtl.

Referenced by test_for_state_update().

8.12.5 Friends And Related Function Documentation

8.12.5.1 void init_attrjeod__RadiationThirdBody() [friend]

8.12.5.2 friend class InputProcessor [friend]

Definition at line 51 of file radiation_third_body.hh.

8.12.6 Field Documentation

8.12.6.1 bool jeod::RadiationThirdBody::active

Model on/off flag.

trick_units(-)

Definition at line 89 of file radiation_third_body.hh.

Referenced by jeod::RadiationPressure::add_third_body(), calculate_shadow(), initialize(), process_third_body(), and update third body state().

8.12.6.2 bool jeod::RadiationThirdBody::added_to_model [protected]

Flag to indicate whether body has already been added to a model.

trick units(-)

Definition at line 121 of file radiation_third_body.hh.

Referenced by get_added_to_model(), and set_added_to_model().

8.12.6.3 double jeod::RadiationThirdBody::d_source_to_third [protected]

Magnitude of source to third.

trick_units(m)

Definition at line 191 of file radiation_third_body.hh.

Referenced by calculate_shadow(), and update_third_body_state().

8.12.6.4 bool jeod::RadiationThirdBody::force_state_update

Flag to indicate whether to enforce an update to the third-body body-state.

Default: true Self-resets to false after each use.trick_units(-)

Definition at line 79 of file radiation_third_body.hh.

Referenced by test_for_state_update().

8.12.6.5 double jeod::RadiationThirdBody::illum_factor [protected]

Value between 0 and 1 representing the fraction of possible flux that is actually incident after shadowing effects.

trick_units(-)

Definition at line 132 of file radiation_third_body.hh.

 $Referenced\ by\ calculate_shadow(),\ and\ process_third_body().$

8.12.6.6 bool jeod::RadiationThirdBody::initialized [protected]

Flag to indicate that initialization has been complete.

trick units(-)

Definition at line 126 of file radiation_third_body.hh.

Referenced by calculate_shadow(), initialize(), and process_third_body().

8.12.6.7 double jeod::RadiationThirdBody::last_update_time [protected]

Time at which the third body state was last updated.

trick_units(s)

Definition at line 137 of file radiation third body.hh.

Referenced by test_for_state_update().

8.12.6.8 RefFrame* jeod::RadiationThirdBody::local_frame_ptr

Pointer to the local reference frame, for determining position of this object.

trick_units(-)

Definition at line 112 of file radiation_third_body.hh.

Referenced by initialize(), and update_third_body_state().

8.12.6.9 std::string jeod::RadiationThirdBody::name

Name of planet.

trick units(-)

Definition at line 84 of file radiation_third_body.hh.

Referenced by jeod::RadiationPressure::add_third_body(), calculate_shadow(), initialize(), process_third_body(), set_name(), and update_third_body_state().

8.12.6.10 double jeod::RadiationThirdBody::output_flux[3]

Calculated value.

Set only in derived class RadiationReflectingThirdBody.trick_units(-)

Definition at line 106 of file radiation third body.hh.

Referenced by RadiationThirdBody().

8.12.6.11 Planet* jeod::RadiationThirdBody::planet_link [protected]

Pointer to the associated Planet object.

trick_units(-)

Definition at line 143 of file radiation_third_body.hh.

Referenced by initialize().

8.12.6.12 RadiationSource* jeod::RadiationThirdBody::primary_source_ptr

Pointer to the primary illumination source.

trick_units(-)

Definition at line 67 of file radiation_third_body.hh.

Referenced by calculate_shadow(), initialize(), and update_third_body_state().

8.12.6.13 double jeod::RadiationThirdBody::r_minus [protected]

The value (radius - R_source)

trick_units(-)

Definition at line 153 of file radiation third body.hh.

Referenced by calculate_shadow(), and initialize().

```
8.12.6.14 double jeod::RadiationThirdBody::r_par [protected]
```

Component of vector from RadiationThirdBody to vehicle that is parallel to vector from primary source to RadiationThirdBody.

trick_units(m)

Definition at line 166 of file radiation third body.hh.

Referenced by calculate_shadow().

8.12.6.15 double jeod::RadiationThirdBody::r_perp [protected]

Component of vector from RadiationThirdBody to vehicle that is perpendicular to vector from primary source to RadiationThirdBody.

trick units(-)

Definition at line 172 of file radiation third body.hh.

Referenced by calculate_shadow().

8.12.6.16 double jeod::RadiationThirdBody::r_plus [protected]

The value (radius + R source)

trick_units(-)

Definition at line 148 of file radiation_third_body.hh.

Referenced by calculate_shadow(), and initialize().

8.12.6.17 double jeod::RadiationThirdBody::r_ratio [protected]

The ratio (radius / R source)

trick_units(-)

Definition at line 158 of file radiation_third_body.hh.

Referenced by calculate_shadow(), and initialize().

8.12.6.18 double jeod::RadiationThirdBody::radius

Radius of RadiationThirdBody.

Note - this is set automatically if RTB is a planet, but must be set manually if RTB is a DynBody.trick_units(m)

Definition at line 100 of file radiation_third_body.hh.

Referenced by calculate_shadow(), and initialize().

8.12.6.19 ShadowGeometry jeod::RadiationThirdBody::shadow_geometry

Flag indicating cylindrical / conical shadow geometry.

trick_units(-)

Definition at line 72 of file radiation_third_body.hh.

Referenced by calculate_shadow(), and convert_shadow_from_int().

8.12.6.20 double jeod::RadiationThirdBody::source_to_third_hat_inrtl[3] [protected]

Unit vector of source_to_third.

trick_units(-)

Definition at line 196 of file radiation third body.hh.

Referenced by calculate_shadow(), RadiationThirdBody(), and update_third_body_state().

8.12.6.21 double jeod::RadiationThirdBody::source_to_third_inrtl[3] [protected]

Vector from the primary source to the RadiationThirdBody in inertial RF.

trick_units(m)

Definition at line 186 of file radiation_third_body.hh.

Referenced by calculate_shadow(), RadiationThirdBody(), and update_third_body_state().

8.12.6.22 double jeod::RadiationThirdBody::third_to_cg_inrtl[3] [protected]

Vector from RadiationThirdBody to vehicle center of gravity, in inertial RF.

trick_units(m)

Definition at line 178 of file radiation_third_body.hh.

Referenced by calculate_shadow(), and RadiationThirdBody().

8.12.6.23 double jeod::RadiationThirdBody::update_interval

Time interval between third body state updates.

trick_units(s)

Definition at line 94 of file radiation third body.hh.

Referenced by test_for_state_update().

The documentation for this class was generated from the following files:

- · radiation_third_body.hh
- radiation_third_body.cc



Chapter 9

File Documentation

9.1 flat_plate_radiation_facet.cc File Reference

Define member functions for class FlatPlateRadiationFacet.

```
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/surface_model/include/flat_plate.hh"
#include "../include/flat_plate_radiation_facet.hh"
#include "../include/radiation_messages.hh"
#include "../include/radiation_third_body.hh"
```

Namespaces

• jeod

Namespace jeod.

9.1.1 Detailed Description

Define member functions for class FlatPlateRadiationFacet.

Definition in file flat_plate_radiation_facet.cc.

9.2 flat_plate_radiation_facet.hh File Reference

Individual facets for use with rad environment interaction models.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "radiation_facet.hh"
```

Data Structures

• class jeod::FlatPlateRadiationFacet

A flat plate facet to be used for radiation interaction.

76 File Documentation

Namespaces

• jeod

Namespace jeod.

9.2.1 Detailed Description

Individual facets for use with rad environment interaction models.

Definition in file flat_plate_radiation_facet.hh.

9.3 flat_plate_radiation_factory.cc File Reference

Factory that creates a FlatPlateRadiationFacet, from a facet model.

```
#include <cstddef>
#include <typeinfo>
#include "utils/surface_model/include/flat_plate_thermal.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/message/include/message_handler.hh"
#include "../include/flat_plate_radiation_factory.hh"
#include "../include/radiation_params.hh"
#include "../include/flat_plate_radiation_facet.hh"
#include "../include/radiation_messages.hh"
```

Namespaces

jeod

Namespace jeod.

9.3.1 Detailed Description

Factory that creates a FlatPlateRadiationFacet, from a facet model.

Definition in file flat_plate_radiation_factory.cc.

9.4 flat_plate_radiation_factory.hh File Reference

Factory that creates an interaction facet, for a specific environment interaction model, from a facet model.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/interaction_facet_factory.hh"
#include "flat_plate_radiation_facet.hh"
```

Data Structures

· class jeod::FlatPlateRadiationFactory

The factory for building flat plate radiation facets.

Namespaces

jeod

Namespace jeod.

9.4.1 Detailed Description

Factory that creates an interaction facet, for a specific environment interaction model, from a facet model. Definition in file flat_plate_radiation_factory.hh.

9.5 radiation_base_facet.cc File Reference

Define member functions for class RadiationBaseFacet.

```
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "../include/radiation_base_facet.hh"
#include "../include/radiation_messages.hh"
#include "../include/radiation_third_body.hh"
```

Namespaces

jeod

Namespace jeod.

9.5.1 Detailed Description

Define member functions for class RadiationBaseFacet.

Definition in file radiation_base_facet.cc.

9.6 radiation base facet.hh File Reference

Individual facets for use with radiation environment interaction models.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/interaction_facet.hh"
#include "interactions/thermal_rider/include/thermal_facet_rider.hh"
```

Data Structures

• class jeod::RadiationBaseFacet

Generic type of facet for radiation pressure.

Namespaces

jeod

Namespace jeod.

78 File Documentation

9.6.1 Detailed Description

Individual facets for use with radiation environment interaction models.

Definition in file radiation_base_facet.hh.

9.7 radiation_default_surface.cc File Reference

Default surface for use with Radiation Pressure interaction model.

```
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "interactions/thermal_rider/include/thermal_facet_rider.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "../include/radiation_default_surface.hh"
#include "../include/radiation_messages.hh"
#include "../include/radiation_third_body.hh"
```

Namespaces

jeod

Namespace jeod.

9.7.1 Detailed Description

Default surface for use with Radiation Pressure interaction model.

Definition in file radiation_default_surface.cc.

9.8 radiation default surface.hh File Reference

Individual facets for use with radiation environment interaction models.

```
#include <string>
#include <utility>
#include "utils/sim_interface/include/jeod_class.hh"
#include "interactions/thermal_rider/include/thermal_facet_rider.hh"
#include "radiation_base_facet.hh"
```

Data Structures

class jeod::RadiationDefaultSurface

The default spherical surface for radiation pressure.

Namespaces

jeod

Namespace jeod.

9.8.1 Detailed Description

Individual facets for use with radiation environment interaction models.

Definition in file radiation default surface.hh.

9.9 radiation_facet.cc File Reference

Individual facets for use with Radiation Pressure interaction models.

```
#include "utils/math/include/vector3.hh"
#include "utils/surface_model/include/facet.hh"
#include "interactions/thermal_rider/include/thermal_facet_rider.hh"
#include "utils/message/include/message_handler.hh"
#include "../include/radiation_facet.hh"
#include "../include/radiation_params.hh"
#include "../include/radiation_messages.hh"
```

Namespaces

jeod

Namespace jeod.

9.9.1 Detailed Description

Individual facets for use with Radiation Pressure interaction models.

Definition in file radiation_facet.cc.

9.10 radiation facet.hh File Reference

Individual facets for use with radiation environment interaction models.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/interaction_facet.hh"
#include "interactions/thermal_rider/include/thermal_facet_rider.hh"
#include "radiation_base_facet.hh"
#include "utils/surface_model/include/facet.hh"
```

Data Structures

class jeod::RadiationFacet

Generic type of facet for radiation pressure.

Namespaces

jeod

Namespace jeod.

80 File Documentation

9.10.1 Detailed Description

Individual facets for use with radiation environment interaction models.

Definition in file radiation_facet.hh.

9.11 radiation_messages.cc File Reference

Implement the class RadiationMessages.

```
#include "../include/radiation_messages.hh"
```

Namespaces

jeod

Namespace jeod.

Macros

• #define PATH "interactions/radiation pressure/"

9.11.1 Detailed Description

Implement the class RadiationMessages.

Definition in file radiation_messages.cc.

9.12 radiation_messages.hh File Reference

Define the class RadiationMessages, the class that specifies the message IDs used in the Radiation model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

· class jeod::RadiationMessages

Provides error messages.

Namespaces

• jeod

Namespace jeod.

9.12.1 Detailed Description

Define the class RadiationMessages, the class that specifies the message IDs used in the Radiation model. Definition in file radiation_messages.hh.

9.13 radiation_params.cc File Reference

A virtual base class for radiation facet parameters, used to create interaction facets for radiation in the Interaction-SurfaceFactorys.

```
#include "../include/radiation_params.hh"
```

Namespaces

· jeod

Namespace jeod.

9.13.1 Detailed Description

A virtual base class for radiation facet parameters, used to create interaction facets for radiation in the Interaction-SurfaceFactorys.

Definition in file radiation_params.cc.

9.14 radiation_params.hh File Reference

A virtual base class for radiation facet parameters, used to create interaction facets for radiation in the Interaction-SurfaceFactorys.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "interactions/thermal_rider/include/thermal_params.hh"
#include "utils/surface_model/include/facet_params.hh"
```

Data Structures

· class jeod::RadiationParams

Provides a parameter list to each facet, based on the facet material properties.

Namespaces

• jeod

Namespace jeod.

9.14.1 Detailed Description

A virtual base class for radiation facet parameters, used to create interaction facets for radiation in the Interaction-SurfaceFactorys.

Definition in file radiation_params.hh.

9.15 radiation_pressure.cc File Reference

Calculation of force and torque due to radiation pressure.

82 File Documentation

```
#include <cstddef>
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "interactions/thermal_rider/include/thermal_facet_rider.hh"
#include "../include/radiation_pressure.hh"
#include "../include/radiation_third_body.hh"
#include "../include/radiation_source.hh"
#include "../include/radiation_messages.hh"
```

Namespaces

· jeod

Namespace jeod.

9.15.1 Detailed Description

Calculation of force and torque due to radiation pressure.

Definition in file radiation_pressure.cc.

9.16 radiation_pressure.hh File Reference

Radiation pressure top-level definition.

```
#include "utils/container/include/pointer_vector.hh"
#include "utils/sim_interface/include/jeod_class.hh"
#include "interactions/thermal_rider/include/thermal_model_rider.hh"
#include "radiation_source.hh"
#include "radiation_surface.hh"
#include "radiation_default_surface.hh"
```

Data Structures

· class jeod::RadiationPressure

Radiation pressure top-level definition.

Namespaces

jeod

Namespace jeod.

9.16.1 Detailed Description

Radiation pressure top-level definition.

Definition in file radiation_pressure.hh.

9.17 radiation_pressure__default_surface.cc File Reference

Calculation of force and torque due to radiation pressure.

```
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "utils/math/include/vector3.hh"
#include "interactions/thermal_rider/include/thermal_model_rider.hh"
#include "../include/radiation_pressure.hh"
#include "../include/radiation_default_surface.hh"
#include "../include/radiation_third_body.hh"
#include "../include/radiation_source.hh"
```

Namespaces

· jeod

Namespace jeod.

9.17.1 Detailed Description

Calculation of force and torque due to radiation pressure.

Definition in file radiation_pressure__default_surface.cc.

9.18 radiation_pressure__surface_model.cc File Reference

Calculation of force and torque due to radiation pressure.

```
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "utils/math/include/vector3.hh"
#include "interactions/thermal_rider/include/thermal_model_rider.hh"
#include "../include/radiation_pressure.hh"
#include "../include/radiation_surface.hh"
#include "../include/radiation_third_body.hh"
#include "../include/radiation_source.hh"
```

Namespaces

jeod

Namespace jeod.

9.18.1 Detailed Description

Calculation of force and torque due to radiation pressure.

Definition in file radiation_pressure__surface_model.cc.

9.19 radiation source.cc File Reference

Definition of methods associated with Primary Sources.

84 File Documentation

```
#include <cstddef>
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "utils/math/include/vector3.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/message/include/message_handler.hh"
#include "environment/planet/include/planet.hh"
#include "utils/ref_frames/include/ref_frame.hh"
#include "../include/radiation_source.hh"
#include "../include/radiation_messages.hh"
```

Namespaces

jeod

Namespace jeod.

9.19.1 Detailed Description

Definition of methods associated with Primary Sources.

Definition in file radiation_source.cc.

9.20 radiation_source.hh File Reference

Radiation pressure parameter and variable definitions.

```
#include <string>
#include <utility>
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

· class jeod::RadiationSource

Provides information on the source of the incident radiation.

Namespaces

· jeod

Namespace jeod.

9.20.1 Detailed Description

Radiation pressure parameter and variable definitions.

Definition in file radiation source.hh.

9.21 radiation surface.cc File Reference

Vehicle surface model for Radiation Pressure model.

```
#include <cstddef>
#include "dynamics/dyn_body/include/dyn_body.hh"
#include "utils/math/include/vector3.hh"
#include "utils/memory/include/jeod_alloc.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/surface_model/include/interaction_facet_factory.hh"
#include "utils/surface_model/include/interaction_facet.hh"
#include "utils/surface_model/include/facet.hh"
#include "../include/radiation_facet.hh"
#include "../include/radiation_surface.hh"
#include "../include/radiation_surface.hh"
#include "../include/radiation_messages.hh"
```

Namespaces

· jeod

Namespace jeod.

9.21.1 Detailed Description

Vehicle surface model for Radiation Pressure model.

Definition in file radiation surface.cc.

9.22 radiation surface.hh File Reference

Vehicle surface model for general environment interaction models.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/interaction_surface.hh"
#include "radiation_facet.hh"
```

Data Structures

· class jeod::RadiationSurface

The surface of the vehicle that interacts with the incident flux.

Namespaces

ieod

Namespace jeod.

9.22.1 Detailed Description

Vehicle surface model for general environment interaction models.

Definition in file radiation_surface.hh.

86 File Documentation

9.23 radiation_surface_factory.cc File Reference

Factory that creates an interaction surface, for a specific environment interaction model, from a surface model.

```
#include <cstddef>
#include "utils/message/include/message_handler.hh"
#include "../include/radiation_surface_factory.hh"
#include "../include/radiation_params.hh"
#include "../include/radiation_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

9.23.1 Detailed Description

Factory that creates an interaction surface, for a specific environment interaction model, from a surface model. Definition in file radiation_surface_factory.cc.

9.24 radiation_surface_factory.hh File Reference

Factory that creates an interaction surface, for a specific environment interaction model, from a surface model.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "utils/surface_model/include/interaction_surface_factory.hh"
#include "flat_plate_radiation_factory.hh"
```

Data Structures

· class jeod::RadiationSurfaceFactory

The factory for creating Radiation Surfaces.

Namespaces

jeod

Namespace jeod.

9.24.1 Detailed Description

Factory that creates an interaction surface, for a specific environment interaction model, from a surface model. Definition in file radiation_surface_factory.hh.

9.25 radiation_third_body.cc File Reference

Provides the functionality associated with RadiationThirdBodys.

```
#include <cstddef>
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "environment/planet/include/planet.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "../include/radiation_third_body.hh"
#include "../include/radiation_source.hh"
#include "../include/radiation_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

9.25.1 Detailed Description

Provides the functionality associated with RadiationThirdBodys.

Definition in file radiation_third_body.cc.

9.26 radiation_third_body.hh File Reference

Define the class RadiationThirdBody.

```
#include <string>
#include <utility>
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

· class jeod::RadiationThirdBody

Provide information on bodies that may cause shadowing or reflected illumination.

Namespaces

jeod

Namespace jeod.

9.26.1 Detailed Description

Define the class RadiationThirdBody.

Definition in file radiation_third_body.hh.

Index

\sim FlatPlateRadiationFacet	jeod::RadiationSurface, 57
jeod::FlatPlateRadiationFacet, 18	allocate_interaction_facet
\sim FlatPlateRadiationFactory	jeod::RadiationSurface, 57
jeod::FlatPlateRadiationFactory, 21	areaxflux
\sim RadiationBaseFacet	jeod::RadiationBaseFacet, 26
jeod::RadiationBaseFacet, 24	areaxflux_e
\sim RadiationDefaultSurface	jeod::RadiationBaseFacet, 26
jeod::RadiationDefaultSurface, 29	
\sim RadiationFacet	bodies_active
jeod::RadiationFacet, 33	jeod::RadiationSource, 51
\sim RadiationParams	
jeod::RadiationParams, 38	calculate_flux
\sim RadiationPressure	jeod::RadiationSource, 51
jeod::RadiationPressure, 41	calculate_forces
\sim RadiationSource	jeod::RadiationPressure, 46
jeod::RadiationSource, 50	calculate_shadow
\sim RadiationSurface	jeod::RadiationThirdBody, 67
jeod::RadiationSurface, 56	center_pressure
\sim RadiationSurfaceFactory	jeod::RadiationFacet, 34
jeod::RadiationSurfaceFactory, 62	Con
\sim RadiationThirdBody	jeod::RadiationSource, 50
jeod::RadiationThirdBody, 66	jeod::RadiationThirdBody, 66
	Conical
accumulate_rad_flux	jeod::RadiationSource, 50
jeod::RadiationThirdBody, 66	jeod::RadiationThirdBody, 66
accumulate_refl_flux	convert_shadow_from_int
jeod::RadiationThirdBody, 66	jeod::RadiationThirdBody, 67
accumulate_thermal_sources	create_facet
jeod::RadiationSurface, 57	jeod::FlatPlateRadiationFactory, 2
active	crot_to_cp
jeod::RadiationPressure, 46	jeod::RadiationFacet, 34
jeod::RadiationThirdBody, 69	cx_area
add_facet_params	jeod::RadiationBaseFacet, 26
jeod::RadiationSurfaceFactory, 62	Cyl
add_thermal_integrator_to	jeod::RadiationSource, 50
jeod::RadiationDefaultSurface, 29	jeod::RadiationThirdBody, 66
add_thermal_integrators_to	Cylindrical
jeod::RadiationSurface, 57	jeod::RadiationSource, 50
add_third_body	jeod::RadiationThirdBody, 66
jeod::RadiationPressure, 42	
added_to_model	d_source_to_cg
jeod::RadiationThirdBody, 70	jeod::RadiationSource, 52
albedo	d_source_to_third
jeod::RadiationBaseFacet, 25	jeod::RadiationThirdBody, 70
jeod::RadiationParams, 39	default_surface_ptr
albedo_IR	jeod::RadiationPressure, 46
jeod::RadiationBaseFacet, 25	define_facet
albedo_vis	jeod::FlatPlateRadiationFacet, 18
jeod::RadiationBaseFacet, 25	define_facet_core
allocate array	ieod::RadiationFacet, 33

diffuse	incident_flux_hat
jeod::RadiationBaseFacet, 26	jeod::FlatPlateRadiationFacet, 20
jeod::RadiationParams, 39	incident_radiation
dyn_manager_ptr	jeod::FlatPlateRadiationFacet, 18
jeod::RadiationPressure, 46	jeod::RadiationBaseFacet, 24
•	jeod::RadiationDefaultSurface, 29
equalize_absorption_emission	jeod::RadiationSurface, 57
jeod::RadiationSurface, 57	include_conduction
	jeod::RadiationSurface, 60
F_absorption	incomplete_setup_error
jeod::RadiationBaseFacet, 26	jeod::RadiationMessages, 36
F_diffuse	inertial_cg
jeod::RadiationBaseFacet, 27	jeod::RadiationSource, 53
F_emission	inertial_frame_ptr
jeod::RadiationBaseFacet, 27	jeod::RadiationSource, 53
F_specular	-
jeod::RadiationBaseFacet, 27	init_attrjeodFlatPlateRadiationFacet
facets	jeod::FlatPlateRadiationFacet, 19
jeod::RadiationSurface, 60	init_attrjeodFlatPlateRadiationFactory
find_third_body	jeod::FlatPlateRadiationFactory, 22
jeod::RadiationPressure, 42	init_attrjeodRadiationBaseFacet
flat_plate_radiation_facet.cc, 75	jeod::RadiationBaseFacet, 25
flat_plate_radiation_facet.hh, 75	init_attrjeodRadiationDefaultSurface
flat_plate_radiation_factory	jeod::RadiationDefaultSurface, 30
jeod::RadiationSurfaceFactory, 63	init_attrjeodRadiationFacet
flat_plate_radiation_factory.cc, 76	jeod::RadiationFacet, 34
flat_plate_radiation_factory.hh, 76	init_attrjeodRadiationMessages
FlatPlateRadiationFacet	jeod::RadiationMessages, 36
jeod::FlatPlateRadiationFacet, 18	init_attrjeodRadiationParams
FlatPlateRadiationFactory	jeod::RadiationParams, 39
jeod::FlatPlateRadiationFactory, 21	init_attrjeodRadiationPressure
	jeod::RadiationPressure, 46
flux_hat	init_attrjeodRadiationSource
jeod::RadiationSource, 52	jeod::RadiationSource, 51
flux_inertial	init_attrjeodRadiationSurface
jeod::RadiationSource, 52	jeod::RadiationSurface, 60
flux_mag	init_attrjeodRadiationSurfaceFactory
jeod::RadiationSource, 52	jeod::RadiationSurfaceFactory, 63
flux_struc	init_attrjeodRadiationThirdBody
jeod::RadiationSource, 52	jeod::RadiationThirdBody, 69
flux_struc_hat	initialize
jeod::RadiationSource, 52	jeod::RadiationBaseFacet, 24
force	jeod::RadiationDefaultSurface, 30
jeod::RadiationPressure, 46	jeod::RadiationDetautiounace, 30
jeod::RadiationSurface, 60	-
force_state_update	jeod::RadiationPressure, 42
jeod::RadiationThirdBody, 70	jeod::RadiationSource, 51
	jeod::RadiationSurface, 59
generate_alpha	jeod::RadiationThirdBody, 68
jeod::RadiationThirdBody, 67	initialize_environment
get_added_to_model	jeod::RadiationPressure, 44
jeod::RadiationThirdBody, 67	initialize_geom
get_thermal_integrator	jeod::FlatPlateRadiationFacet, 19
jeod::RadiationFacet, 33	jeod::RadiationFacet, 34
	initialize_runtime_values
ii_facet	jeod::RadiationBaseFacet, 24
jeod::RadiationSurface, 60	jeod::RadiationSurface, 59
illum_factor	initialized
jeod::RadiationPressure, 47	jeod::RadiationPressure, 47
jeod::RadiationThirdBody, 70	jeod::RadiationThirdBody, 70
•	

InputProcessor	\sim RadiationBaseFacet, 24
jeod::FlatPlateRadiationFacet, 19	albedo, 25
jeod::FlatPlateRadiationFactory, 22	albedo_IR, 25
jeod::RadiationBaseFacet, 25	albedo_vis, 25
jeod::RadiationDefaultSurface, 30	areaxflux, 26
jeod::RadiationFacet, 34	areaxflux_e, 26
jeod::RadiationMessages, 36	cx_area, 26
jeod::RadiationParams, 39	diffuse, 26
jeod::RadiationPressure, 46	F_absorption, 26
jeod::RadiationSource, 51	F_diffuse, 27
jeod::RadiationSurface, 60	F_emission, 27
jeod::RadiationSurfaceFactory, 63	F_specular, 27
jeod::RadiationThirdBody, 69	incident_radiation, 24
interact_with_third_body	init_attrjeodRadiationBaseFacet, 25
jeod::RadiationBaseFacet, 25	initialize, 24
jeod::RadiationSurface, 59	initialize_runtime_values, 24
Interactions, 12	InputProcessor, 25
invalid_function_call	interact with third body, 25
jeod::RadiationMessages, 36	operator=, 25
invalid_setup_error	RadiationBaseFacet, 24
jeod::RadiationMessages, 36	speed of light, 27
is_correct_factory	thermal, 27
jeod::FlatPlateRadiationFactory, 22	jeod::RadiationDefaultSurface, 28
is_interactive	\sim RadiationDefaultSurface, 29
jeod::RadiationThirdBody, 68	add_thermal_integrator_to, 29
total de	incident_radiation, 29
jeod, 15	init_attrjeodRadiationDefaultSurface, 30
jeod::RadiationSource	initialize, 30
Con, 50	InputProcessor, 30
Conical, 50	name, 31
Cyl, 50	operator=, 30
Cylindrical, 50	rad_coeff, 31
jeod::RadiationThirdBody	RadiationDefaultSurface, 29
Con, 66	set_name, 30
Conical, 66	surface_area, 31
Cylindrical 66	temperature, 31
Cylindrical, 66	thermal_update, 30
jeod::FlatPlateRadiationFacet, 17	jeod::RadiationFacet, 31
~FlatPlateRadiationFacet, 18 define facet, 18	\sim RadiationFacet, 33
FlatPlateRadiationFacet, 18	center_pressure, 34
incident flux hat, 20	crot_to_cp, 34
incident_radiation, 18	define_facet_core, 33
init attrjeod FlatPlateRadiationFacet, 19	get_thermal_integrator, 33
initialize_geom, 19	init attrjeod RadiationFacet, 34
InputProcessor, 19	initialize, 33
normal, 20	initialize geom, 34
operator=, 19	InputProcessor, 34
radiation_pressure, 19	operator=, 34
sin_theta, 20	radiation_pressure, 34
jeod::FlatPlateRadiationFactory, 20	RadiationFacet, 33
~FlatPlateRadiationFactory, 21	two_thirds, 35
create_facet, 21	jeod::RadiationMessages, 35
FlatPlateRadiationFactory, 21	incomplete_setup_error, 36
init_attrjeodFlatPlateRadiationFactory, 22	init_attrjeodRadiationMessages, 36
InputProcessor, 22	InputProcessor, 36
is_correct_factory, 22	invalid_function_call, 36
operator=, 22	invalid_setup_error, 36
jeod::RadiationBaseFacet, 22	operational_setup_error, 37
,	-p-:oo.sp_o., o,

	operator=, 36		luminosity, 53
	RadiationMessages, 36		multiple_shadow_bodies, 53
	unknown_numerical_error, 37		name, 53
jeod:	::RadiationParams, 37		num_bodies, 53
	\sim RadiationParams, 38		OldShadowGeometry, 50
	albedo, 39		operator=, 51
	diffuse, 39		RadiationSource, 50
	init_attrjeodRadiationParams, 39		radius, 53
	InputProcessor, 39		set_name, 51
	operator=, 39		shadow_geometry, 54
	RadiationParams, 38		solar_luminosity, 54
	thermal, 39		solar_radius, 54
	::RadiationPressure, 39		source_to_cg, 54
	\sim RadiationPressure, 41		source_to_struc_origin, 54
	active, 46		third_body, 54
	add_third_body, 42	jeod	::RadiationSurface, 55
	calculate_forces, 46		\sim RadiationSurface, 56
	default_surface_ptr, 46		accumulate_thermal_sources, 57
	dyn_manager_ptr, 46		add_thermal_integrators_to, 57
	find_third_body, 42		allocate_array, 57
	force, 46		allocate_interaction_facet, 57
	illum_factor, 47		equalize_absorption_emission, 57
	init_attrjeodRadiationPressure, 46		facets, 60
	initialize, 42		force, 60
	initialize_environment, 44		ii_facet, 60
	initialized, 47		incident_radiation, 57
	InputProcessor, 46		include_conduction, 60
	num_third_bodies, 47		init_attrjeodRadiationSurface, 60
	operator=, 44		initialize, 59
	RadiationPressure, 41		initialize_runtime_values, 59
	set_calculate_forces, 44		InputProcessor, 60
	set_third_body_active, 44		interact_with_third_body, 59
	set_third_body_inactive, 44		num_facets, 61
	source, 47		operator=, 59
	surface_ptr, 47		radiation_pressure, 59
	thermal, 47		RadiationSurface, 56
	third_bodies, 48		thermal_conduction, 61
	third_bodies_active, 48		thermal_integrator, 60
	third_body_adjustments, 45		torque, 61
	torque, 48	jeod	::RadiationSurfaceFactory, 61
	update, 45		\sim RadiationSurfaceFactory, 62
	update_default_surface, 45		add_facet_params, 62
	update_facet_surface, 45		flat_plate_radiation_factory, 63
jeod:	::RadiationSource, 48		init_attrjeodRadiationSurfaceFactory, 63
	\sim RadiationSource, 50		InputProcessor, 63
	bodies_active, 51		operator=, 63
	calculate_flux, 51		RadiationSurfaceFactory, 62
	d_source_to_cg, 52	jeod	::RadiationThirdBody, 63
	flux_hat, 52		\sim RadiationThirdBody, 66
	flux_inertial, 52		accumulate_rad_flux, 66
	flux_mag, 52		accumulate_refl_flux, 66
	flux_struc, 52		active, 69
	flux_struc_hat, 52		added_to_model, 70
	inertial_cg, 53		calculate_shadow, 67
	inertial_frame_ptr, 53		convert_shadow_from_int, 67
	init_attrjeodRadiationSource, 51		d_source_to_third, 70
	initialize, 51		force_state_update, 70
	InputProcessor, 51		generate_alpha, 67

get_added_to_model, 67	operational_setup_error
illum_factor, 70	jeod::RadiationMessages, 37
init_attrjeodRadiationThirdBody, 69	operator=
initialize, 68	jeod::FlatPlateRadiationFacet, 19
initialized, 70	jeod::FlatPlateRadiationFactory, 22
InputProcessor, 69	jeod::RadiationBaseFacet, 25
is_interactive, 68	jeod::RadiationDefaultSurface, 30
last_update_time, 70	jeod::RadiationFacet, 34
_ · _	
local_frame_ptr, 70	jeod::RadiationMessages, 36
name, 71	jeod::RadiationParams, 39
operator=, 68	jeod::RadiationPressure, 44
output_flux, 71	jeod::RadiationSource, 51
planet_link, 71	jeod::RadiationSurface, 59
primary_source_ptr, 71	jeod::RadiationSurfaceFactory, 63
process_third_body, 68	jeod::RadiationThirdBody, 68
r_minus, 71	output_flux
r_par, 71	jeod::RadiationThirdBody, 71
r_perp, 72	
r_plus, 72	PATH
r_ratio, 72	RadiationPressure, 14
RadiationThirdBody, 66	planet_link
radius, 72	jeod::RadiationThirdBody, 71
	primary_source_ptr
set_added_to_model, 68	jeod::RadiationThirdBody, 71
set_name, 69	process_third_body
shadow_geometry, 72	
ShadowGeometry, 66	jeod::RadiationThirdBody, 68
source_to_third_hat_inrtl, 72	r minuo
source_to_third_inrtl, 73	r_minus
test_for_state_update, 69	jeod::RadiationThirdBody, 71
third_to_cg_inrtl, 73	r_par
update_interval, 73	jeod::RadiationThirdBody, 71
update_third_body_state, 69	r_perp
· [- · · · · _ · · _ · _ · _ · _ ·]_ · · · ·	jeod::RadiationThirdBody, 72
last update time	r_plus
jeod::RadiationThirdBody, 70	jeod::RadiationThirdBody, 72
local_frame_ptr	r_ratio
jeod::RadiationThirdBody, 70	jeod::RadiationThirdBody, 72
luminosity	rad coeff
,	jeod::RadiationDefaultSurface, 31
jeod::RadiationSource, 53	radiation_base_facet.cc, 77
Models, 11	radiation_base_facet.hh, 77
·	radiation default surface.cc, 78
multiple_shadow_bodies	radiation_default_surface.bt, 78
jeod::RadiationSource, 53	
	radiation_facet.cc, 79
name	radiation_facet.hh, 79
jeod::RadiationDefaultSurface, 31	radiation_messages.cc, 80
jeod::RadiationSource, 53	radiation_messages.hh, 80
jeod::RadiationThirdBody, 71	radiation_params.cc, 81
normal	radiation_params.hh, 81
jeod::FlatPlateRadiationFacet, 20	radiation_pressure
num bodies	jeod::FlatPlateRadiationFacet, 19
jeod::RadiationSource, 53	jeod::RadiationFacet, 34
num facets	jeod::RadiationSurface, 59
jeod::RadiationSurface, 61	radiation_pressure.cc, 81
num_third_bodies	radiation_pressure.hh, 82
	radiation_pressuredefault_surface.cc, 83
jeod::RadiationPressure, 47	-
OldShadawGaamater	radiation_pressuresurface_model.cc, 83
OldShadowGeometry	radiation_source.cc, 83
jeod::RadiationSource, 50	radiation_source.hh, 84

radiation_surface.cc, 84	jeod::RadiationSource, 54		
radiation_surface.hh, 85	source_to_third_hat_inrtl		
radiation_surface_factory.cc, 86	jeod::RadiationThirdBody, 72		
radiation_surface_factory.hh, 86	source_to_third_inrtl		
radiation_third_body.cc, 86	jeod::RadiationThirdBody, 73		
radiation third body.hh, 87	speed_of_light		
RadiationBaseFacet	jeod::RadiationBaseFacet, 27		
jeod::RadiationBaseFacet, 24	surface area		
RadiationDefaultSurface	jeod::RadiationDefaultSurface, 31		
jeod::RadiationDefaultSurface, 29	surface_ptr		
RadiationFacet	jeod::RadiationPressure, 47		
jeod::RadiationFacet, 33	tomporaturo		
RadiationMessages	temperature		
jeod::RadiationMessages, 36	jeod::RadiationDefaultSurface, 31		
RadiationParams	test_for_state_update		
jeod::RadiationParams, 38	jeod::RadiationThirdBody, 69		
RadiationPressure, 13	thermal		
jeod::RadiationPressure, 41	jeod::RadiationBaseFacet, 27		
PATH, 14	jeod::RadiationParams, 39		
RadiationSource	jeod::RadiationPressure, 47		
jeod::RadiationSource, 50	thermal_conduction		
RadiationSurface	jeod::RadiationSurface, 61		
jeod::RadiationSurface, 56	thermal_integrator		
RadiationSurfaceFactory	jeod::RadiationSurface, 60		
jeod::RadiationSurfaceFactory, 62	thermal update		
	jeod::RadiationDefaultSurface, 30		
RadiationThirdBody	third bodies		
jeod::RadiationThirdBody, 66	jeod::RadiationPressure, 48		
radius	-		
jeod::RadiationSource, 53	third_bodies_active		
jeod::RadiationThirdBody, 72	jeod::RadiationPressure, 48		
	third_body		
set_added_to_model	jeod::RadiationSource, 54		
jeod::RadiationThirdBody, 68	third_body_adjustments		
set_calculate_forces	jeod::RadiationPressure, 45		
jeod::RadiationPressure, 44	third_to_cg_inrtl		
set_name	jeod::RadiationThirdBody, 73		
jeod::RadiationDefaultSurface, 30	torque		
jeod::RadiationSource, 51	jeod::RadiationPressure, 48		
jeod::RadiationThirdBody, 69	jeod::RadiationSurface, 61		
set_third_body_active	two thirds		
jeod::RadiationPressure, 44	jeod::RadiationFacet, 35		
set_third_body_inactive	,		
jeod::RadiationPressure, 44	unknown_numerical_error		
shadow_geometry	jeod::RadiationMessages, 37		
jeod::RadiationSource, 54	update		
jeod::RadiationTource, 34 jeod::RadiationThirdBody, 72	jeod::RadiationPressure, 45		
· ·	update default surface		
ShadowGeometry	· – –		
jeod::RadiationThirdBody, 66	jeod::RadiationPressure, 45		
sin_theta	update_facet_surface		
jeod::FlatPlateRadiationFacet, 20	jeod::RadiationPressure, 45		
solar_luminosity	update_interval		
jeod::RadiationSource, 54	jeod::RadiationThirdBody, 73		
solar_radius	update_third_body_state		
jeod::RadiationSource, 54	jeod::RadiationThirdBody, 69		
source			
jeod::RadiationPressure, 47			
source_to_cg			
jeod::RadiationSource, 54			
source_to_struc_origin			
 			