

REHEARSAL WALK

Shaper Assistant · the live site, www.shaperassistant.com · sheet of Tuesday 6 October 2026 (issue 3). It replaces the 3 October sheet: it adds the Board Rack, the home page's new place for your saved boards (step 12 reworded, step 13 new, the old steps 13 to 17 now 14 to 18, and four looks at the rack on page 3).

DONE ON 3 OCT
1 Google sign-in open to everyone ✓ · 2 Room for a crowd ✓ · 3 A new email sign-up on a phone ✓ · 7 A friend's Google sign-up ✓

STILL TO DO
4 iPhone walk · 5 Android walk · 6 Laptop walk · 8 Demo account · 9 The freeze, Wednesday 7 October evening

HOW TO MARK
Tick a box for a pass. For a fail, put a cross and write what happened in your own words; that sentence becomes the fix. About 25 minutes a device. Use Google to sign in on one device and email on another.

NEVER WRITE DOWN
Anything you typed into a sign-in form: no email address, password or code, and no screenshot showing one. Only whether it worked.

NEW IN THIS ISSUE (6 OCT)
The Board Rack: your saved boards stand side by side on the home page and turn as you pass. Steps 12 and 13 and the rack's four looks need it on the live site, and it goes live only on your go, so walk those once it has. On a phone you move a board by holding it until it lifts, then sliding it, the way you kept it after trying it on your iPad and an Android phone. The 3 October fix (ROCKER's tail Automatic button clear of Redo) is still live, so step 6 should simply pass.

THE WALK · STEPS 1 TO 6

#	DO THIS	LOOK FOR	IPHONE	ANDROID	LAPTOP
1	Text yourself www.shaperassistant.com and tap the link (laptop: type the address)	The preview card with the board picture and “Shaper Assistant — Surfboard Shaping and Design”; the home screen opens	☐	☐	☐
2	Read the four preset cards	Shortboard 6'2" · 18 3/4" · 2 1/4" · 29.6 L Fish 5'8" · 20 1/4" · 2 1/2" · 35.3 L Mid-length 7'2" · 21 1/4" · 2 3/4" · 50.4 L Longboard 9'0" · 22 1/2" · 3" · 73.9 L	☐	☐	☐
3	Sign in with your own account (phones: in the menu, top right; laptop: Sign in, in the top bar)	The keyboard never hides the field you're typing in; any code arrives within a minute; you land back signed in	☐	☐	☐
4	Start Shaping on a preset → TEMPLATE: drag an outline point, then Undo and Redo	The point follows your finger or mouse and the numbers update; the Undo and Redo pair appears at the bottom right and puts it back exactly; a faint line shows the shape before the change, and the ghost button in the drawing's corner hides it	☐	☐	☐
5	ROCKER: press Change Blank and pick another blank, slide Placement, drag Deck Skin	The list opens, shortest first, with greyed blanks saying where they don't fit; the picked blank, the drawing, the foam-off numbers and the planer passes follow you	☐	☐	☐
6	ROCKER, at the end of the controls: drag Nose Thinning Starts and Tail Thinning Starts, then press Automatic on each	The label follows the drag (12" to 13"), the hint reads “Automatic would be 12”” and the dashed mark on the drawing moves; Automatic puts it back and the hint reads “Picked automatically”; the DATASHEET tab shows THINNING STARTS	☐	☐	☐

THE WALK · STEPS 7 TO 18

#	DO THIS	LOOK FOR	IPHONE	ANDROID	LAPTOP
7	RAILS: View Full Sized, then each tab including INSTRUCTIONS, where you flip Flat / Domed	Nothing cut off; View Full Sized opens and Close shuts it	☐	☐	☐
8	VOLUME: note the litres; change width or thickness on TEMPLATE; come back	The litres change and read sensibly	☐	☐	☐
9	FINS: change the fin setup; tick and untick Import Template Values	The fin numbers and the drawing follow	☐	☐	☐
10	SUMMARY: read the order form, then Print Order Form — print for real or save as a PDF	Both pages complete and legible. Page 2's Planing box ends "Thinning starts from the tip: nose ..., tail" inside its box. On the iPhone, page 2's rail markings and fin numbers each sit inside their own box	☐	☐	☐
11	SUMMARY: Export Template → Overview Sheet → Download PDF	A PDF of the board opens or downloads	☐	☐	☐
12	Save (top bar) with a name → tap the wordmark for home → open the board from the Board Rack → rename it, duplicate it, delete the copy	The same board comes back, with its blank and any Thinning Start you set by hand; Cancel is easy to hit on the delete question	☐	☐	☐
13	NEW Board Rack, at home: look along the rack (laptop: move the mouse along it and rest on a board; phones: swipe along it), then move a board (laptop: drag it, or ... → Move right; phones: hold it until it lifts, then slide it), reload, then open the home page on another device	Each board turns to show its outline as you pass, with its name and numbers under the one that's turned; the board moves where you put it and a small note says "Moved ... The rack keeps your order."; after the reload, and on your other device, the order is the same; the unsaved board always stands first	☐	☐	☐
14	App Default Settings (the gear on a laptop, ≡ on a phone) → Metric; look at ROCKER and SUMMARY; switch back to Imperial	Centimetres for sizes, millimetres for marks; Thinning Starts read in centimetres (30.5 cm for 12"); back in Imperial every number is exactly what it was	☐	☐	☐
15	Menu → Contact, then Privacy. Send one Contact message from one device only	Both pages open; the message reaches support@ in Zoho	☐	☐	☐
16	Type a wrong address, e.g. www.shaperassistant.com/xyz	"We couldn't find that page", with a way home	☐	☐	☐
17	Phones: turn sideways on a design screen, then upright again	Sideways the top bar stays one thin line (wordmark, Save, menu) with the six screens in the menu, and the controls sit beside the board; no sideways scrolling; upright stacks them again	☐	☐	N/A
18	Sign out, then sign back in	Your boards are all still there	☐	☐	☐

Laptop extras: use the browser you'll present from. If a projector or TV will be used, walk at least steps 2 to 10 on it and pick the theme that reads best from the back of the room. Print one order form on a real printer.

PHASE 14'S FIVE LOOKS · SAME SITTING

	ON	DO THIS	WHAT GOOD IS	OK
A	A phone, then the laptop	In Metric on ROCKER, drag each Thinning Starts slider to both ends. On the laptop, click a slider that is on Automatic and press the arrow keys	On the Shortboard the ends read 16.0 cm and 93.0 cm and nothing jumps. A start set at 6" in Imperial reads 15.2 cm in Metric with the thumb at the left end. From 30.5 cm the right arrow steps to 31.0 and 32.0 and the left arrow back, with no jump on the first press	☐
B	Paper	Print page 2 of the order form with a blank picked: on Letter, on A4 if you have it, and from a phone	The Planing box ends "Thinning starts from the tip: nose 12", tail 12"." (in Metric, "nose 30.5, tail 30.5 cm."), on two lines at most, inside its box	☐
C	Both phones	With Change Blank's list open, drag a Thinning Starts slider, slide Placement end to end and change a tip setting	The list and the fit flag keep up; no stutter or freeze	☐
D	The laptop	In each of the four themes, look at ROCKER's drawing with a blank picked and both starts at 12"	The faint dashed mark can be picked out where it meets the 12" line. At go-live 2 you found it hard to pick out on a computer and asked for no change; confirm that still stands	☐
E	The laptop	In a private window open www.shaperassistant.com/design/volume , then ROCKER: the first board a visitor sees. Then the thin-board corner you saw at go-live 2	VOLUME reads 30.51 L and the curves read the way a board flows. The thin-board corner (a 1" to 1 1/4" center on the Arctic Foam 7'9" SBF, its tail reading below the center) is still what you want to leave for the showing	☐

PHASE 15'S FOUR LOOKS · THE BOARD RACK · SAME SITTING

	ON	DO THIS	WHAT GOOD IS	OK
A	A phone held sideways (the iPhone, then the Android)	Give a board a long name, 20 letters or more (e.g. "Ocean Beach Winter Step-Up"), and look along the rack	The long name is cut with "... " and what's left still reads; its numbers stay whole and nothing runs into the next board	☐
B	The iPhone	Move a board, then look at the bottom of the screen while the small note shows	The note "Moved ... The rack keeps your order." reads in full and doesn't cover Open This Board under the turned board	☐
C	The iPhone, with VoiceOver on (Settings → Accessibility → VoiceOver)	Swipe through two boards on the rack	Each board's full name is read out, even a long one that is cut on screen, and the way its numbers are spoken (the inch marks) is tolerable to listen to	☐
D	The laptop, in Chrome	Click a board on the rack, then hold Alt and press ←	The board moves one place left and the browser never goes Back to the previous page	☐

Both tables belong to their phase's own sign-off, not to the nine checks. They need the same devices, so do them in the same sitting and report them with the walk.

WHAT FAILED, IN YOUR OWN WORDS (DEVICE AND STEP NUMBER FIRST)

CHECK 8 · THE DEMO ACCOUNT

A separate demo account, so nothing typed during the demo touches your real boards (your call). For example one signed up on support@shaperassistant.com, whose codes land in Zoho.

BOARD (NAME IT THE WAY A SHAPER WOULD)	BLANK PICKED ON ROCKER	FINS SET ON FINS	OPENS ON THE LAPTOP	ORDER FORM PRINTED
1.	☐	☐	☐	☐
2.	☐	☐	☐	☐
3.	☐	☐	☐	☐
4.	☐	☐	☐	☐

One board per family is a good spread. A blank picked on ROCKER is what puts numbers in the order form's Planing table. A few printed order forms also make handouts for the room.

CHECK 9 · THE FREEZE, WEDNESDAY 7 OCTOBER EVENING

- ☐ The walk has passed on all three devices, or passed after fixes.
- ☐ Claude tags the live build and writes down the Vercel deployment it runs on; the tag goes to GitHub on your go.
- ☐ From then on nothing is pushed, and nothing is changed in Clerk, Google, Neon or Vercel, except a fix for something this walk found, on your go. At most one fix should follow the freeze.

THE DEMO-DAY CARD

The address	www.shaperassistant.com
For shapers' questions	support@shaperassistant.com
Demo account (its name, never its password)	
Live build (tag) and Vercel deployment	
Backup connection	Your phone's hotspot

IF THE SITE MISBEHAVES ON THE DAY

Vercel → the shaper project → the Production Deployment → Instant Rollback → Continue → Confirm Rollback.

On the free plan that goes back one deployment only. A rollback also stops new pushes going live until Undo Rollback is pressed, so tell Claude when you've used it.

IF SIGN-UPS STALL IN THE ROOM

One Wi-Fi is one internet address, and Clerk lets one address start 5 sign-ups every 10 seconds. A "too many requests" message clears after ten seconds.

Continue with Google is the quickest. Or ask people to use their phone's own data, or sign up a few at a time. Looking round the app signed out is never limited.