Interface view: E&M Borgerstamdata

By: Beemen Beshara

Contents

JY64000V: Borger (Citizen)

This interface view retrieves information from the following tables: Borger

One of the following keys should be used in queries:

BORGER   Kommunenummer
             Personnummer

No	Field name	Description	Field Type	Code table
1	PERSONNUMMER	PNR	decimal(11)	
2	KOMMUNENUMMER	Municipality number	smallint	
3	FODSEL_DATO	Date of birth	datetime	
4	PERSONNR_OPRETDATO	PNR creation date	datetime	
5	PERSONNR_MRK_DATO	PNR marking date	datetime	
6	KON	Gender	char(1)	
7	STILLING	Occupation	char(34)	
8	STILLING_DATO	Occupation date	datetime	
9	ADRESSERINGSNAVN	Addressing name	char(34)	
10	ADRNAVN_DATO	Addressing name date	datetime	
11	FOLKEKIRKE_MYND_KD	National church authority code	smallint	
12	FOLKEKIRK_TILH_MRK	National church marker	char(1)	
13	FOLKEKIRK_MRK_DATO	National church marker date	datetime	
14	BORGERSTATUS_KODE	Citizen status code	smallint	QL58900V
15	BORGERSTATUS_TS	Citizen status timestamp	datetime	
16	FODSELSREG_MYND_KD	Birth registration authority code	smallint	
17	FODSELSREG_DATO	Birth registration date	datetime	
18	FODESTED_TEKST	Birthplace text	char(20)	
19	ANTAL_BORN	Number of children	smallint	
20	CPR_FOLKEKIRKE_TS	CPR national church timestamp	datetime	
21	CPR_PERSON_TS	CPR person timestamp	datetime	
22	ADR_TILFLYT_TS	Arrival timestamp	datetime	
23	VEJ_KODE	Road code	smallint	
24	HUS_NUMMER	House number/letter	char(4)	
25	ETAGE	Floor	char(2)	
26	SIDE_DORNR	Door	char(4)	
27	BYGNING_NUMMER	Building number	char(4)	
28	ADR_FRAFLYT_TS	Departure timestamp	datetime	
29	CO_NAVN	C/O name	char(34)	
30	VEJSIDE_F_LIG_ULIG	Odd / Even road side	char(1)	
31	KOM_TILFLYTDATO	Municipality arrival date	datetime	
32	FRAFLYT_KOMMUNENR	Departure municipality code	smallint	
33	ADRESSEBESKYT_DATO	Address protection date	datetime	
34	ADR_BESKYT_SLTDATO	Address protection removal date	datetime	

35	VEJVIS_BESKYT_DATO	Diretory protection date	datetime	
36	CIVILSTAND_TS	Marital status timestamp	datetime	
37	CIVILSTAND	Marital status	char(1)	QL58800V
38	CIVILST_OPHOR_TS	Marital status termination timestamp	datetime	
39	PERSONNR_AGTEFALLE	Spouse PNR	decimal(11)	
40	AGTEFALLE_FLAG	Spouse flag	char(1)	
41	LAND_KODE	Country code	smallint	QL59400V
42	STATSB_RET_TS	Nationality change timestamp	datetime	
43	STATBORG_OPHOR_TS	Nationality termination timestamp	datetime	
44	PERSONNUMMER_MOR	Mother PNR	decimal(11)	
45	PERSONNUMMER_FAR	Father PNR	decimal(11)	
46	MOR_DOK	Mother document	char(3)	
47	FAR_DOK	Father document	char(3)	
48	VEJVIS_BESK_SLTDTO	Directory protection end date	datetime	
49	FODSEL_UM	Birthdate uncertainty	char(1)	
50	PERSONNR_OPRET_UM	PNR creationdate uncertainty	char(1)	
51	PERSONNR_MRK_UM	PNR marking date uncertainty	char(1)	
52	STILLING_UM	Post date uncertainty	char(1)	
53	ADRNAVN_UM	Addressing name uncertainty	char(1)	
54	FOLKEKIRK_MRK_UM	National church marker uncertainty	char(1)	
55	BORGERSTATUS_UM	Citizen status timestamp uncertainty	char(1)	
56	FODSELSREG_UM	Birth registration date uncertainty	char(1)	
57	ADR_TILFLYT_UM	Arrival timestamp uncertainty	char(1)	
58	ADR_FRAFLYT_UM	Departure timestamp uncertainty	char(1)	
59	KOM_TILFLYT_UM	Municipality arrival timestamp uncertainty	char(1)	
60	ADR_BESKYT_UM	Address protection date uncertainty	char(1)	
61	ADR_BESKYT_SLT_UM	Address protection termination date uncertainty	char(1)	
62	VEJVIS_BESKYT_UM	Directory protection date uncertainty	char(1)	
63	CIVILSTAND_UM	Marital status timestamp uncertainty	char(1)	
64	CIVILST_OPHOR_UM	marital status termination timestamp uncertainty	char(1)	
65	STATSB_RET_UM	Nationality change timestamp uncertainty	char(1)	
66	STATBORG_OPHOR_UM	Nationality termination timestamp uncertainty	char(1)	
67	VEJVIS_BESK_SLT_UM	directory protection removal date uncertainty	char(1)	

JY64100V: Bosættelse (Resettlement)

This interface view retrieves information from the following tables: Bosættelse (Resettlement)

One of the following keys should be used in queries:

BORGER (Citizen)   Kommunenummer (Municipality code)
                         Personnummer (PNR)

No	Field name	Description	Field Type	Code table
1	KOMMUNENUMMER	Municipality code	smallint	
2	PERSONNUMMER	PNR	decimal(11)	
3	ADR_TILFLYT_TS	Arrival timestamp	datetime	
4	VEJ_KODE	Road code	smallint	
5	HUS_NUMMER	House number/letter	char(4)	
6	ETAGE	Floor	char(2)	
7	SIDE_DORNR	Door	char(4)	
8	BYGNING_NUMMER	Building number	char(4)	
9	ADR_FRAFLYT_TS	Departure timestamp	datetime	
10	ADRESSE_KORR_MRK	Address correction marker	char(1)	
11	CO_NAVN	C/O Name	char(34)	
12	KOM_FRAFLYTDATO	Municipality departure date	datetime	
13	FRAFLYT_KOMMUNENR	Departure municipality code	smallint	
14	KOM_TILFLYTDATO	Municipality arrival date	datetime	
15	CPR_BOSAT_TS	CPR resettlement timestamp	datetime	
16	VEJSIDE_F_LIG_ULIG	Odd / Even road side	char(1)	
17	ADR_TILFLYT_MRK	Arrival marker	char(1)	
18	ADR_TILFLYT_UM	Arrival timestamp uncertainty	char(1)	
19	ADR_FRAFLYT_UM	Departure timestamp uncertainty	char(1)	
20	KOM_TILFLYT_UM	Municipality arrival date uncertainty	char(1)	
21	KOM_FRAFLYT_UM	Municipality departure date uncertainty	char(1)	

JY64200V: Børnetabel (Children table)

This interface view retrieves information from the following tables: Forældreskab (Parenthood)

One of the following keys should be used in queries:

PERSON Personnummer

No	Field name	Description	Field Type	Code table
1	PERSONNUMMER	PNR	decimal(11)	
2	PERSONNUMMER_MOR	Mother PNR	decimal(11)	
3	PERSONNUMMER_FAR	Father PNR	decimal(11)	
4	MOR_DOK	Mothet document	char(3)	
5	FAR_DOK	Father document	char(3)	
6	BORGERSTATUS_KODE	Citizen status code	smallint	QL58900V

JY64300V: Aktiv borger (Active citizen)

This interface view retrieves information from the following tables: Borger (Citizen)

One of the following keys should be used in queries:

BORGER (Citizen)   Kommunenummer (Municipality code)
                              Personnummer (PNR)

No	Field name	Description	Field Type	Code table
1	PERSONNUMMER	PNR	decimal(11)	
2	KOMMUNENUMMER	Municipality code	smallint	
3	FODSEL_DATO	Date of birth	datetime	
4	KON	Gender	char(1)	
5	STILLING	Occupation	char(34)	
6	STILLING_DATO	Occupation date	datetime	
7	ADRESSERINGSNAVN	Addressing name	char(34)	
8	ADRNAVN_DATO	Addressing name date	datetime	
9	FOLKEKIRK_TILH_MRK	National church marker	char(1)	
10	FOLKEKIRK_MRK_DATO	National church marker date	datetime	
11	BORGERSTATUS_KODE	Citizen status code	smallint	QL58900V
12	BORGERSTATUS_TS	Citizen status code timestamp	datetime	
13	ANTAL_BORN	Number of children	smallint	
14	ADR_TILFLYT_TS	Arrival timestamp	datetime	
15	VEJ_KODE	Road code	smallint	
16	HUS_NUMMER	House number/letter	char(4)	
17	ETAGE	Floor	char(2)	
18	SIDE_DORNR	Door	char(4)	
19	BYGNING_NUMMER	Building number	char(4)	
20	ADR_FRAFLYT_TS	Departure timestamp	datetime	
21	CO_NAVN	C/O name	char(34)	
22	KOM_TILFLYTDATO	Municipality arrival date	datetime	
23	FRAFLYT_KOMMUNENR	Departure municipality code	smallint	
24	ADRESSEBESKYT_DATO	Address protection date	datetime	
25	ADR_BESKYT_SLTDATO	Address protection termination date	datetime	
26	CIVILSTAND_TS	Marital status timestamp	datetime	
27	CIVILSTAND	Marital status	char(1)	QL58800V
28	CIVILST_OPHOR_TS	Marital status termination date	datetime	
29	PERSONNR_AGTEFALLE	Spouse PNR	decimal(11)	
30	AGTEFALLE_FLAG	Spouse flag	char(1)	
31	LAND_KODE	Country code	smallint	QL59400V
32	STATSB_RET_TS	Nationality change timestamp	datetime	
33	STATBORG_OPHOR_TS	Nationality termination timestamp	datetime	
34	PERSONNUMMER_MOR	Mother PNR	decimal(11)	

35	PERSONNUMMER_FAR	Father PNR	decimal(11)	
36	MOR_DOK	Mother document	char(3)	
37	FAR_DOK	Father document	char(3)	
38	BORGERSTATUS_UM	Citizen status timestamp uncertainty	char(1)	
39	FODSELSREG_UM	Birth registration date uncertainty	char(1)	

JY64400V: Postnummer (Post code)

This interface view retrieves information from the following tables:

Bosættelse (Resettlement)

Vejinddeling - Postnummer (Road subdivision - Postcode)

Vejdistrikt (Road District)

One of the following keys should be used in queries:

ADRESSEBYG (address book???)   Kommunenummer (Municipality code)
Vejkode (Road code)
Husnummer (House number)

No	Field name	Description	Field Type	Code table
1	KOMMUNENUMMER	Municipality code	smallint	
2	VEJ_KODE	Road code	smallint	
3	HUS_NUMMER	House number/letter	char(4)	
4	POSTNR	Post code	smallint	
5	POSTDISTRIKT	Post district	char(20)	

JY67800V: Borger grydeklar adresse (Citizen pot ready address)

No	Field name	Description	Field Type	Code table
1	EKOMNR	Municipality code	smallint	
2	PERSONNUMMER	PNR	decimal(11)	
3	ADRESSERINGSNAVN	Addressing name	char(34)	
4	CO_NAVN	C/O name	char(34)	
5	VEJ_KODE	Road code	smallint	
6	VEJ_NAVN	Road name	char(20)	
7	HUS_NUMMER	House number/letter	char(4)	
8	ETAGE	Floor	char(2)	
9	SIDE_DORNR	Door	char(4)	
10	BYNAVN	City name	char(34)	
11	POSTNR	Post code	smallint	
12	POSTDISTRIKT	Post district	char(20)	

JY68800V: Borger - afdøde (Citizen-dead)

No	Field name	Description	Field Type	Code table
1	EKOMNR	Municipality code	smallint	
2	PERSONNUMMER	PNR	decimal(11)	
3	ADRESSERINGSNAVN	Adressing name	char(34)	
4	CO_NAVN	C/O name	char(34)	
5	VEJ_KODE	Road code	smallint	
6	VEJ_NAVN	Road name	char(20)	
7	HUS_NUMMER	House number/letter	char(4)	
8	ETAGE	Floor	char(2)	
9	SIDE_DORNR	Door	char(4)	
10	BYNAVN	City name	char(34)	
11	POSTNR	Post code	smallint	
12	POSTDISTRIKT	Post district	char(20)	
13	BORGERSTATUS_KODE	Citizen status code	smallint	QL58900V
14	BORGERSTATUS_TS	Citizen status timestamp	datetime	