Redis - Configuration

In Redis, there is a configuration file (redis.conf) available at the root directory of Redis. Although you can get and set all Redis configurations by Redis **CONFIG** command.

Syntax

Following is the basic syntax of Redis **CONFIG** command.

```
redis 127.0.0.1:6379> CONFIG GET CONFIG_SETTING_NAME
```

Example

```
redis 127.0.0.1:6379> CONFIG GET loglevel

1) "loglevel"

2) "notice"
```

To get all configuration settings, use * in place of CONFIG_SETTING_NAME

Example

```
redis 127.0.0.1:6379> CONFIG GET *

1) "dbfilename"

2) "dump.rdb"

3) "requirepass"

4) ""

5) "masterauth"

6) ""

7) "unixsocket"

8) ""

9) "logfile"

10) ""

11) "pidfile"

12) "/var/run/redis.pid"

13) "maxmemory"

14) "0"
```

15) "maxmemory-samples" 16) "3" 17) "timeout" 18) "0" 19) "tcp-keepalive" 20) "0" 21) "auto-aof-rewrite-percentage" 22) "100" 23) "auto-aof-rewrite-min-size" 24) "67108864" 25) "hash-max-ziplist-entries" 26) "512" 27) "hash-max-ziplist-value" 28) "64" 29) "list-max-ziplist-entries" 30) "512" 31) "list-max-ziplist-value" 32) "64" 33) "set-max-intset-entries" 34) "512" 35) "zset-max-ziplist-entries" 36) "128" 37) "zset-max-ziplist-value" 38) "64" 39) "hll-sparse-max-bytes" 40) "3000" 41) "lua-time-limit" 42) "5000" 43) "slowlog-log-slower-than" 44) "10000" 45) "latency-monitor-threshold" 46) "0" 47) "slowlog-max-len" 48) "128" 49) "port" 50) "6379" 51) "tcp-backlog" 52) "511" 53) "databases" 54) "16" 55) "repl-ping-slave-period"

56) "10"

57) "repl-timeout" 58) "60" 59) "repl-backlog-size" 60) "1048576" 61) "repl-backlog-ttl" 62) "3600" 63) "maxclients" 64) "4064" 65) "watchdog-period" 66) "0" 67) "slave-priority" 68) "100" 69) "min-slaves-to-write" 70) "0" 71) "min-slaves-max-lag" 72) "10" 73) "hz" 74) "10" 75) "no-appendfsync-on-rewrite" 76) "no" 77) "slave-serve-stale-data" 78) "yes" 79) "slave-read-only" 80) "yes" 81) "stop-writes-on-bgsave-error" 82) "yes" 83) "daemonize" 84) "no" 85) "rdbcompression" 86) "yes" 87) "rdbchecksum" 88) "yes" 89) "activerehashing" 90) "yes" 91) "repl-disable-tcp-nodelay" 92) "no" 93) "aof-rewrite-incremental-fsync" 94) "yes" 95) "appendonly" 96) "no" 97) "dir" 98) "/home/deepak/Downloads/redis-2.8.13/src"

```
99) "maxmemory-policy"
100) "volatile-lru"
101) "appendfsync"
102) "everysec"
103) "save"
104) "3600 1 300 100 60 10000"
105) "loglevel"
106) "notice"
107) "client-output-buffer-limit"
108) "normal 0 0 0 slave 268435456 67108864 60 pubsub 33554432 8388608 60"
109) "unixsocketperm"
110) "0"
111) "slaveof"
112) ""
113) "notify-keyspace-events"
114) ""
115) "bind"
116) ""
```

Edit Configuration

To update configuration, you can edit **redis.conf** file directly or you can update configurations via **CONFIG set** command.

Syntax

Following is the basic syntax of **CONFIG SET** command.

```
redis 127.0.0.1:6379> CONFIG SET CONFIG_SETTING_NAME NEW_CONFIG_VALUE
```

Example

```
redis 127.0.0.1:6379> CONFIG SET loglevel "notice"
OK
redis 127.0.0.1:6379> CONFIG GET loglevel
1) "loglevel"
2) "notice"
```