

CS3281 / CS5281

I/O Devices

CS3281 / CS5281 Spring 2025

*Some lecture slides borrowed and adapted from Andrea Arpaci-Dusseau



Motivation

What good is a computer without any I/O devices?

- e.g., keyboard, display, disks

We want:


- H/W that will let us plug in different devices
- OS that can interact with different combinations

- I/O also allows for persistence
 - RAM is volatile, i.e., contents are lost when the machine restarts





Hardware support for I/O







Canonical Device

OS reads/writes to these

Device Registers:







Canonical Device

Device Registers:

Status COMMAND DATA

Hidden Internals:

????





Canonical Device

OS reads/writes to these

Device Registers:

Status

COMMAND

DATA

Hidden Internals:

Microcontroller (CPU+RAM)


Extra RAM

Other special-purpose chips





Example Write Protocol



```
while (STATUS == BUSY)
  ; // spin
Write data to DATA register
Write command to COMMAND register
while (STATUS == BUSY)
  ; // spin
```

This is called <u>polling</u> when the processor "asks" what the hardware is doing, often continuously





```
CPU:
Disk:
  while (STATUS == BUSY) // 1
  Write data to DATA register
  Write command to COMMAND register // 3
  while (STATUS == BUSY) // 4
```

```
CPU: A

Disk: C
```


```
while (STATUS == BUSY)  // 1
;
Write data to DATA register  // 2
Write command to COMMAND register // 3
while (STATUS == BUSY)  // 4
:
```

```
A wants to do I/O
CPU:
Disk:
  while (STATUS == BUSY) // 1
  Write data to DATA register
  Write command to COMMAND register // 3
  while (STATUS == BUSY)
                       // 4
```

```
while (STATUS == BUSY)  // 1
;
Write data to DATA register  // 2
Write command to COMMAND register // 3
while (STATUS == BUSY)  // 4
```

Write command to COMMAND register // 3
while (STATUS == BUSY) // 4

```
CPU:
Disk:
  while (STATUS == BUSY)
                              // 1
  Write data to DATA register
  Write command to COMMAND register // 3
  while (STATUS == BUSY)
                             // 4
```



how to avoid spinning? 3,4 CPU: В В Disk: while (STATUS == BUSY) // 1 Passively wait for interrupt; Write data to DATA register Write command to COMMAND register // 3 while (STATUS == BUSY) // 4 Passively wait for interrupt;

interrupts!

Interrupts vs. Polling

Are interrupts ever worse than polling?

Fast device: Better to spin than take interrupt and context-switching overhead

Device time unknown? Hybrid approach (spin then use interrupts)

Flood of interrupts arrive


- Can lead to livelock (always handling interrupts)
- Better to ignore interrupts while making some progress handling them

Other improvement

Interrupt coalescing (hardware batches together several interrupts)



Protocol Variants



- Status checks: polling vs. interrupts
- Data: programmed I/O (PIO) vs. direct memory access (DMA)
- Control: special instructions vs. memory-mapped I/O





what else can we optimize? data transfer!

Programmed I/O vs. Direct Memory Access

PIO (Programmed I/O):

- CPU directly tells device what the data is
- Efficient for a few bytes/words, but scales terribly

DMA (Direct Memory Access):

- CPU leaves data in memory
- Device reads/writes data directly from/to memory
- Efficient for large data transfers





wait for interrupt;


// 4

while (STATUS == BUSY)

wait for interrupt;

// 4


while (STATUS == BUSY)



Write data to DATA register

Write command to COMMAND register // 3

Protocol Variants




Status checks: polling vs. interrupts

Data: PIO vs. DMA


Control: special instructions vs. memory-mapped I/O







Protocol Variants



Status checks: polling vs. interrupts

Data: PIO vs. DMA

Control: special instructions vs. memory-mapped I/O





Special Instructions vs. Memory-Mapped I/O

Special instructions

- each device has a port
- in/out instructions (x86) communicate with device

Memory-Mapped I/O

- H/W maps registers into the virtual address space
- loads/stores sent to device

Doesn't matter much (both are used)



