Deploy

Prerequisites

- 1. Tomcat (latest version)
- 2. Java (7 or 8)

Installation and Configuration


- Download and install tomcat from this site https://tomcat.apache.org/download-70.cgi
- Navigate to the home directory <tomcat_home>/conf/tomcat-users.xml
- 3. Add the following lines
 Add users to the tomcat

```
<role rolename="manager-gui"/>
<role rolename="manager-script"/>
<user username="tomcat" password="tomcat" roles="manager-gui,manager-script"/>
```

```
the License. You may obtain a copy of the License at
      http://www.apache.org/licenses/LICENSE-2.0
  Unless required by applicable law or agreed to in writing, software
  distributed under the License is distributed on an "AS IS" BASIS,
  WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied.
  See the License for the specific language governing permissions and
  limitations under the License.
<!--
  NOTE: By default, no user is included in the "manager-gui" role required
  to operate the "/manager/html" web application. If you wish to use this app,
  you must define such a user - the username and password are arbitrary.
<!--
  NOTE: The sample user and role entries below are wrapped in a comment
  and thus are ignored when reading this file. Do not forget to remove
  <!... > that surrounds them.
 -->
<!--
  <role rolename="tomcat"/>
  <role rolename="role1"/>
  <user username="tomcat" password="tomcat" roles="tomcat"/>
  <user username="both" password="tomcat" roles="tomcat, role1"/>
  <user username="role1" password="tomcat" roles="role1"/>
 <role rolename="manager-gui"/>
  <role rolename="manager-script"/>
 <user username="tomcat" password="tomcat" roles="manager-gui,manager-script"/>
 </tomcat-users>
```


(the bicense); you may not use this life except in compilance with

4. Save and start the tomcat server




5. Run in the browser

http://Localhost:8080/



6. Click on manager app



It will ask for username and password

Username and password should be same as mentioned in the tomcat –user.xml

```
<user username="tomcat" password="tomcat"</pre>
```

Now we can see able to login into tomcat server as users!!!!