




Note that each successive step in an analysis contains a summary of its inputs and attributes, and those of each previous step in the analysis. For example, in the above report the attributes of the *Health Impact Function* file used to generate the APV Results are present in the *Estimate Health Impacts* node. Similarly, the metadata for both the baseline and control air quality grids are present under the *Estimate Health Impacts* node.

The process of creating an Audit Trail is described below:

- Click the **Audit Trail Report** tab in the results window. Select *Current Audit Trail Report* (this is the default setting). Click **OK**.
- Carefully review the report, ensuring that the air quality grids, population data, health incidence data, health impact functions and economic value estimates appear as you expected.
- Click the **Export** button to save the audit trail report. The default location for saving audit trail export (.txt, .ctlx, or .xml) files will be the location you chose earlier for saving your shape files.

Audit Trail Reports have three export options: *.txt*, *.ctlx*, and *.xml*. These file types can all be viewed using a standard text editor. The *.txt* and *.xml* files will contain the same information displayed in the **Audit Trail Report** window

BenMAP-CE Guidance and Best Practices

It is *always* recommended that you save your Audit Trail Report at the end of each analysis.

(however, the *.xml* file contains tags to retain the tree structure). If you are familiar with the command line feature, you may use the audit trail report to produce a control (*.ctlx*) file using an existing analysis, rather than creating one from scratch. The control file documents variables and configurations (file paths) associated with an analysis. For more information about the command line tool see Appendix L.

8.4 Frequently Asked Questions

Can I reorder the data layers?

Yes, data layers may be dragged within the GIS table of contents to reorder them within a group.

How do I export shapefiles?

When viewing any of the displayed maps in the **GIS Map** tab (lower right frame of the main window), click on the GIS toolbar icon for *Save Shapefile* (looks like a 3.5-inch diskette). Follow the prompts to provide a name and location for the file. BenMAP-CE will export a set of files (*.dbf*, *.prj*, *.shp*, *.shx*) associated with the shapefile that you can use with any GIS viewer.

How do I save a GIS map as an image?

To export the map as an image, click the *Export map* image icon (immediately below the *Save Shapefile* icon). This will use built-in DotSpatial GIS tools to allow you to save the map as a formatted image (*.png*) file. Alternately, use the *Print Screen* (PrtScn) button on your keyboard to create an image (saved in memory) which you can then paste into a graphics editor or document.

Can I display my map using a projection other than GCS-NAD 83 or Albers?

Yes, click the GIS toolbar icon for “**change projection to...**”; this feature will allow you to alternate between GCS-NAD83 and Albers projections. For more options, right-click on the **Map Layers** feature in the GIS table of contents and select **Projection** from the pop-up menu. This will display information about the current projection. Click the **Change Projection** button to view and apply other available projections.


Chapter 9

Tools Menu

In this chapter...

- **Learn about the options in the Tools menu.**

The **Tools** menu, available on the main BenMAP-CE screen, provides access to six special add-on tools and an **Options** menu. Below we summarize the purpose of each tool. Note that other sections of the manual have already covered several of these items, so we merely list them here and point you to the appropriate section.



- **Aggregate Air Quality Surface.** Use this tool to change an air quality grid based on one grid definition to a coarser grid definition, using a simple spatially weighted average approach. For example—you could aggregate your air quality surface from 12km × 12km grids to U.S. Counties.
- **Database Export.** Export your entire database (every item in your setup) or parts of your setup (e.g. all GridDefinitions, or individual Health Impact Function Datasets) to a specified file location.
- **Database Import.** Import an entire setup or parts of an individual setup from a specified file location.
- **Online Database Export.** Export your BenMAP-CE dataset(s) and upload to a cloud-based data archive to share with the BenMAP-CE community.
- **Online Database Import.** Import dataset(s) provided by the BenMAP-CE community from a shared cloud-based data archive.
- **Export Air Quality Surface.** Generate a data file that contains all of the air quality values saved within an air quality surface (.aqgx) file.
- **GBD Rollback.** This application estimates the air pollution-attributable health burden, and the benefits of improved air quality, in each country using data from the Global Burden of Disease (GBD) study.