






NOTE: Exported BenMAP-CE database files have a *.bdbx* extension, and are a binary format not suitable for viewing in external applications.


To view exported data in external application, choose “Other file Format”. The tool will export Grid definitions in shapefile (*.*shp*) format and the rest of the data in CSV (*.*csv*) format. If the dataset contains multiple tables, it will be exported into multiple CSV files. In the screen below, we have chosen to export *EPA Standard Variables* to a CSV file.



In the **Save As** window, the File name has been pre-populated with dataset name. You may leave it as is or change to something you want.



In this case, each variable of *EPA Standard Variables* dataset is saved as one CSV file with its variable name appended to the end of the dataset name.




NOTE: When exporting datasets in Other File Format, only one dataset can be selected at one time.

9.3 Database Import

Import entire setups or parts of individual setups. This option is described in the Import Setups section of Chapter 4: Loading Data.

To import part or all of an existing setup, go to the **Tools** menu, and choose the *Database Import* option. This will bring up the **Database Import** window.



The **Database Object File** identifies the file that you want to import. Click on the **Browse** icon to locate the file. This will display the **Open** window.

Find and select the *.bdbx* file that you want to import, and then click **Open**. This will return you to the **Database Import** window. Click **OK** to finish the import process.

If the import file contains a subset of a setup, such as a collection (e.g., a set of Grid Definitions) or an individual dataset (e.g., a single grid definition from among many available), select the **Setup** into which it should be imported from the **Target Setup** drop-down list. Click **OK** to finish.

NOTE: Duplicates of datasets (typically identified by their names, e.g., ‘*Detroit Population*’) will default to the existing dataset in the Setup. New datasets (i.e., non-duplicated) will be added to the setup.

9.4 Online Database Export

The **Online Database Export** feature was designed to facilitate sharing of BenMAP-CE datasets among the user community. The data is stored in an online database. Sharing and use of this data is at the discretion of the user community.

To share data in the online repository, select *Online Database Export* from the BenMAP-CE **Tools** menu. In the **EPRI Online Database Export** form, provide your name (required field), organization, and a description of the data you are sharing. Then select the object you wish to export from the tree menu. Similar to the database export feature (see Section 9.2), you can select an entire setup, dataset type, or specific data element. Once you make your selection and click “**OK**”, you will be prompted to confirm the upload.