PK DOCUMENT TRACKING SYSTEM

CURRENT PROCESS FLOW

1. Prepare, save and submit a request

STEP 1

Choose a request action, enter its details and select Save Draft.



REQUESTER

STEP 2


Validate fields, permission, ownership and active targets; save a valid draft.




PK DTS

STEP 3

Reopen the saved draft; review the proposal and required Document File.



REQUESTER



REQUESTER

STEP 4

Submit the saved proposal for its configured approval route.



PK DTS

STEP 5

Capture the published route and version; activate the first step; mark Submitted.

NOTES

Softcopy Create/Revise need a Document File before submission: PDF, TXT, PNG, JPG/JPEG, DOCX or XLSX; maximum 15 MB.

Only the requester may edit Draft/Returned proposals. Access and assignment requests name that requester as recipient.

Cancel applies only to Drafts; owner-only Delete applies to eligible Cancelled drafts with no submission or workflow state.

Access expiry must be after today when saved and remain valid at final approval.

A Submitted access, assignment or transfer request blocks another of these for the same requester and document.

Hardcopy updates require the current holder or an Administrator.


LEGEND / REQUEST COVERAGE

Softcopy Create registers a controlled record/file; Revise publishes a replacement revision; Cancel marks Cancelled and retires files.
Hardcopy Create registers title, storage and holder; Update applies proposed metadata and retention information.
Access Grant provides time-limited access; Document Assignment adds a softcopy assignee or changes the hardcopy holder.
Hardcopy Transfer creates handoff work (sheet 3). Hardcopy Disposal marks Disposed, clears Location and revokes grants.

PK DOCUMENT TRACKING SYSTEM

CURRENT PROCESS FLOW

2. Review, decide and apply a request



NOTES

Only the active step's assigned user or role member may decide. Types: user, role, Requester's leader or requester; resolved accounts must be active at submission.

Return after the first step will reopen the immediately preceding approved step. Return from the first step will send the proposal to its requester.

Resubmission will retain the captured approval route and preserve previous decision history. Rejection will end the request.

Final approval applies the operation atomically; failed checks save no decision. A transfer remains Approved until Dispatch and Accept complete.

LEGEND / REQUEST COVERAGE

Approve: continue the configured route or apply the final operation.
Return: reopen the previous step or return to the requester.
Reject: end the approval route.


PK DOCUMENT TRACKING SYSTEM

CURRENT PROCESS FLOW

3. Approve, dispatch and accept a hardcopy

STEP 1

Select an active hardcopy, recipient and different active destination; submit.



REQUESTER

STEP 2

Review and approve the transfer through its configured approval route.




CONFIGURED APPROVERS

STEP 3

Prepare the For Transfer handoff; preserve the current holder and Location.




PK DTS



ORIGINAL REQUESTER

STEP 4


Dispatch the physical document and confirm its release.



DESIGNATED RECIPIENT

STEP 5

Accept the in-transit document and confirm physical receipt.



PK DTS

STEP 6

Recheck the holder and approved destination; update custody and Location; complete the request.

NOTES

Only the original transfer requester will be allowed to Dispatch; this account may differ from the current holder. Only the designated recipient will be allowed to Accept.

Approval will prepare the handoff without moving custody. Dispatch will mark it In Transit; recipient acceptance will complete it.

Acceptance will require the active document, unchanged holder and approved active destination hierarchy. A failed check will preserve custody and location.

When custody changes to another user, acceptance will revoke the previous holder's personal hardcopy grants.

LEGEND / REQUEST COVERAGE

For Transfer: approved handoff awaiting Dispatch.
In Transit: dispatched document awaiting recipient acceptance.
Accepted / Completed: receipt and custody update recorded.

PK DOCUMENT TRACKING SYSTEM


CURRENT PROCESS FLOW

4. Browse, use files and apply authorized direct actions

A. DOCUMENT USE

STEP 1

Sign in, complete any required temporary-password setup, and open the Softcopy or Hardcopy catalog.



REGISTERED USER

STEP 2

Apply role permissions and document scope to records and available actions.



PK DTS

STEP 3

For a softcopy, open, download or print its current controlled file when authorized.



REGISTERED USER

B. PERMITTED DIRECT ACTIONS



AUTHORIZED OPERATOR

STEP 4


Choose a permitted direct document maintenance or assignment action.



PK DTS

STEP 5

Validate the direct permission, document scope, active targets and proposed changes.



PK DTS

STEP 6

Apply the authorized changes immediately and save the controlled record.

NOTES

File access requires permission, document scope, an active record and its current approved file; catalog visibility alone is insufficient.

Direct actions need their own permission and apply without an approval request.

Assignments cover one record, a hardcopy Location or a softcopy category branch; bulk limit: 2,000 active records.

Hardcopy assignment changes Current Holder immediately, without Dispatch/Accept; softcopy assignment adds the user and keeps earlier assignees.

Active transfers block direct hardcopy reassignment. Expired or revoked grants confer no access.

LEGEND / REQUEST COVERAGE

Direct Softcopy actions: Create, Revise, Cancel and Dispose.
Direct Hardcopy actions: Create, Update and Dispose.
Direct assignments: selected active document or permitted location/category group.

PK DOCUMENT TRACKING SYSTEM

CURRENT PROCESS FLOW

5. Maintain definitions and prepare controlled recovery

LEGEND / ADMINISTRATION SCOPE

Places: Area > Specific > optional Asset > Location.
Categories: softcopy category and subcategory hierarchy.
Recovery: protected archive, verified contents and pre-restore snapshot.



AUTHORIZED MAINTAINER

OPEN A PERMITTED ADMINISTRATION AREA

Sign in and open the permitted system administration pages. The options below will be independent; permissions will determine access.



ACCOUNT ADMINISTRATOR

ACCOUNTS AND ROLES

Maintain active user accounts, roles and delegated permissions.



AUTHORIZED MAINTAINER

PLACES AND CATEGORIES

Maintain the hardcopy place hierarchy and softcopy categories.



WORKFLOW ADMINISTRATOR

APPROVAL WORKFLOWS

Clone and edit workflow drafts; publish the default approval route per request type.



AUTHORIZED AUDIT / BACKUP USER

AUDIT AND BACKUPS

Inspect audit records; create, download or import backups; clean up eligible old archives.

ONLY WHEN RESTORE IS SELECTED



PK DTS

AUTHORIZED RESTORE

Verify the selected archive, password and RESTORE confirmation; create a recovery snapshot before restoring database and private data.

NOTES / CONFIGURATION AND RECOVERY RULES

Separate admin permissions; workflow changes preserve Submitted/Returned routes.

Backup needs encryption password, signing key, AES-256 ZIP and DB tools. Includes DB/code/private data; excludes sessions/cache/backups.

Restore checks archive/password/RESTORE, makes a recovery backup, restores DB/private data in maintenance, then signs out. Code recovery is offline.

Cleanup: eligible backup/audit/log archives older than 3 months.

Request outcomes / 1-5

Current source behavior; permissions and record scope apply to each operation.

softcopy_create - Create controlled softcopy and its approved file.

softcopy_revise - Publish replacement revision; retain history; retire superseded file bytes after commit.

softcopy_cancel - Mark controlled document Cancelled and retire its files; separate from cancelling a draft.

hardcopy_create - Register physical document, holder, place hierarchy and optional retention dates.

hardcopy_update - Apply approved metadata and retention changes to the active hardcopy.

Request outcomes / 6-9

Current source behavior; permissions and record scope apply to each operation.

access - Grant personal access to the requester until expiry; role permissions still govern file actions.

assignment - Assign to requester: add/reactivate softcopy assignment or replace hardcopy holder.

transfer - Approve handoff, then requester Dispatch and recipient Accept; acceptance updates custody/location.

disposal - Dispose hardcopy, preserve history, clear Location and revoke personal grants.

Supporting work and operating boundaries

Current source behavior; permissions and record scope apply to each operation.

Use the theme button to select light or dark mode. The preference is saved in this browser; without one, the system follows the device theme.

Use Toggle navigation on a narrow screen. Table and Folder views, filters, breadcrumbs and paging operate within your document permissions.

Use Install app when the browser offers it. Confirm the browser prompt. After installation the install control is hidden; eligibility depends on browser support and a secure context.

Open the installed app to use the same server and account. Installation does not provide offline document editing or approval. Reconnect before performing server actions.

Opening the notification panel does not mark everything read. Selecting an entry acknowledges that entry; dismissing a reminder does not decide a task.

Accounts, roles, places/categories, workflow drafts/publication, audit inspection and backup recovery follow Process Flow sheet 5 and User Guide sections 17-22.

A scheduler is installed separately for automatic backups. Review readiness and a resulting archive; a documented schedule does not prove a completed backup.