

Ubuntu 24.04.4 LTS 可以部署 Outline Server 完整教程。

YouTube: @cursigtv

Outline 的组成: 搭建 Outline 时，要分清三个东西：

1. Outline Server

Outline Server 运行在 VPS 上，负责接收客户端连接并通过服务器转发网络流量到互联网。

第 1 步：安装 Docker

Outline Server 通常通过 Docker 部署。先执行：

```
apt update
apt install -y docker.io
```

安装完成后执行：

```
systemctl enable --now docker
```

然后检查：

```
docker --version
```

如果看到类似：

```
Docker version 28.x.x
```

就说明 Docker 已经好了。

设置 Docker 开机启动

```
systemctl enable docker
systemctl start docker
```

检查：

```
systemctl status docker
```

看到：

Active: **active** (running)

就正常。

第 2 步：安装 Outline Server

现在不要自己 `docker pull` 镜像。


Outline 官方推荐使用安装脚本部署 Server。我们下一步先下载/执行官方安装程序，它会自动处理 Docker、镜像和容器。

你先执行：

```
sudo bash -c "$(wget -qO-  
https://raw.githubusercontent.com/OutlineFoundation/outline-apps/master/server\_manager/install\_scripts/install\_server.sh)"
```


2. Outline Manager 端口号：Outline 自动分配

Outline Manager 是用于管理 Outline Server、创建和管理访问密钥、查看服务器状态的管理工具。选择安装：“随时随地安装 Outline”



在服务器输入：

```
sudo bash -c "$(wget -qO-  
https://raw.githubusercontent.com/OutlineFoundation/outline-apps/master/server  
_manager/install_scripts/install_server.sh)"
```



```

root@fred-server:~#
root@fred-server:~# sudo bash -c "$(wget -qO- https://raw.githubusercontent.com/OutlineFoundation/outline-apps/master/server_manager/install_scripts/install_server.sh)"
  Verifying that Docker is installed ..... OK
> Verifying that Docker daemon is running ..... OK
> Setting PUBLIC_HOSTNAME to external IP ..... OK
> Creating persistent state dir ..... OK
> Generating secret key ..... OK
> Generating TLS certificate ..... OK
> Generating SHA-256 certificate fingerprint .. OK
> Writing config ..... OK
> Starting Shadowbox ..... OK
> Starting Watchtower ..... FAILED
> The container name "watchtower" is already in use by another container. This may happen when running this script multiple times. Would you like to replace this container? [Y/n] y
ill proceed with the remainder of the installation. [Y/n] y
> Removing watchtower container ..... OK
> Restarting watchtower ..... OK
> Waiting for Outline server to be healthy .... OK
> Creating first user ..... OK
> Adding API URL to config ..... OK
> Checking host firewall ..... OK

CONGRATULATIONS! Your Outline server is up and running.

To manage your Outline server, please copy the following line (including curly
brackets) into Step 2 of the Outline Manager interface:

{"apiUrl":"https://141.164.38.198:60198/Kf1a4ChKx-Yqgx2kVlZuGw","certSha256":"46A3731EC0B6485F40547C651380212F3982CBC852CC02A9229DD8BCBF06AAEF1"}

If you have connection problems, it may be that your router or cloud provider
blocks inbound connections, even though your machine seems to allow them.

Make sure to open the following ports on your firewall, router or cloud provider:
- Management port 60198, for TCP
- Access key port 24010, for TCP and UDP

If you use UFW, you can allow these ports with:
sudo ufw allow 60198/tcp
sudo ufw allow 24010/tcp
sudo ufw allow 24010/udp

```

注意：每次使用命令后端口会有改变：在防火墙中添加蓝色的端口。

If you use UFW, you can allow these ports with:

```
sudo ufw allow 60198/tcp
```


```
sudo ufw allow 24010/tcp
```

```
sudo ufw allow 24010/udp
```

3. Outline Client 端口号：Outline 自动分配 tcp/udp

安装在：

- Windows



客户端拿到访问密钥以后，连接 Outline Server。

- Android
- iPhone
- macOS
- Linux