

## Connect to the PingOne Remote MCP Server

You will need a feature flag to use the remote MCP server, if you do not have it enabled contact [Amit Ben-Chanoch](#) or [Nathan Langton](#) or [Saparja Dey](#)

## Setup a worker app

The PingOne MCP Server requires a worker application to authenticate with the PingOne APIs.

1. In the [PingOne admin console](#), select the environment where you want to connect. This should be where your administrator identity lives.
2. Click **Applications > Applications** in the left navigation menu.
3. Click **+ Add Application** and select **Worker**.
  - Enter the following:
    - **Name:** For example, `PingOne MCP Server`.
    - **Description:** Optional.
  - Click **Save**.
  - Enable the application using the toggle at the top right of the details panel.
4. On the **Configuration** tab, click the **Edit** icon and set:
  - **Grant Types:** `Authorization Code, Refresh Token`
  - **Response Type:** `Code`
  - **PKCE Enforcement:** `S256_REQUIRED`
  - **Redirect URIs:** `http://127.0.0.1:7474/callback`
    - **For VS Code, use a Redirect URI Pattern:** `http://127.0.0.1/*`
  - **Token Endpoint Authentication Method:** `None` (Public Client)
5. Click **Save**.
6. Copy the **Client ID** from the **Configuration** tab.

## Claude code

### NA Example

Replace your worker app clientId and environment ID and paste in terminal

```
claude mcp add --transport http --client-id {clientId} --callback-port 7474 pingone https://api.pingone.com/v1/environments/{envId}/mcp
```

## Github Copilot

### ! FAQ

1. **Using PingOne Remote MCP with existing PingOne and DaVinci Local MCPs.**

To avoid conflicts, ensure that any existing "PingOne" or "DaVinci" Local MCP servers set up in the same directory are disabled.

## **2. What Roles should be assigned to the user to view all the tools of PingOne Remote MCP Server?**

The specific tools available to you within the PingOne Remote MCP Server are determined by your assigned Admin Role.

To ensure you have full admin visibility:

- **For PingOne tools:** Assign the "Environment Admin" role.
- **For DaVinci tools:** Assign either the "DaVinci Admin" role.

## **3. Modify the administrative roles for the account used during authentication.**

If you update the Admin roles for the user connected to the Remote MCP Server, you must perform a reconnection to make the revised list of tools visible.