Pāhekoheko Tau Matihiko

Pou āwhina

Te wāhi tono āwhina

Mēnā ka raruraru tō whakamahi i tēnei kōpae, me whakapā atu ki te wāhi tono āwhina (ICT), waea utukore 0800 22 55 428 (0800 CALLICT).

Koinei ngā hōtaka rorohiko me matua whiwhi, e pai ai tō whakamahi i tēnei kōpae:

- Windows: Internet Explorer v6 (runga ake rānei)
- Mac: Internet Explorer v5 (runga ake rānei), Safari 1.2 rānei

Flash Player v6

Pāwhiria te hononga e hāngai ana i raro nei hei whakauru i te Flash Player v6 ki tō rorohiko:

- Windows / Internet Explorer Flash player installer
- Mac OS X Flash Player installer

Adobe Reader

Mā te Adobe Acrobat Reader e whai wāhi atu koe ki te pānui i tētahi tuhinga kua tāpirihia te .pdf ki tōna ingoa.

Pāwhiria te hononga e hāngai ana i raro nei hei whakauru i te Adobe Reader ki tō rorohiko:

- Windows XP, Windows 2000 SP2 <u>Adobe Reader 7.0 installer</u>
- Windows 2000 SP1 <u>Adobe Reader 6.0 installer</u>
- Windows 98 SE Adobe Reader 6.0 installer
- Windows 98 <u>Adobe Reader 5.0 installer</u>
- Mac OS 9.1-10.2.7 Adobe Reader 7.0 installer
- Mac OS 10.2.8-10.3 Adobe Reader 7.0 installer

Kia mōhiotia ai: Ngā mea e whakamahi ana i te Windows XP

Me tono atu mā te kaiwhakahaere rorohiko o tō kura e whakauru tēnei hōtaka. He tawhito tonu te Flash Player o roto i te Windows XP, nō reira me whakahou tēnei wāhanga kia whai wāhi atu ki ngā akoranga matihiko.

Whakamārama

He maha ngā kura e whakamahi ana i te Windows XP i ā rātou rorohiko. Ahakoa kāore i hangaia ngā akoranga matihiko o TLF kia haere tahi me te Windows XP, ka pai tonu i te nuinga o te wā. Engari ka raruraru ētahi o ngā akoranga matihiko i te whakaurunga aunoa o te Windows XP.

Mēnā kua whakaurua te Flash Player 5 (kaua ko te Flash Player 6) ka kitea tētahi whārangi wātea i te mata o te rorohiko, anō nei e tīkina atu ana te akoranga matihiko. Ka pēnei anō te raruraru mēnā kua whakaurua te Flash Player 6 me te kore i tika te mana whakahaere.

Me whakahou te Flash Player, mai i te 5 ki te 6, kia pai ai te haere o ngā akoranga matihiko (Flash TLF). E tutuki pai ai te whakauru i te Flash Player 6 ki te Windows XP, me matua whiwhi te mana whakahaere mō taua hōtaka

Pāhekoheko Tau Matihiko

rorohiko. Ko te raruraru, kāore te nuinga o ngā tāngata whakamahi rorohiko i ngā kura e whiwhi ana i te mana whakahaere hei whakahou i te Flash Player.

Te whakahou i te Flash Player

Hei whakatau i tēnei raruraru, me whakahou te Flash Player o roto i te Windows XP, mai i te 5 ki te 6. E tika ana kia riro i a koe te mana whakahaere i te rorohiko hei whakatutuki i tēnei whakahoutanga. Kuhu atu ki te rorohiko hei kaiwhakahaere.

- Tīkina te hōtaka hei whakauru i te Flash Player 6, mai i: http://www.macromedia.com/support/flash/ts/documents/oldplayers.htm.

 He rerekē te hōtaka whakauru e hāngai ana ki te Internet Explorer me te Netscape, me te pūnaha whakahaere mō te Windows me te Mac.
- 2. Whakahaeretia te hōtaka whakauru mō te Flash Player 6, ka whai ai i ngā tohutohu.
- 3. Whakamātauria te whakaurunga mā te toro atu ki: http://www.macromedia.com/shockwave/welcome/.
- 4. Kimihia te wāhanga o tēnei whārangi e pā ana ki te Flash Player.
- 5. Pāwhiria te pūtohu About kia kite ai koe mēnā i tika te whakauru i te Flash Player 6.

Ko tētahi atu whakamātau, ko te whakahaere i tētahi o ngā Akoranga Matihiko (Flash TLF) kāore i tika te haere i mua.

Whakaritenga Mamaru

Mō ētahi rorohiko e whakahaere ana i te Windows XP me te Internet Explorer 6.0 SP2, me whakarerekē tētahi o ngā whakaritenga mamaru i roto i te pūmanawa tirotiro, e tika ai te haere o ngā akoranga matihiko. Koinei ngā tohutohu:

- 1. Huakina te Internet Explorer.
- 2. Kōwhiria 'Tools' > 'Internet Options' > 'Advance Tab'.
- 3. Haere whakararo ki 'Security' tohua 'Allow active content from CDs to run on My Computer'.
- 4. Kōwhiria 'Apply'.
- Kōwhiria 'OK'.