MAISON AFFLUENCY

TRADE PORTAL · STUDIO GUIDE

STUDIO GUIDE · v1.0

Installing Maison Affluency on Your Phone

A short visual checklist for designers and architects who use Maison Affluency as an app on their iPhone or Android home screen.

Maison Affluency

01

What this guide is for

Maison Affluency can be added to your phone's home screen and opened like any other app — no App Store, no download. This is what's called a **PWA** (Progressive Web App): a website that, once "Added to Home Screen", runs full-screen with its own icon, exactly like a native app.

This guide walks you through **how to install it** on iPhone and Android, and gives you a short **visual checklist** to make sure everything looks right on your device — no overlapping menus, no text hidden behind the notch or the bottom gesture bar, no clipped buttons.

It's particularly useful for designers and architects who consult the Maison Affluency catalogue on site visits, in Galleries or in client meetings, where the app needs to look polished and behave like a real app — not a browser tab.

> **Share this with your team**
> Print it, forward it to your design partners, or pin it in the studio handbook so anyone reviewing the app on a phone knows what "good" looks like — and how to flag anything that isn't.

02

iPhone — reinstall the app

Always test on the live *maisonaffluency.com* domain. Staging or preview environments may run inside an iframe and won't reflect manifest, theme-color or display-mode changes.

1. Remove the existing icon	Long-press the Maison Affluency icon on the Home Screen **Remove App** **Delete from Home Screen**.
2. Open Safari	Not Chrome. Navigate to *https://www.maisonaffluency.com*.
3. Force a fresh load	Pull down to refresh, or close and reopen the Safari tab.
4. Add to Home Screen	Tap the **Share** icon (square with arrow) scroll to **Add to Home Screen** **Add**.

5. Launch from the icon	Open the app from the Home Screen icon, not from Safari, otherwise you'll see browser chrome.

03

iPhone — screenshots to capture

Take a screenshot (Side button + Volume Up) on each of the following and save them for review.

Home — portrait, top	Status bar (clock, battery) sits in a clean white strip above the logo; nothing overlaps the burger menu.
Home — burger menu open	Drawer items aren't clipped by the notch / Dynamic Island.
Home — landscape	Notch on the left doesn't overlap the logo or nav icons.
Designers Directory	Sticky filters clear the status bar; chips remain readable.
Product page — bottom	iPhone home indicator does not cover the cookie banner, sticky CTA or footer links.
Trade login / modal	Dialog close button isn't hidden behind the notch.
Cookie consent visible	Banner sits above the home indicator with breathing room.

> **What to look for**
> Top: a solid white strip above the nav, no overlap. Notch: nothing disappears behind the left-side cutout in landscape. Bottom: the thin indicator bar must not cover any sticky element. Pull-to-refresh must **not** reveal Safari chrome — if it does, the app launched from Safari, not from the icon.

04

Android — reinstall the app

Android Chrome also pins the manifest at install time, so reinstall to see theme-color, display-mode or icon updates.

1. Remove the existing icon	Long-press the Maison Affluency icon **Remove** (or drag to *Uninstall*).
2. Open Chrome	Navigate to *https://www.maisonaffluency.com*.
3. Force a fresh load	Pull down to refresh, or tap the **menu Reload**.
4. Add to Home screen	Tap **menu Add to Home screen Add** (or **Install** if the app install prompt appears).
5. Launch from the icon	Open the app from the home screen icon, not from a Chrome tab.

05

Android — screenshots to capture

Take a screenshot (Power + Volume Down) on each of the following.

Home — portrait, top	Status bar (clock, battery, notifications) sits above the logo; nothing overlaps the burger or brand text.
Home — drawer open	Drawer header and first items aren't hidden behind the status bar or cut off by rounded corners.
Home — landscape	No nav icon or logo lost in display cutouts (punch-hole or top-left notch).
Designers Directory	Sticky filter bars clear the status bar; chips stay tappable.
Product page — bottom	Gesture / 3-button navigation bar does not cover sticky CTAs, cookie banner or footer links.
Trade login / modal	Dialog close button and top margin aren't hidden behind a display cutout.
Cookie consent visible	Banner sits above the gesture bar with breathing room.

© 2026 Maison Affluency · maisonaffluency.com

What to look for

Top: nav must start **below** the status bar — no overlap. Cutouts: no critical UI behind a punch-hole or notch. Bottom: the system bar must not cover sticky elements. Pulling down should **not** reveal Chrome's address bar or a blue overscroll glow — if it does, the shortcut is opening as a browser tab, not standalone.

06

If something overlaps

Note the exact page and attach the screenshot, then ask Maison Affluency to patch the affected component using the iOS / Android **safe-area** CSS environment variables — *env(safe-area-inset-top)* for top overlap, *env(safe-area-inset-bottom)* for bottom overlap. These resolve to **0px** on devices without cutouts, so they never harm desktop or older devices.

One last sanity check

Before signing off, rotate the device to landscape. That's where notches and cutouts most often overlap content — and where the iPhone home indicator becomes most disruptive over fixed CTAs.