



Instalación, configuración de una máquina virtual UBUNTU SERVER

1. Descargar VirtualBox


The image shows the VirtualBox website and two screenshots of its installer. The website header includes the VirtualBox logo and navigation links: Home, Download, Documentation, and Community. A search bar is also present. The main content area features the text "Powerful open source virtualization" and "For personal and enterprise use". Below this, a description states: "VirtualBox is a general-purpose full virtualization software for x86_64 hardware (with version 7.1 additionally for macOS/Arm and with version 7.2 also for Windows/Arm), targeted at laptop, desktop, server and embedded use." A "Get Started" button labeled "Download" is visible, with a note: "Download VirtualBox binaries and platform packages".

The first screenshot is the "Oracle VirtualBox 7.2.20 Installer" window, titled "Custom Setup". It prompts the user to "Select the features to install". A tree view on the left shows the following features: VirtualBox Application, VirtualBox USB Support, VirtualBox Networking, VirtualBox Bridge, VirtualBox Host-C, and VirtualBox Python Support. The "VirtualBox Application" feature is selected. To the right, a message states: "Oracle VirtualBox 7.2.20 application. This feature requires 235MB on your hard drive. It has 3 of 3 subfeatures selected. The subfeatures require 968KB on yo...". The "Installation Location" is set to "C:\Program Files\Oracle\VirtualBox\". A "Check Disk Space" button is available. At the bottom, the version "Version 7.2.20 (amd64)" is displayed, along with "Previous", "Next", and "Cancel" buttons.

The second screenshot is the "Oracle VirtualBox 7.2.20" window, titled "Missing Dependencies". It contains the VirtualBox logo and the following text: "Installing the Oracle VirtualBox 7.2.20 Python bindings requires the Python Core package and the win32api bindings to be installed. You can install and configure these later. For instructions, refer to the Oracle VirtualBox 7.2.20 SDK Programming Guide. Alternatively, install them before continuing with the Oracle VirtualBox installation." At the bottom, the version "Version 7.2.20 (amd64)" is displayed, along with "Yes" and "No" buttons.




2. Descargar la imagen ISO de ubuntu server



The screenshot shows the Ubuntu Server download page. The top navigation bar includes 'Downloads', 'Desktop', 'Server', 'WSL', 'Core', and 'Cloud'. The main heading is 'Get Ubuntu Server'. Below it, there are tabs for 'Manual installation', 'Instant VMs', and 'Automated provisioning'. The version 'Ubuntu 26.04.1 LTS' is displayed. A large Ubuntu logo is on the left. On the right, it states 'The latest LTS version of Ubuntu Server. LTS stands for long-term support — which means five years of free security and maintenance updates, extended to up to 15 years with [Ubuntu Pro](#).' A 'Download' button is available for 'Intel or AMD 64-bit architecture' (3GB). Below this, there are links for 'What's new', 'System requirements', and 'How to install'. A list of features includes 'Linux 7.0 kernel' and 'Dual-track system for container stacks: traditional with regular major updates, or stable to maintain consistent versions of core components'. Below the webpage, a file manager window titled 'Descargas' shows the file 'ubuntu-26.04.1-live-server-amd64.iso' with a progress bar indicating '30,4 MB/s - 2,0 GB de 2,7 GB, Quedan 25 s'.

3. Instalación de la máquina virtual



The screenshot shows the 'New Virtual Machine' wizard in Oracle VM VirtualBox. The title bar says 'New Virtual Machine'. The main window is titled 'Virtual machine name and operating system'. It includes the instruction: 'The ISO image is used to install the operating system on the VM.' The fields are filled as follows: 'VM Name' is 'Despliegue', 'VM Folder' is 'C:\Users\2DAW\VirtualBox VMs', 'ISO Image' is 'C:\Users\2DAW\Downloads\ubuntu-26.04.1-live-server-amd64.iso', 'OS Edition' is empty, 'OS' is 'Linux', 'OS Distribution' is 'Ubuntu', and 'OS Version' is 'Ubuntu 25.04 (Plucky Puffin) (64-bit)'. There is a checkbox for 'Proceed with Unattended Installation' which is checked. A message at the bottom states: 'Tipo de SO detectado: Ubuntu 25.04 (Plucky Puffin) (64-bit). VirtualBox will install the OS using an unattended installation when the VM is created. Supply the required information in the following steps.' At the bottom, there are buttons for 'Ayuda', 'Anterior', 'Siguiente' (highlighted with a red border), and 'Cancelar'.

Poner nombre y contraseña

New Virtual Machine

Set up unattended guest OS installation

Enter the information that will be required when the OS is installed.

User Name and Password

User Name: david ✓

Contraseña: •••••• •••••• ✓

Confirm Password: •••••• •••••• ✓

OS Installation Options

Product Key: _____ ✓

Host Name: Despliegue ✓

Domain Name: myguest.virtualbox.org ✓

☐ Instalar en segundo plano

☐ Install Guest Additions

Guest Additions ISO Image: C:\Program Files\Oracle\VirtualBox\VBBoxGuestAdditions.iso

Ayuda Anterior **Siguiente** Cancelar

Añado componentes a la máquina

New Virtual Machine

Specify virtual hardware

Specify the VM's hardware. Resources allocated to the VM will not be available to the host when the VM is running.

Base Memory: 8763 MB (4 MB to 16384 MB)


Number of CPUs: 3 (1 CPU to 12 CPUs)

Disk Size: 25,00 GB (4,00 MB to 2,00 TB)


☐ Use EFI

Ayuda Anterior **Siguiente** Cancelar

Máquina creada



Máquina cargando



Pide el nombre y contraseña para logear

```
[ 8.817263] cloud-init[971]: | .0 0. +.  
[ 8.817281] cloud-init[971]: | 0. =. .S+.  
[ 8.817297] cloud-init[971]: | . .+=0.0.+0  
[ 8.817318] cloud-init[971]: | 0E.0*0. 0.  
[ 8.817335] cloud-init[971]: | +...+0+ .  
[ 8.817353] cloud-init[971]: | 0+ .+=..  
[ 8.817372] cloud-init[971]: +---- [SHA256] ----  
  
Ubuntu 26.04.1 LTS Despliegue tty1  
  
Despliegue login: david  
Password: _
```

Máquina lista para usar

```
Despliegue login: david  
Password:  
Login incorrect  
  
Despliegue login: david  
Password:  
Welcome to Ubuntu 26.04.1 LTS (GNU/Linux 7.0.0-34-generic x86_64)  
  
* Documentation:  https://docs.ubuntu.com  
* Management:    https://landscape.canonical.com  
* Support:        https://ubuntu.com/pro  
  
System information as of Thu Sep 24 05:14:02 PM UTC 2026  
  
System load:          0.07  
Usage of /:           14.4% of 24.44GB  
Memory usage:         4%  
Swap usage:           0%  
Processes:            138  
Users logged in:      0  
IPv4 address for enp0s3: 10.0.2.15  
IPv6 address for enp0s3: fd17:625c:f037:2:a00:27ff:fe97:47ba  
  
Expanded Security Maintenance for Applications is not enabled.  
  
108 updates can be applied immediately.  
94 of these updates are standard security updates.  
To see these additional updates run: apt list --upgradable  
  
Enable ESM Apps to receive additional future security updates.  
See https://ubuntu.com/esm or run: sudo pro status  
  
The programs included with the Ubuntu system are free software;  
the exact distribution terms for each program are described in the  
individual files in /usr/share/doc/*/copyright.  
  
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by  
applicable law.  
  
david@Despliegue:~$ ls  
david@Despliegue:~$ sudo apt update  
[sudo: authenticate] Password:  
Hit:1 http://es.archive.ubuntu.com/ubuntu resolute InRelease  
Hit:2 http://es.archive.ubuntu.com/ubuntu resolute-updates InRelease  
Hit:3 http://es.archive.ubuntu.com/ubuntu resolute-backports InRelease  
Hit:4 http://security.ubuntu.com/ubuntu resolute-security InRelease  
113 packages can be upgraded. Run 'apt list --upgradable' to see them.  
david@Despliegue:~$
```