

Download the Global Publishing Status




For supported software information, click here.

You can download the global publishing status in CSV format for all sites and appliances. Each row in the CSV file contains the following information:


- · Site-Name of the site
- · Appliance—Name of the appliance
- Status—Current publishing status
- Master Profile—Name of the master profile assigned to the appliance

To download the global publishing status in CSV format:

- 1. For a tenant, select the Deploy lifecycle in the left navigation screen. The Deploy screen displays
- 2. Select the Sites tab in the horizontal menu bar. The screen then displays all the tenant's sites.



3. Click the Publish button. The global publish screen for all the tenant's sites and appliances displays.



4. Click the Download icon to download a file in CSV format that contains the publishing status for all the tenant's sites and appliances. The following figure shows an example of the contents of a downloaded CSV file.

Global-Publish-09202023T03 09 10PDT			
SITE	APPLIANCE	STATUS	MASTER_PROFILE
Dallas	Dallas-D1	CURRENT	Central-Spoke-MP:v1
Denver	Denver-D1	CURRENT	FullMesh-MP.v3
Denver	Denver-Hub-1	PENDING_PROFILE	
Denver	Denver-Hub2	PENDING_PROFILE	
Denver	Denver-Primary	CURRENT	Copy_of_Default-Active-Active.v1-customized
Denver	Denver-Secondary	CURRENT	Copy_of_Default-Active-Active.v1-customized
Denver	HCN9	PENDING_PROFILE	
Denver	TestApp1	PENDING_PROFILE	
London	London-D1	CURRENT	East-Spoke-MP.v3
Miami	Miami-D1	CURRENT	East-Spoke-MP.v1
New York	NY-HCN-1	PENDING_PUBLICATION	Default-Basic-MP-Sub-Tenant.v1
New York	NY-HCN-2	PENDING_PROFILE	
New York	TestHCN1	PENDING_PROFILE	
San Francisco	SFO-D1	CURRENT	Spoke-MP.v3
Seattle	Seattle-D1	CURRENT	Spoke-MP.v3
TestSiteRam1	HCN-1	CURRENT	Hub-MP.v1

Software Release Information

Release 11.4.1 and supports all content described in this article

Additional Information

Concerto Deploy Lifecycle Overview