# Arduino Gyroscope Driver

Generated by Doxygen 1.8.9.1


Tue Aug 18 2015 22:52:20

# **Contents**

1	Hiera	archical Index	2				
	1.1	Class Hierarchy	2				
2	Clas	Class Index					
	2.1	Class List	2				
3	File I	Index	2				
	3.1	File List	2				
4	Class Documentation 2						
	4.1	RemoteCarControl Class Reference	2				
		4.1.1 Detailed Description	3				
		4.1.2 Member Function Documentation	3				
		4.1.3 Member Data Documentation	4				
	4.2	RemoteCarRadioControl Class Reference	4				
		4.2.1 Detailed Description	5				
		4.2.2 Constructor & Destructor Documentation	6				
		4.2.3 Member Function Documentation	6				
		4.2.4 Member Data Documentation	6				
	4.3	RemoteFlightControl Class Reference	6				
		4.3.1 Detailed Description	7				
		4.3.2 Member Function Documentation	7				
5	File Documentation 7						
	5.1	RemoteCarControl.cpp File Reference	7				
		5.1.1 Macro Definition Documentation	8				
	5.2	RemoteCarControl.cpp	8				
	5.3	RemoteCarControl.h File Reference	9				
	5.4	RemoteCarControl.h	9				
	5.5	RemoteCarRadioControl.cpp File Reference	10				
		5.5.1 Macro Definition Documentation	10				
	5.6	RemoteCarRadioControl.cpp	10				
	5.7	RemoteCarRadioControl.h File Reference	11				
	5.8	RemoteCarRadioControl.h	12				
	5.9	RemoteFlightControl.cpp File Reference	13				
		5.9.1 Macro Definition Documentation	13				
	5.10	RemoteFlightControl.cpp	13				
	5.11		14				
	5.12	RemoteFlightControl.h	14				

Index		
1	Hierarchical Index	
1.1	Class Hierarchy	
Thi	is inheritance list is sorted roughly, but not completely, alphabetically:	
	RemoteCarControl	2
	RemoteCarRadioControl	4
	RemoteFlightControl	6
2	Class Index	
2.1	Class List	
He	ere are the classes, structs, unions and interfaces with brief descriptions:	
	RemoteCarControl Arduino - Remote Car Control	2
	RemoteCarRadioControl  Arduino - Remote Car Radio Control	4
	RemoteFlightControl Arduino - Remote Flight Control	6
3	File Index	
3.1	File List	
He	ere is a list of all files with brief descriptions:	
	RemoteCarControl.cpp	7
	RemoteCarControl.h	9
	RemoteCarRadioControl.cpp	10
	RemoteCarRadioControl.h	11
	RemoteFlightControl.cpp	13
	RemoteFlightControl.h	14
4	Class Documentation	
4.1	RemoteCarControl Class Reference	
#i	nclude <remotecarcontrol.h></remotecarcontrol.h>	

Inheritance diagram for RemoteCarControl:



### **Public Member Functions**

- virtual void apply ()=0
- void setThrottle (int throttle)
- void stop ()
- void forward ()
- void backward ()
- void turnLeft ()
- void turnRight ()

### **Protected Attributes**

- char isForward
- int throttle
- int leftWheel
- int rightWheel

# 4.1.1 Detailed Description

Arduino - Remote Car Control.

RemoteCarControl.h

Author

Dalmir da Silva dalmirdasilva@gmail.com

Definition at line 12 of file RemoteCarControl.h.

### 4.1.2 Member Function Documentation

**4.1.2.1** virtual void RemoteCarControl::apply() [pure virtual]

Implemented in RemoteCarRadioControl.

4.1.2.2 void RemoteCarControl::backward ( )

Definition at line 54 of file RemoteCarControl.cpp.

```
4.1.2.3 void RemoteCarControl::forward ( )
Definition at line 47 of file RemoteCarControl.cpp.
4.1.2.4 void RemoteCarControl::setThrottle (int throttle)
Definition at line 14 of file RemoteCarControl.cpp.
4.1.2.5 void RemoteCarControl::stop ( )
Definition at line 41 of file RemoteCarControl.cpp.
4.1.2.6 void RemoteCarControl::turnLeft ( )
Definition at line 19 of file RemoteCarControl.cpp.
4.1.2.7 void RemoteCarControl::turnRight ( )
Definition at line 30 of file RemoteCarControl.cpp.
4.1.3 Member Data Documentation
4.1.3.1 char RemoteCarControl::isForward [protected]
Definition at line 16 of file RemoteCarControl.h.
4.1.3.2 int RemoteCarControl::leftWheel [protected]
Definition at line 18 of file RemoteCarControl.h.
4.1.3.3 int RemoteCarControl::rightWheel [protected]
Definition at line 19 of file RemoteCarControl.h.
```

- · RemoteCarControl.h
- RemoteCarControl.cpp

# 4.2 RemoteCarRadioControl Class Reference


**4.1.3.4** int RemoteCarControl::throttle [protected]

The documentation for this class was generated from the following files:


Definition at line 17 of file RemoteCarControl.h.

#include <RemoteCarRadioControl.h>

Inheritance diagram for RemoteCarRadioControl:



Collaboration diagram for RemoteCarRadioControl:



# **Public Member Functions**

- RemoteCarRadioControl (SerialRadioFrequency \*serialRadioFrequency, int leftForwardPin, int left
   BackwardPin, int rightForwardPin, int rightBackwardPin)
- virtual void apply ()
- void parseCommand (char \*cmdBuf, char cmdBufPointer)
- void loop ()

# **Private Attributes**

- SerialRadioFrequency \* serialRadioFrequency
- int leftForwardPin
- int leftBackwardPin
- int rightForwardPin
- int rightBackwardPin

# **Additional Inherited Members**

# 4.2.1 Detailed Description

Arduino - Remote Car Radio Control.

RemoteCarRadioControl.h

**Author** 

Dalmir da Silva dalmirdasilva@gmail.com

Definition at line 15 of file RemoteCarRadioControl.h.

- 4.2.2 Constructor & Destructor Documentation
- 4.2.2.1 RemoteCarRadioControl::RemoteCarRadioControl ( SerialRadioFrequency \* serialRadioFrequency, int leftForwardPin, int leftBackwardPin, int rightForwardPin, int rightBackwardPin )

Definition at line 14 of file RemoteCarRadioControl.cpp.

- 4.2.3 Member Function Documentation
- **4.2.3.1** void RemoteCarRadioControl::apply() [virtual]

Implements RemoteCarControl.

Definition at line 85 of file RemoteCarRadioControl.cpp.

4.2.3.2 void RemoteCarRadioControl::loop ( )

Definition at line 29 of file RemoteCarRadioControl.cpp.

4.2.3.3 void RemoteCarRadioControl::parseCommand ( char \* cmdBuf, char cmdBufPointer )

Definition at line 49 of file RemoteCarRadioControl.cpp.

- 4.2.4 Member Data Documentation
- **4.2.4.1** int RemoteCarRadioControl::leftBackwardPin [private]

Definition at line 19 of file RemoteCarRadioControl.h.

**4.2.4.2** int RemoteCarRadioControl::leftForwardPin [private]

Definition at line 18 of file RemoteCarRadioControl.h.

**4.2.4.3** int RemoteCarRadioControl::rightBackwardPin [private]

Definition at line 21 of file RemoteCarRadioControl.h.

**4.2.4.4** int RemoteCarRadioControl::rightForwardPin [private]

Definition at line 20 of file RemoteCarRadioControl.h.

4.2.4.5 SerialRadioFrequency\* RemoteCarRadioControl::serialRadioFrequency [private]

Definition at line 17 of file RemoteCarRadioControl.h.

The documentation for this class was generated from the following files:

- · RemoteCarRadioControl.h
- RemoteCarRadioControl.cpp
- 4.3 RemoteFlightControl Class Reference

#include <RemoteFlightControl.h>

5 File Documentation 7

#### **Private Member Functions**

- virtual void setThrottle (int throttle)=0
- virtual void setPitch (int pitch)=0
- virtual void setRoll (int roll)=0
- virtual void setYaw (int yaw)=0

### 4.3.1 Detailed Description

Arduino - Remote Flight Control.

RemoteFlightControl.h

**Author** 

Dalmir da Silva dalmirdasilva@gmail.com

Definition at line 12 of file RemoteFlightControl.h.

- 4.3.2 Member Function Documentation
- **4.3.2.1** virtual void RemoteFlightControl::setPitch (int pitch) [private], [pure virtual]
- **4.3.2.2** virtual void RemoteFlightControl::setRoll (int roll) [private], [pure virtual]
- 4.3.2.3 virtual void RemoteFlightControl::setThrottle(int throttle) [private], [pure virtual]
- 4.3.2.4 virtual void RemoteFlightControl::setYaw ( int yaw ) [private], [pure virtual]


The documentation for this class was generated from the following file:

• RemoteFlightControl.h

# 5 File Documentation

# 5.1 RemoteCarControl.cpp File Reference

#include "RemoteCarControl.h"
Include dependency graph for RemoteCarControl.cpp:



**Macros** 

#define \_\_ARDUINO\_LIBRARY\_REMOTE\_CAR\_CONTROL\_CPP\_\_ 1

#### 5.1.1 Macro Definition Documentation

```
5.1.1.1 #define __ARDUINO_LIBRARY_REMOTE_CAR_CONTROL_CPP__ 1
```

Arduino - Remote Car Control.

RemoteCarControl.cpp

**Author** 

Dalmir da Silva dalmirdasilva@gmail.com


Definition at line 10 of file RemoteCarControl.cpp.

# 5.2 RemoteCarControl.cpp

```
00001
00009 #ifndef __ARDUINO_LIBRARY_REMOTE_CAR_CONTROL_CPP_
00010 #define __ARDUINO_LIBRARY_REMOTE_CAR_CONTROL_CPP__ 1
00012 #include "RemoteCarControl.h"
00013
00014 void RemoteCarControl::setThrottle(int throttle) {
00015
         this->throttle = throttle;
00016
          this->apply();
00017 }
00018
00019 void RemoteCarControl::turnLeft() {
00020
       if (this->isForward) {
              this->leftWheel = throttle;
00021
00022
              this->rightWheel = 0;
00023
          } else {
00024
              this->leftWheel = 0;
00025
              this->rightWheel = -(throttle);
00026
00027
          this->apply();
00028 }
00029
00030 void RemoteCarControl::turnRight() {
00031
        if (this->isForward) {
00032
              this->leftWheel = 0:
              this->rightWheel = throttle;
00033
00034
          } else {
00035
              this->leftWheel = -(throttle);
00036
              this->rightWheel = 0;
00037
00038
          this->apply();
00039 }
00040
00041 void RemoteCarControl::stop() {
00042
         this->leftWheel = 0;
00043
          this->rightWheel = 0;
00044
          this->apply();
00045 }
00046
00047 void RemoteCarControl::forward() {
        this->leftWheel = throttle;
00048
00049
          this->rightWheel = throttle;
00050
          this->isForward = 1;
00051
          this->apply();
00052 }
00053
00054 void RemoteCarControl::backward() {
       this->leftWheel = -(throttle);
this->rightWheel = -(throttle);
00055
00056
00057
          this->isForward = 0;
00058
          this->apply();
00059 }
00061 #endif /* __ARDUINO_LIBRARY_REMOTE_CAR_CONTROL_CPP__ */
```

# 5.3 RemoteCarControl.h File Reference

This graph shows which files directly or indirectly include this file:



### Classes


· class RemoteCarControl

# 5.4 RemoteCarControl.h

```
00009 #ifndef __ARDUINO_LIBRARY_REMOTE_CAR_CONTROL_H_
00010 #define __ARDUINO_LIBRARY_REMOTE_CAR_CONTROL_H__ 1
00011
00012 class RemoteCarControl {
00013
00014 protected:
00015
00016
         char isForward;
        int throttle;
int leftWheel;
int rightWheel;
00017
00018
00020
00021 public:
00022
00023
        virtual void apply() = 0;
00024
00025
        void setThrottle(int throttle);
00026
00027
        void stop();
00028
00029
         void forward();
00030
00031
         void backward();
00032
00033
         void turnLeft();
00034
00035
         void turnRight();
00036 };
00037
00038 #endif /* __ARDUINO_LIBRARY_REMOTE_CAR_CONTROL_H__ */
```

# 5.5 RemoteCarRadioControl.cpp File Reference

#include "RemoteCarRadioControl.h"
Include dependency graph for RemoteCarRadioControl.cpp:



#### **Macros**

• #define \_\_ARDUINO\_LIBRARY\_REMOTE\_CAR\_RADIO\_CONTROL\_CPP\_\_ 1

### 5.5.1 Macro Definition Documentation

5.5.1.1 #define \_\_ARDUINO\_LIBRARY\_REMOTE\_CAR\_RADIO\_CONTROL\_CPP\_\_ 1

Arduino - Remote Car Radio Control.

RemoteCarRadioControl.cpp

**Author** 

Dalmir da Silva dalmirdasilva@gmail.com

Definition at line 10 of file RemoteCarRadioControl.cpp.

# 5.6 RemoteCarRadioControl.cpp

```
00001
00009 #ifndef __ARDUINO_LIBRARY_REMOTE_CAR_RADIO_CONTROL_CPP__
00010 #define __ARDUINO_LIBRARY_REMOTE_CAR_RADIO_CONTROL_CPP__ 1
00011
00012 #include "RemoteCarRadioControl.h"
{\tt 00014\ RemoteCarRadioControl::} RemoteCarRadioControl \textbf{(}
      SerialRadioFrequency* serialRadioFrequency,
00015
            int leftForwardPin,
00016
             int leftBackwardPin,
            int rightForwardPin,
00018
            int rightBackwardPin) :
00019
          RemoteCarControl(),
00020
          serialRadioFrequency(serialRadioFrequency) {
            this->leftForwardPin = leftForwardPin;
this->leftBackwardPin = leftBackwardPin;
00021
00022
00023
            this->rightForwardPin = rightForwardPin;
00024
            this->rightBackwardPin = rightBackwardPin;
```


```
00025
            this->throttle = 200;
00026
00027 }
00028
00029 void RemoteCarRadioControl::loop() {
00030
          char cmdBuf[8];
          unsigned char cmdBufPointer = 0;
00031
00032
          char endCommandMark = ';';
00033
          while(true) {
00034
              if (this->serialRadioFrequency->available()) {
                  char c = this->serialRadioFrequency->read();
00035
                  serialRadioFrequency->write(c);
00036
                  if (c == endCommandMark || cmdBufPointer >= 8) {
   if (cmdBufPointer > 1) {
00037
00038
00039
                        parseCommand(cmdBuf, cmdBufPointer);
00040
00041
                       cmdBufPointer = 0;
00042
                  } else {
00043
                      cmdBuf[cmdBufPointer++] = c;
00044
                  }
00045
              }
00046
          }
00047 }
00048
00049 void RemoteCarRadioControl::parseCommand(char* cmdBuf, char
     cmdBufPointer) {
00050
          char action = cmdBuf[cmdBufPointer - 1];
00051
          Serial.println(action);
00052
          switch(action) {
00053
             case 'B':
00054
                  serialRadioFrequency->println("backward");
00055
                  this->backward();
00056
              break;
              case 'F':
00057
00058
                  serialRadioFrequency->println("forward");
00059
                  this->forward();
00060
              break;
case 'S':
00061
00062
                  serialRadioFrequency->println("stop");
00063
                  this->stop();
              break; case 'L':
00064
00065
                 serialRadioFrequency->println("turnLeft");
00066
00067
                  this->turnLeft();
              break;
00068
00069
              case 'R':
00070
                  serialRadioFrequency->println("turnRight");
00071
                  this->turnRight();
00072
              break:
00073
00074
              case 'T':
00075
                  serialRadioFrequency->println("setThrottle");
00076
                  char throttle = cmdBuf[1];
00077
                  this->setThrottle(((int) throttle) | 0xff);
00078
              break;
00079
08000
              default:
00081
                  serialRadioFrequency->println("not recognized");
00082
00083 }
00084
00085 void RemoteCarRadioControl::apply() {
00086
         if (this->leftWheel >= 0) {
00087
              analogWrite(this->leftForwardPin, this->leftWheel);
00088
              analogWrite(this->leftBackwardPin, 0);
00089
          } else {
00090
              analogWrite(this->leftForwardPin, 0);
00091
              analogWrite(this->leftBackwardPin, abs(this->leftWheel));
00092
00093
          if (this->rightWheel >= 0) {
00094
              analogWrite(this->rightForwardPin, this->rightWheel);
00095
              analogWrite(this->rightBackwardPin, 0);
00096
          } else {
00097
              analogWrite(this->rightForwardPin, 0);
              \verb| analogWrite(this->rightBackwardPin, abs(this->rightWheel))|;\\
00098
00099
00100 }
00102 #endif /* __ARDUINO_LIBRARY_REMOTE_CAR_RADIO_CONTROL_CPP__ */
```

### 5.7 RemoteCarRadioControl.h File Reference


#include "SerialRadioFrequency.h"

```
#include "RemoteCarControl.h"
```

Include dependency graph for RemoteCarRadioControl.h:



This graph shows which files directly or indirectly include this file:



### Classes

· class RemoteCarRadioControl


# 5.8 RemoteCarRadioControl.h

```
00001
00009 #ifndef __ARDUINO_LIBRARY_REMOTE_CAR_RADIO_CONTROL_H_
00010 #define __ARDUINO_LIBRARY_REMOTE_CAR_RADIO_CONTROL_H_ 1
00011
00012 #include "SerialRadioFrequency.h" 00013 #include "RemoteCarControl.h"
00014
00015 class RemoteCarRadioControl : public RemoteCarControl {
00016
00017
          SerialRadioFrequency* serialRadioFrequency;
00018
          int leftForwardPin;
00019
          int leftBackwardPin;
00020
          int rightForwardPin;
00021
          int rightBackwardPin;
00022
00023 public:
00024
00025
          RemoteCarRadioControl(SerialRadioFrequency* serialRadioFrequency,
            int leftForwardPin,
00026
00027
              int leftBackwardPin,
00028
               int rightForwardPin,
00029
              int rightBackwardPin);
00030
```

```
00031     virtual void apply();
00032
00033     void parseCommand(char* cmdBuf, char cmdBufPointer);
00034
00035     void loop();
00036 };
00037
00038 #endif /* __ARDUINO_LIBRARY_REMOTE_CAR_RADIO_CONTROL_H__ */
```

# 5.9 RemoteFlightControl.cpp File Reference

#include "RemoteFlightControl.h"
Include dependency graph for RemoteFlightControl.cpp:



# Macros

#define \_\_ARDUINO\_LIBRARY\_REMOTE\_FLIGHT\_CONTROL\_CPP\_\_ 1

# 5.9.1 Macro Definition Documentation

# 5.9.1.1 #define \_\_ARDUINO\_LIBRARY\_REMOTE\_FLIGHT\_CONTROL\_CPP\_\_ 1

Arduino - Remote Flight Control.

RemoteFlightControl.cpp

**Author** 

Dalmir da Silva dalmirdasilva@gmail.com


Definition at line 10 of file RemoteFlightControl.cpp.

# 5.10 RemoteFlightControl.cpp

```
00001
00009 #ifndef __ARDUINO_LIBRARY_REMOTE_FLIGHT_CONTROL_CPP_
00010 #define __ARDUINO_LIBRARY_REMOTE_FLIGHT_CONTROL_CPP_ 1
00011
00012 #include "RemoteFlightControl.h"
00013
00014 RemoteFlightControl::RemoteFlightControl() {}
00015
00015 #endif /* __ARDUINO_LIBRARY_REMOTE_FLIGHT_CONTROL_CPP__ */
```

# 5.11 RemoteFlightControl.h File Reference

This graph shows which files directly or indirectly include this file:



#### Classes

· class RemoteFlightControl

# 5.12 RemoteFlightControl.h

```
00001
00009 #ifndef __ARDUINO_LIBRARY_REMOTE_FLIGHT_CONTROL_H_
00010 #define __ARDUINO_LIBRARY_REMOTE_FLIGHT_CONTROL_H_ 1
00011
00012 class RemoteFlightControl {
00013
00014
        virtual void setThrottle(int throttle) = 0;
00015
00016 virtual void setPitch(int pitch) = 0;
00017
00018
        virtual void setRoll(int roll) = 0;
00019
00020
        virtual void setYaw(int yaw) = 0;
00021 };
00022
00023 #endif /* __ARDUINO_LIBRARY_REMOTE_FLIGHT_CONTROL_H__ */
```

# Index

ARDUINO_LIBRARY_REMOTE_CAR_CONTROL ← CPP	RemoteCarRadioControl, 6 rightBackwardPin, 6
RemoteCarControl.cpp, 8	rightForwardPin, 6
ARDUINO_LIBRARY_REMOTE_CAR_RADIO_C	serialRadioFrequency, 6
ONTROL CPP	RemoteCarRadioControl.cpp, 10
RemoteCarRadioControl.cpp, 10	ARDUINO_LIBRARY_REMOTE_CAR_RADI↔
_ARDUINO_LIBRARY_REMOTE_FLIGHT_CONTR←	O_CONTROL_CPP, 10
OL CPP	RemoteCarRadioControl.h, 11, 12
RemoteFlightControl.cpp, 13	RemoteFlightControl, 6
Tierroter light control opp, To	setPitch, 7
apply	setRoll, 7
RemoteCarControl, 3	setThottle, 7
RemoteCarRadioControl, 6	
Tiemoto carriadio control, c	setYaw, 7
backward	RemoteFlightControl.cpp, 13
RemoteCarControl, 3	ARDUINO_LIBRARY_REMOTE_FLIGHT_C
	ONTROL_CPP, 13
forward	RemoteFlightControl.h, 14
RemoteCarControl, 3	rightBackwardPin
	RemoteCarRadioControl, 6
isForward	rightForwardPin
RemoteCarControl, 4	RemoteCarRadioControl, 6
,	rightWheel
leftBackwardPin	RemoteCarControl, 4
RemoteCarRadioControl, 6	
leftForwardPin	serialRadioFrequency
RemoteCarRadioControl, 6	RemoteCarRadioControl, 6
leftWheel	setPitch
RemoteCarControl, 4	RemoteFlightControl, 7
loop	setRoll
RemoteCarRadioControl, 6	RemoteFlightControl, 7
Tiomoto carriadio control, c	setThrottle
parseCommand	RemoteCarControl, 4
RemoteCarRadioControl, 6	RemoteFlightControl, 7
,	setYaw
RemoteCarControl, 2	RemoteFlightControl, 7
apply, 3	stop
backward, 3	RemoteCarControl, 4
forward, 3	riemote dar dontroi, 4
isForward, 4	throttle
leftWheel, 4	RemoteCarControl, 4
rightWheel, 4	turnLeft
setThrottle, 4	RemoteCarControl, 4
stop, 4	turnRight
•	•
throttle, 4	RemoteCarControl, 4
turnLeft, 4	
turnRight, 4	
RemoteCarControl.cpp, 7, 8	
ARDUINO_LIBRARY_REMOTE_CAR_CONT↔ ROL_CPP, 8	
RemoteCarControl.h, 9	
RemoteCarRadioControl, 4	
apply, 6	
leftBackwardPin, 6	
leftForwardPin, 6	
loop, 6	
parseCommand, 6	