



Assignment -3

**Launch AWS EC2 Ubuntu Instance and
configure the Security Group - Inbound Rule:
8080. Justify the usage of Inbound Rules**


- Click **Launch Instance** and choose instance Name: **ex: server-1**




- Select **AMI: Ubuntu Server 24.04 LTS**



- **Instance Type: t3.micro (Free Tier), Key Pair: Create new or select existing and Launch instance**



- ✓ **Instance State → Running and Click your instance**



- Click Security

The screenshot shows the AWS Management Console for an EC2 instance. The 'Security' tab is selected and highlighted with a purple box. The instance details are as follows:

Instance details Info		
AMI ID	ami-06e3c045d79fd65d9	Monitoring disabled
AMI name	ubuntu/images/hvm-ssd-gp3/ubuntu-noble-24.04-amd64-server-20251212	Allowed image -
Stop protection	Disabled	Launch time Fri Feb 27 2026 13:03:14 GMT+0530 (India Standard Time) (1 minute)
Instance reboot migration	Default (On)	Instance auto-recovery Default
Stop-hibernate behavior	Disabled	AMI Launch index 0
Platform details		Linux/UNIX
Termination protection		Disabled
AMI location		amazon/ubuntu/images/hvm-ssd-gp3/ubuntu-noble-24.04-amd64-server-20251212
Lifecycle		normal
Key pair assigned at launch		key-pair1

- Click Security Group link

The screenshot shows the AWS Management Console for the same EC2 instance. The 'Security' tab is selected. In the 'Security groups' section, the link 'sg-0eacf5d54b04bbf75 (launch-wizard-3)' is highlighted with an orange box. The instance details are as follows:

Instance details		
IMDSv2 Required	Instance ARN	Managed false
Operator -	arn:aws:ec2:us-east-2:040591922284:instance/i-0d51d318630855930	
▼ Security details		
IAM role -	Owner ID	Launch time
	040591922284	Fri Feb 27 2026 13:03:14 GMT+0530 (India Standard Time)
Security groups		
sg-0eacf5d54b04bbf75 (launch-wizard-3)		
▼ Inbound rules		

- Check **Inbound Rules** and Click **Edit inbound rules**

The screenshot shows the AWS Management Console for a security group named 'launch-wizard-3'. The 'Inbound rules' tab is selected, and the 'Edit inbound rules' button is highlighted with an orange box. The console displays the following information:

- Security group name:** launch-wizard-3
- Security group ID:** sg-0eacf5d54b04bbf75
- Description:** launch-wizard-3 created 2026-02-27T07:29:08.556Z
- VPC ID:** vpc-0966f952c1c3f6c0e
- Owner:** 040591922284
- Inbound rules count:** 1 Permission entry
- Outbound rules count:** 1 Permission entry

The 'Inbound rules' table shows one rule:

Name	Security group rule ID	IP version	Type	Protocol
-	sgr-0eae54b07f52fcdc1	IPv4	SSH	TCP

- Click on **Add rule**

The screenshot shows the 'Edit inbound rules' page in the AWS Management Console. The 'Add rule' button is highlighted with a purple arrow. The page displays the following information:

- Security group rule ID:** sgr-0469da3be24e79ead
- Type:** SSH
- Protocol:** TCP
- Port range:** 22
- Source:** Cus... (0.0.0.0/0)
- Description - optional:**

The 'Add rule' button is highlighted with a purple arrow. The 'Delete' button is also visible. The 'Add rule' button is highlighted with a purple arrow.

- ❖ Set **Type** : Custom TCP, **Port** : 8080 and **Source**: 0.0.0.0/0
- ❖ Save rule

Edit inbound rules Info

Inbound rules control the incoming traffic that's allowed to reach the instance.

Security group rule ID	Type	Protocol	Port range	Source	Description - optional	
sgr-0469da3be24e79ead	SSH	TCP	22	Cus...		Delete
-	Custom TCP	TCP	8080	An...	0.0.0.0/0	Delete

[Add rule](#) [Cancel](#) [Preview changes](#) [Save rules](#)

✓ **Configured with Security Group - Inbound Rule: 8080**

Inbound security group rules successfully modified on security group (sg-093e4e5771b6f6d55 | launch-wizard-8)

Details

Owner 040591922284	Inbound rules count 2 Permission entries	Outbound rules count 1 Permission entry
------------------------------	--	---

[Inbound rules](#) [Outbound rules](#) [Sharing](#) [VPC associations](#) [Related resources - new](#) [Tags](#)

Inbound rules (2) [Manage tags](#) [Edit inbound rules](#)

	Name	Security group rule ID	IP version	Type	Protocol
☐	-	sgr-06ab4817569bdc4f3	IPv4	Custom TCP	TCP
☐	-	sgr-0469da3be24e79ead	IPv4	SSH	TCP

Launch AWS EC2 Ubuntu Instance and configured with Security Group - Inbound Rule: 8080

Justification:

-  Inbound rules are used to control and secure incoming traffic to an EC2 instance. They allow access only on required ports (like 22 or 8080) and block unauthorized connections. This ensures both security and proper access to applications running on the server.